

This call changes the mode (attribute) of the specified file.

Syntax

DosSet FileMode (FileName, NewAttribute, Reserved)

Parameters

;FileName (PSZ) - input : Address of the file path name. ;[DosQSysInfo](#) is called by an application during initialization to determine the maximum path length allowed by OS/2. ;NewAttribute (USHORT) - input : File's new attribute. File attributes are defined as follows: 'Bit Description' 15-6 Reserved and must be zero. 5 File archive 4 Subdirectory 3 Volume label 2 System file (excluded from normal directory searches) 1 Hidden file 0 Read only file :These bits may be set individually or in combination. For example, an attribute value of 0021H (bits 5 and 0 set to 1) indicates a read-only file that should be archived. ;Reserved (ULONG) - input : Reserved must be set to zero.

Return Code

rc (USHORT) - return Return code descriptions are: * 0 NO_ERROR * 2 ERROR_FILE_NOT_FOUND * 3 ERROR_PATH_NOT_FOUND * 5 ERROR_ACCESS_DENIED * 26 ERROR_NOT_DOS_DISK * 32 ERROR_SHARING_VIOLATION * 36 ERROR_SHARING_BUFFER_EXCEEDED * 87 ERROR_INVALID_PARAMETER * 108 ERROR_DRIVE_LOCKED * 206 ERROR_FILENAME_EXCED_RANGE

Remarks

Attributes for Volume Label (0008H) and Subdirectory (0010H) cannot be changed using DosSet FileMode. If these attributes are specified, ERROR_INVALID_PARAMETER is returned.

[DosQFileMode](#) is used to query the current settings for file attributes. Calling [DosQFSInfo](#) obtains volume label information.

Attributes of root directories cannot be changed using DosSet FileMode. If these attributes are specified, ERROR_ACCESS_DENIED is returned.

Example Code

C Binding

```
<PRE> #define INCL_DOSFILEMGR  
  
USHORT rc = DosSet FileMode(FileName, NewAttribute, Reserved);  
  
PSZ FileName; /* File path name string */ USHORT NewAttribute; /* New attribute of file */ ULONG 0; /* Reserved (must be zero) */
```

USHORT rc; /* return code */ </PRE>

MASM Binding

<PRE> EXTRN DosSet FileMode: FAR INCL_DOSFILEMGR EQU 1

PUSH@ ASCIIZ FileName ;File path name string PUSH WORD NewAttribute ;New attribute of file PUSH
DWORD 0 ;Reserved (must be zero) CALL DosSet FileMode

Returns WORD </PRE>

Note

Text based on <http://www.edm2.com/index.php/DosSet FileMode>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQFileInfo DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGet HugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://www.osfree.org/doku/> - osFree wiki



Permanent link:
<http://www.osfree.org/doku/doku.php?id=en:docs:fapi:dossetfilemode&rev=1535448548>

Last update: **2018/08/28 09:29**