MVM/DOS personality

This is an infrastructure for running VM's with unmodified OS's

MVM server

The MVM server is a central server of the MVM personality – the infrastructure for running multiple virtual machines on top of L4 microkernel. It is almost separate from OS/2 personality, but can be controlled by OS/2 programs via DosOpenVDD/DosCloseVDD/DosRequestVDD API's.

So, the MVM server exposes some interfaces to other OS personalities to be controlled by them. Also, it starts VM's, which are executed in the context of a VM monitor, running a guest OS (DOS, for example). The VM environment is defined by the VDD's ¹⁾ loaded. The MVM server loads VDD's, which are a kind of plugins. Also, it exports some helper API's for VDD's via MVDM.DLL.

Virtual Device Drivers (VDD's)

A VDD is like a plugin for MVM Server, and it can communicate with outside programs via request API (DosRequestVDD for OS/2 programs). On the other side, from the VM point of view, the VDD emulates some BIOS services/Option ROM's, a hardware devices of guest platform. It installs interrupt handlers, catches I/O ports or MMIO registers accesses from inside the guest OS. A VDD implements its services based on VDD helpers API, served by the MVM server.

Originally, the MV(D)M were used to emulate a 8086 machine with BIOS and DOS/Win 3.1. But now it is a trend for many OS'es to have the kernel virtual machines, like kvm in Linux or VirtualPC in WinNT. Our MVM personality is our solution of the same kind, but it not so monolithic like qemu/kvm – it decomposed to several parts, in best IBM solutions design traditions. The VDD's are like plugins for MVM server, allowing to extend the MVM environment. They're loadable modules (DLL's).

Also, as we're told previously, to share the screen with OS/2 apps and apps of other personalities, IBM created the solution of "Seamless WinOS/2". This is the possibility for Win 3.1 programs to share the same screen with OS/2 PM ones.

This is done with a special VDD's, like VVIDEO (VVGA, VSVGA, etc) implementiing a video mode support in a DOS window (or fullscreen). The DOS window is implemented as a special DLL (pmvdmp.dll) which was loaded by PM. It communicates with a VM via DosRequestVDD and implement the video functions via GPI calls (for windowed mode, so it is a PM application, based on VIO Shield (pmviop.dll), working via BVH drivers, like bvhwndw.dll for windowed OS/2 and DOS sessions, or bvhvga.dll+bvhsvga for fullscreen OS/2 or DOS sessions).

For windowed WinOS/2 sessions, it existed the solution of using a so-called PM shield (seamless.dll) and WinOS/2 shield (winsheld.exe). The 1st one is an "avatar" of Windows application in OS/2 PM world. And vice versa, the WinOS/2 shield is a representative of a PM app in WinOS/2 world.

Also, the second solution exists, based on GRADD video driver model. It works via VVMI (vmanwin.sys in the Intel OS/2). It is the VDD related to the communication of windows video driver (ifgdi2vm.drv for fullscreen, isgdi2vm.drv for seamless mode) with GRADD's VMAN². The special thread in VMAN polls the VVMI driver to communicate with Windows driver. So, the Windows driver is a generic one,

but it communicates with a "real" driver. This results in WinOS/2 and OS/2 PM shared the same screen using access to a common video driver. See the GRADD-related section for more details about multiple graphics engines sharing the same screen/video driver.

Virtual Machine Monitor

The VMM ³⁾ is a program implementing the environment of guest hardware platform, with help of VDD's. It maintains the contexts of all VM's, and handles the traps redirecting them to the needed VDD, loads the IST ⁴⁾ for different processor instruction sets, utilizes the hardware emulation features of the CPU, like VM86, AMD SVM, Intel VT-x etc.

It maintains the address space layout of a VM application, loads a firmware (for BIOS, the SeaBIOS can be used) and DOS emulation kernel.

The DOS emulation kernel (doskrnl)

The DOS emulation kernel is a special rehosted DOS kernel working via OS/2 (or PN ⁵) services. For example, file system API's of int 21h are implemented via OS/2 (or PN) file API's. Access to OS/2 API's done via SVC API (supervisor call?) which is trap of HLT instruction followed by call number and inverted call number. Also DOSKRNL provides MVM specific API for DOS applications.

Instruction Set Translator (IST)

The IST is a DLL, emulating the instructions of Guest hardware via Host CPU instructions. It exports a set of entry points, each corresponding the emulated instruction.

The similar component exist in QEMU – but it is linked statically with the emulator binary.

VM86 on Intel, and Hardware-assisted virtualization

Some processors implement special compatibility modes (VM86 allows creation of special task in protected mode, which emulates a virtual i8086 processor) or special instruction to assist the Virtual Machine Monitors creation. (Like "hypercall" to change context to a hypervisor, to execute its service and exit "hypervisor" mode). Also, the very new processors implement the IOMMU (a hardware support for sharing a hardware).

These extensions can be used to run unmodified OS'es on top of a hypervisor (it is supported in newer versions of Xen, VBox, VMWare, VPC).

Microkernels as Hypervisors

Microkernels and Hypervisors are very similar things. Microkernels implement similar features. For example, the Fiasco.OC microkernel supports SVM and VT-x and allows to run unmodified Linux in very thin VM's. This feature can be utilized in our MVM personality too.

SVC API

Superviser calls API aimed to call host services from VM.

0 Image: Constant of the second	Ordinal	Description
2Terminate VDM and return code to parent process from AX3	0	
2Terminate VDM and return code to parent process from AX3	1	
3	2	Terminate VDM and return code to parent process from AX
4Image: style st		
5 Image: Set DTA from DS:DX 8 Image: Set DTA from DS:DX 9 Image: Set DTA from DS:DX 10 Image: Set DTA from DS:DX 11 Image: Set DTA from DS:DX 12 Image: Set DTA from DS:DX 13 Image: Set DTA from DS:DX 14 Image: Set DS:DX → unopened FCB ES → environment segment BS 15 Image: Set DS:DX → unopened FCB ES → environment segment BS 16 Image: Set DS:DX → unopened FCB ES → environment segment BS 17 Image: Set DS:DX → unopened FCB ES → environment segment BS 18 Image: Set DS:DX → unopened FCB ES → environment segment BS 19 Image: Set DS:DX → unopened FCB ES → environment segment BS 10 Image: Set DS:DX → unopenet FCB ES → environment segment BS 11 Image: Set DS:DX → unopenet FCB ES → environment Segment BS 11 Image: Set DS:DX → unopenet FCB ES → environment Segmet BS 12		
67Set DTA from DS:DX899101111121314151617181920212223242526272829Delete file using FCB DS:DX → unopened FCB ES → environment segment303134353637383939		
7 Set DTA from DS:DX 8 9 9 9 10 9 11 9 12 9 13 9 14 9 15 9 16 9 17 9 18 9 19 9 20 9 21 9 22 9 23 9 24 9 25 9 26 9 27 9 28 9 29 Delete file using FCB DS:DX → unopened FCB ES → environment segment 30 9 31 9 32 9 33 9 34 9 35 9 36 9 37 9 38 9 39 9		
8		Set DTA from DS:DX
9	8	
10		
11 Image: I		
12		
13 Image: Constraint of the second of t		
14 Image: style st		
15 Image: style st		
16		
17 Image:		
18		
19		
20		
21		
2223232424252627282929Delete file using FCB DS:DX \rightarrow unopened FCB ES \rightarrow environment segment303131313233343536373839		
2323242425252627272829Delete file using FCB DS:DX \rightarrow unopened FCB ES \rightarrow environment segment303131323334343536373839		
24		
25		
26 27 27 28 28 29 Delete file using FCB DS:DX → unopened FCB ES → environment segment 30 31 31 32 32 33 33 34 35 35 36 37 38 39		
272829Delete file using FCB DS:DX → unopened FCB ES → environment segment3031313233343536373839		
282829Delete file using FCB DS:DX → unopened FCB ES → environment segment3031313232333334343536373839		
29Delete file using FCB DS:DX → unopened FCB ES → environment segment30313132323333343435363637383939		
30		Delete file using FCB DS:DX \rightarrow unopened FCB ES \rightarrow environment segment
31		
32 33 34 35 36 37 38 39		
33 33 34 35 35 36 36 37 38 39		
34		
35		
36		
37 38 39		
38 39		
39		
	40	

mvm

3/5

Ordinal	Description
41	
42	
43	
44	Set VERIFY flag from AL
45	
46	
47	
48	
49	
50	
51	
52	
53	
54	
55	
56	
57	
58	
59	
60	
61	
62	
63	
64	
65	
66	
67	
68	
69	
70	
71	
72	
73	
74	
75	
76	
77	
78	
79	
80	
81	
82	
83	
84	
85	

1)

Virtual Device Drivers ²⁾ Video Manager ³⁾ Virtual Machine Monitor ⁴⁾ Instruction Set Translator ⁵⁾ Personality Neutral

From: http://www.osfree.org/doku/ - **osFree wiki**

Permanent link: http://www.osfree.org/doku/doku.php?id=en:docs:general:mvm&rev=1700910790

Last update: 2023/11/25 11:13



mvm