



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

MouSetDevStatus

This call sets the mouse device driver status flags for the installed mouse device driver.

Syntax

```
MouSetDevStatus (DeviceStatus, DeviceHandle)
```

Parameters

- DeviceStatus (USHORT) - input : Address of the desired status flag settings.

The passed parameter is a 2-byte set of flags. Only the high-order byte has meaning.

Bit	Description
15-10	Reserved, set to zero.
9	Set if mouse device is to return data in mickeys.
8	Set if the drawing operations for the pointer draw routine are to be disabled.
7-0	Reserved, set to zero.

- DeviceHandle (HMOU) - input : Handle of the mouse device from a previous MouOpen.

Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO_ERROR
- 385 ERROR_MOUSE_NO_DEVICE
- 387 ERROR_MOUSE_INV_PARMS
- 466 ERROR_MOU_DETACHED
- 501 ERROR_MOUSE_NO_CONSOLE
- 505 ERROR_MOU_EXTENDED_SG

Remarks

MouSetDevStatus is the complement to MouGetDevStatus. However, not all status flags may be set with MouSetDevStatus. Only the flags corresponding to the following functions may be modified:

- Return data in mickeys.

Normally, mouse data is returned to the application with the absolute display mode coordinates of the pointer image position on the display screen. By setting this status flag, mouse data is returned in relative mickeys, a unit of mouse movement.

- Don't call pointer draw device.

Normally, the pointer draw device driver is called for all drawing operations. By setting this status flag, the mouse device driver does not call the pointer draw device driver. The application must draw any required pointer image on the screen.

Bindings

C

```
#define INCL_MOUSE

USHORT rc = MouSetDevStatus(DeviceStatus, DeviceHandle);

PUSHORT DeviceStatus; /* Status flags */
HMOU DeviceHandle; /* Mouse device handle */

USHORT rc; /* return code */
```

MASM

```
EXTRN MouSetDevStatus:FAR
INCL_MOUSE EQU 1

PUSH@ WORD DeviceStatus ;Status flags
PUSH WORD DeviceHandle ;Mouse device handle
CALL MouSetDevStatus

Returns WORD
```

From:

<https://www.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://www.osfree.org/doku/doku.php?id=en:docs:fapi:mousetdevstatus&rev=1634201380>

Last update: **2021/10/14 08:49**

