



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## VioModeUndo

This call allows one thread within a process to cancel a [VioModeWait](#) issued by another thread within the same process.

### Syntax

```
VioModeUndo (OwnerIndic, KillIndic, Reserved)
```

### Parameters

- OwnerIndic (USHORT) - input : Indicates whether the thread issuing VioModeUndo wants ownership of VioModeWait to be reserved for its process.
  - 0 - Reserve ownership
  - 1 - Give up ownership
- KillIndic (USHORT) - input : Indicates whether the thread (with the outstanding VioModeWait) should be returned an error code or be terminated.
  - 0 - Return error code
  - 1 - Terminate thread
- Reserved (USHORT) - input : Reserved word of 0s.

### Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO\_ERROR
- 421 ERROR\_VIO\_INVALID\_PARMS
- 422 ERROR\_VIO\_FUNCTION\_OWNED
- 427 ERROR\_VIO\_NO\_MODE\_THREAD
- 430 ERROR\_VIO\_ILLEGAL\_DURING\_POPUP
- 465 ERROR\_VIO\_DETACHED
- 486 ERROR\_VIO\_BAD\_RESERVE
- 494 ERROR\_VIO\_EXTENDED\_SG

## Remarks

VioModeUndo may be issued only by a thread within the process that owns VioModeWait. The thread issuing VioModeUndo can either reserve ownership of the VioModeWait function for its process or give up ownership. The thread whose VioModeWait is cancelled is optionally terminated.

## Bindings

### C

```
#define INCL_VIO

USHORT rc = VioModeUndo(OwnerIndic, KillIndic, Reserved);

USHORT OwnerIndic;    /* Ownership indicator */
USHORT KillIndic;     /* Terminate indicator */
USHORT Reserved;      /* Reserved (must be zero) */

USHORT rc;            /* return code */
```

### MASM

```
EXTRN VioModeUndo:FAR
INCL_VIO EQU 1

PUSH WORD OwnerIndic ;Ownership indicator
PUSH WORD KillIndic ;Terminate indicator
PUSH WORD Reserved ;Reserved (must be zero)
CALL VioModeUndo

Returns WORD
```

[http://www.edm2.com/index.php/VioModeUndo\\_\(OS/2\\_1.x\)](http://www.edm2.com/index.php/VioModeUndo_(OS/2_1.x))

From:  
<https://www.osfree.org/doku/> - **osFree wiki**

Permanent link:  
<https://www.osfree.org/doku/doku.php?id=en:docs:fapi:viomodeundo&rev=1634194393>

Last update: **2021/10/14 06:53**

