osFree Classic REXX Interpreter

Version 3.9.6

Original Authors:

- Mark Hessling < mark@rexx.org>
- Florian Große-Coosmann < florian@grosse-coosmann.de>
- Anders Christensen < Anders.Christensen@idi.ntnu.no>

Regina Home Page at: http://regina-rexx.sourceforge.net

- Copyright © 1992-1998 Anders Christensen
- Copyright © 1998-2022 Mark Hessling

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation; with no Invariant Sections, with no Front-Cover Texts, and with no Back-Cover Texts.

A copy of the license is included in the section entitled "GNU Free Documentation License".

Introduction to REXX

This chapter provides an introduction to osFree Classic REXX, an Open Source REstructured eXtended eXecutor (REXX) Interpreter distributed under the GNU General Library License.

Purpose of this document

The purpose of this document is to provide an overview of the REXX Language and the osFree Classic REXX implementation of the REXX Language. It is not intended as a definitive reference to REXX; you should really have a copy of the REXX "bible"; The REXX Language, by Mike Cowlishaw [TRL2].

Implementation

The osFree Classic REXX Interpreter is implemented as a library suitable for linking into third-party applications. Access to osFree Classic REXX from third-party applications is via the REXX API, which is consistent with the IBM's REXX SAA API. This API is implemented on most other REXX interpreters.

The osFree Classic REXX distribution also includes a front end to the osFree Classic REXX library, to enable the execution of REXX programs directly from the command line. The command line referred to the a OS/2 command window.

Last update: 2024/09/04 06:58

Executing REXX programs with osFree Classic REXX

REXX programs are generally executed by osFree Classic REXX from the command line in the following manner:

program.cmd [program parameters]

where:

- program the name of the REXX program to be executed. Program source code must be started from comment /* */.
- program parameters any optional parameters to be passed to the REXX program.

Another way is following command line:

rexx [switches] [program] [program parameters]

where:

- rexx is the name of the osFree Classic REXX executable
- switches are optional switches. See the section below for an explanation of the switches currently supported by osFree Classic REXX
- program the name of the REXX program to be executed. See the section External REXX
 Programs, below, for details on how osFree Classic REXX interprets this argument. If no program
 name is specified, osFree Classic REXX waits for REXX commands to be typed in and will
 execute those commands when the appropriate end-of-file character is typed.
- program parameters any optional parameters to be passed to the REXX program.

The special processing done by osFree Classic REXX to find the file name in REGINA_MACROS and the file extension searching is ignored for the program to be run when using the magic number method of invocation, but is still done inside the program when using CALL.

Switches

The following switches allow the user to control how osFree Classic REXX executes the supplied REXX program. Switches are recognised by either a leading hyphen character; '-', followed immediately by a single alphabetic character, or the full switch name preceded by two hyphen characters. Some switches allow for optional parameters. These, too must follow the switch without any intervening spaces. All switches and their optional parameters are case-sensitive. Single character switches that take no option can be combined. e.g. "-arp"

```
-t[trace char]
--trace[=trace char]
```

Turn on the specified tracing level. The optional trace char indicates the tracing level to be used. See the TRACE command later in this document for an explanation of each trace level. Use of this switch will result in any TRACE commands in the program to be ignored. Default trace char is A.

-i[trace char]

--interactive[=trace char]

Same as -trace switch above but sets tracing to be interactive

```
-a
--args
```

Without this switch, all command line parameters are passed to osFree Classic REXX as a single argument. Specifying -a, ensures that the REXX program invoked has access to the command line parameters as separate arguments, as passed from the command line interpreter. i.e. The BIF ARG() can return a value of other than 1 or 0. Also PARSE SOURCE will return SUBROUTINE instead of the normal COMMAND value.

```
-r
--restricted
```

Run osFree Classic REXX in restricted mode. See the section on osFree Classic REXX Restricted Mode for more details.

```
-v[a|b|v|]
--version[=a|b|v]
```

Displays the version information for the executable run. The string displayed is the same that is returned by PARSE SOURCE followed by the processor architecture bits. The version string provides an indicator as to whether the osFree Classic REXX library is thread-safe or not. If the first word ends in"(MT)", then the library is thread-safe. This switch, executed by the static executable, will always result in no"(MT)"indicator.

Options:

- a displays location of osFree Classic REXX's ADDONS directory
- b number of bits osFree Classic REXX is complied with; eg 32 or 64 v numeric version; eg 3.9.3

```
-l[locale]
--locale[=locale]
```

Indicates which national locale that osFree Classic REXX is to use for BIFs like TRANSLATE, LOWER, or UPPER. No validation is done on the specified locale. The affected behaviour is defined in Section 2; "Native Language Support".

The locale is passed to the underlying C library, which resolves the describer in a system specific way. An omitted locale lets the system choose the current pre-selected locale for the user. This is the usual option a user would choose. "-I" without a locale, works best for most users who decided to use locale support. Error messages can be selected by another scheme using an environment variable, see Section 10.2; Native Language Support; this variable can be used to select a locale, too.

The text of the locale is equivalent to those of the environment variables LANG or LC_CTYPE or the value used in registries, etc. Examples are en_US.ISO-8859-1 or English_USA.1252 for some systems.

-oOPTIONS

Last update: 2024/09/04 06:58

--options=OPTIONS

This switch specifies the values of OPTIONS to set. This is a string of words in the same format as the OPTIONS instruction. This switch overwrites REGINA_OPTIONS Environment variable.

```
-p
--pause
```

This switch causes osFree Classic REXX to pause on exit. This switch is useful if you run REXX programs from a GUI file manager and want to see the output from that program before the console window closes.

```
-c
--compile
```

Compile the specified program into a tokenised format. The only program parameters when using this switch is the filename for the tokenised program. i.e. rexx -c program filename

```
-e
--execute
```

Execute the specified program from a tokenised format. program must be a file created by the -c switch. All other switches and program parameters are allowed except -c.

External REXX programs

osFree Classic REXX searches for REXX programs, using a combination of the REGINA_MACROS environment variable, the PATH environment variable, the REGINA_SUFFIXES environment variable and the addition of filename extensions. This rule applies to both external function calls within a REXX program and the program specified on the command line.

First of all we process the environment variable REGINA_MACROS. If no file is found we proceed with the current directory and then with the environment variable PATH. The semantics of the use of REGINA_MACROS and PATH are the same, and the search in the current directory is omitted for the superuser on Unix systems for security reasons. The current directory must be specified explicitly by the superuser.

When processing an environment variable, the content is split into the different paths and each path is processed separately. Note that the search algorithm to this point is ignored if the program name contains a file path specification. eg. if "CALL .\MYPROG" is called, then no searching of REGINA_MACROS or PATH is done; only the concatenation of suffixes is carried out.

For each file name and path element, a concatenated file name is created. If a known file extension is part of the file name only this file is searched, otherwise the file name is extended by the extensions "" (empty string), ".rexx", ".rex", ".cmd", and ".rx" in this order. The file name case is ignored.

The first matching file terminates the whole algorithm and the found file is returned.

The environment variable REGINA_SUFFIXES extends the list of known suffixes as specified above, and is inserted after the empty extension in the process. REGINA_SUFFIXES has to contain a space or

comma separated list of extensions, a dot in front of each entry is allowed,

e.g. ".macro,.mac,.regina" or "macro mac regina"

Note that it is planned to extend the list of known suffixes by ".rxc" in version 3.4 to allow for seamless integration of pre-compiled macros.

Example: Locating an external REXX program for execution

Assume you have a call to an external function, and it is coded as follows:

```
Call myextfunc arg1, arg2
```

Assume also that the file myextfunc.cmd exists in the directory \os2\, and that PATH=C:\OS2\APPS;C:\OS2, REGINA MACROS is not set, and REGINA SUFFIXES=.macro.

The files that osFree Classic REXX will search for in order are:

```
.\myextfunc
.\myextfunc.macro
.\myextfunc.rexx
.\myextfunc.rex
.\myextfunc.cmd
.\myextfunc.rx
```

```
C:\0S2\APPS\myextfunc
C:\0S2\APPS\myextfunc.macro
C:\0S2\APPS\myextfunc.rexx
C:\0S2\APPS\myextfunc.rex
C:\0S2\APPS\myextfunc.cmd
C:\0S2\APPS\myextfunc.rx
```

```
C:\0S2\myextfunc
C:\0S2\myextfunc.macro
C:\0S2\myextfunc.rexx
C:\0S2\myextfunc.rex
C:\0S2\myextfunc.cmd /* found!! terminate search*/
```

REXX Language Constructs

In this chapter, the concept and syntax of REXX clauses are explained. At the end of the chapter there is a section describing how osFree Classic REXX differs from standard REXX as described in the first part of the chapter.

Definitions

A program in the REXX language consists of clauses, which are divided into four groups: null clauses,

commands, assignments, and instructions. The three latter groups (commands, assignments, and instructions) are collectively referred to as statements. This does not match the terminology in [TRL2], where "instruction" is equivalent to what is known here as "statement", and "keyword instruction" is equivalent to what is known here as "instruction". However, I find the terminology used here simpler and less confusing.

Incidentally, the terminology used here matches [DANEY].

A clause is defined as all non-clause-delimiters (i.e. blanks and tokens) up to and including a clause delimiter. A token delimiter can be:

An end-of-line, unless it lies within a comment, or the last token on a line is the line continuation character; comma. An end-of-line within a constant string is considered a syntax error {6}.

A semicolon character that is not within a comment or constant string.

A colon character, provided that the sequence of tokens leading up to it consists of a single symbol and whitespace. If a sequence of two symbol tokens is followed by a colon, then this implies SYNTAX condition {20}.

Some systems have the ability to store a text file having a last line unterminated by an end-of-line character sequence. In general, this applies to systems that use an explicit end-of-line character sequence to denote end-of-lines, e.g. Unix and MS-DOS systems. Under these systems, if the last line is unterminated, it will strictly speaking not be a clause, since a clause must include its terminating clause delimiter. However, some interpreters are likely to regard the end-of-file as a clause delimiter too. The functionality of INTERPRET gives some weight to this interpretation. But other systems may ignore that last, unterminated line, or maybe issue a syntax error. (However, there is no SYNTAX condition number adequately covering this situation.

Example: Binary transferring files

Suppose a REXX program is stored on an MS-DOS machine. Then, an end-of-line sequence is marked in the file as the two characters carriage return and newline. If this file is transferred to a Unix system, then only newline marks the end-of-line. For this to work, the file must be transferred as a text file. If it is (incorrectly) transferred as a binary file, the result is that on the Unix system, each line seems to contain a trailing carriage return character. In an editor, it might look like this:

```
say 'hello world'^M
say 'that"s it'^M
```

This will probably raise SYNTAX condition {13}.

Tokens

The fundamental building block of a REXX clause is a token. Tokens can be split into a number of different types; Literal Strings, Hexadecimal Strings, Binary Strings, Symbols, Operators and Special Characters.

Literal String

Any characters enclosed in single or double quotes is treated as a literal string; no interpretation of the contents is done. A literal string with no characters (ie two adjacent single or double quotes) is the null string. To include a single or double quote inside a literal string, either use the other quote character as the string delimiter or specify two adjacent quote characters to indicate a single, embedded quote.

Examples: Literal String

```
'def'
"Mary"
"I'm a string"
'I''m a "valid" string'
'' → null string
```

Hexadecimal String

Any hexadecimal (0-9, a-f, A-F) characters, grouped in pairs, enclosed in single or double quotes and immediately followed by 'x' or 'X' is interpreted as a hexadecimal string. (The "X" is outside of the quotes). If the first group has an odd number of characters, a zero is prepended.

Examples: Hexadecimal String

```
'0def'x "01 02 03"X
'123 45'x \rightarrow same as '01 23 45'x
```

Binary String

Any binary (0 or 1) characters, grouped in fours, enclosed in single or double quotes and immediately followed by 'b' or 'B' is interpreted as a binary string. (The "B" is outside of the quotes). If the first group has an odd number of characters, a zero is prepended. If the number of groups is an odd number, a group of 4 zeros (0000) is prepended.

Examples: Binary String

```
'11011101'b
"1111 0101 0001 1000"B
'111 0101 1010'b → same as '0000 0111 0101 1010'b
```

Symbol

A symbol contains a number of characters in the set of A-Z, a-z, 0-9 and other special characters; "._!?\$#@". Lower case characters are converted to upper case before being used by the interpreter.

Examples: Symbol

```
joe a.Br.3 @xyz!
```

Operators

The full list and definition of Operators are specified in section 2.5 Operators.

Special Characters

The characters in the table below have special significance in REXX's syntax. They also delimit tokens.

```
: Identifies the termination of a label
; Indicates the end of a clause
( Opening character for precedence grouping. Also used to specify the start
of a group of arguments to a function call.
) Closing character for precedence grouping. Also used to specify the end of
a group of arguments to a function call.
, Line continuation character
```

Null clauses

Null clauses are clauses that consist of only whitespace, or comments, or both; in addition to the terminating clause delimiter. These clauses are ignored when interpreting the code, except for one situation: null clauses containing at least one comment is traced when appropriate. Null clauses not containing any comments are ignored in every respect.

Example: Tracing comments

The tracing of comments may be a major problem, depending on the context. There are basically two strategies for large comments: either box multiple lines as a single comment, or make the text on each line an independent comment, as shown below:

```
/*
This is a single, large comment, which spans multiple lines.
Such comments are often used at the start of a subroutine or similar, in order to describe both the interface to and the functionality of the function.
*/

/* This is also a large comment, but it is written as */
/* multiple comments, each on its own line. Thus, these */
/* are several clauses while the comment above is a */
/* single comment. */

-- These lines also consist of multiple comments, and thus
```

```
-- multiple clauses. This form of comment was introduced
-- in Regina 3.4
```

During tracing, the first of these will be displayed as one large comment, and during interactive tracing, it will only pause once. The second will be displayed as multiple lines, and will make several pauses during interactive tracing. An interpreter may solve this situation in several ways, the main objective must be to display the comments nicely the to programmer debugging the code.

Preferably, the code is shown in a fashion that resembles how it is entered in the file.

If a label is multiple defined, the first definition is used and the rest are ignored. Multiple defined labels is not an SYNTAX condition.

A null clause is not a statement. In some situations, like after the THEN subclause, only a statement is expected. If a null clause is provided, then it is ignored, and the next statement is used instead.

Consider the following code:

```
parse pull foo if foo=2 then
say 'foo is not 2'
else
/* do nothing */ say 'that"s it'
```

This will not work the way indentation indicates, since the comment in this example is not a statement. Thus, the ELSE reads beyond the comment, and connects to the SAY instruction which becomes the ELSE part. (That what probably not what the programmer intended.) This code will say that's it, only when foo is different from 2. A separate instruction, NOP has been provided in order to fill the need that was inadequately attempted filled by the comment in the code fragment above.

Example: Trailing comments

The effect that comments are not statements can be exploited when documenting the program, and simultaneously making the program faster. Consider the following two loops:

```
sum = 0
do i=1 to 10
/* sum 1 2 3 ... 8 9 10 */ sum = sum + i
end

sum = 0
do i=1 to 10
sum = sum + i /* sum 1 2 3 ... 8 9 10 */
end
```

In the first loop, there are two clauses, while the second loop contains only one clause, because the comment is appended to an already existing clause. During execution, the interpreter has to spend time ignoring the null clause in the first loop, while the second loop avoids this problem (assuming tracing is not enabled). Thus, the second loop is faster; although only insignificantly faster for small loops. Of course, the comment could have been taken out of the loop, which would be equally fast to the second version above.

Commands

Last update: 2024/09/04 06:58

Assignments

Assignments are clauses where the first token is a symbol and the second token is the equal sign (=). This definition opens for some curious effects, consider the following clauses:

```
a == b
```

This is not a command, but an assignment of the expression = b to the variable a. Of course, the expression is illegal (=b) and will trigger a SYNTAX condition for syntax error

 $\{35\}$. TRL2 defines the operator == as consisting of two tokens. Thus, in the first of these examples, the second token is =, the third token is also =, while the fourth token is b.

```
3 = 5
```

This is an assignment of the value 5 to the symbol 3, but since this is not a variable symbol, this is an illegal assignment, and will trigger the SYNTAX condition for syntax error {31}.

```
"hello" = foo
```

This is not an invalid assignment, since the first token in the clause is not a symbol. Instead, this becomes a command.

```
arg =(foo) bar
```

The fourth statement is a valid assignment, which will space-concatenate the two variable symbols foo and bar, and assign the result to the variable symbol arg. It is specifically not an ARG instruction, even though it might look like one. If you need an ARG instruction which template starts with an absolute indirect positional pattern, use the PARSE UPPER ARG instruction instead, or prepend a dot in front of the template.

An assignment can assign a value to a simple variable, a stem variable or a compound variable. When assigning to a stem variable, all possible variable symbols having that stem are assigned the value. Note specifically that this is not like setting a default, it is a one time multiple assignment.

Example: Multiple assignment

The difference between REXX's multiple assignment and a default value can be seen from the following code:

```
foo. = 'bar' foo.1 = 'baz' drop foo.1
say foo.1 /* says "F00.1" */
```

Here, the SAY instruction writes out FOO.1, not bar. During the DROP instruction, the variable FOO.1 regains its original, uninitialized value FOO.1, not the value of its stem variable FOO., i.e. bar, because stem assignments does not set up a default.

Example: Emulating a default value

If you want to set the compound variable to the value of its stem variable, if the stem is initialized, then you may use the following code:

```
if (symbol('foo.')) then foo.1 = foo.
else
drop foo.1
```

In this example, the FOO.1 variable is set to the value of its stem if the stem currently is assigned a value. Else, the FOO.1 variable is dropped.

However, this is probably not exactly the same, since the internal storage of the computer is likely to store variables like FOO.2 and FOO.3 only implicitly (after all, it can not explicitly store every compound having FOO. as stem). After the assignment of the value of FOO. to FOO.1, the FOO.1 compound variable is likely to be explicitly stored in the interpreter.

There is no way you can discover the difference, but the effects are often that more memory is used, and some functionality that dumps all variables may dump FOO.1 but not FOO.2 (which is inconsistent). See section RexxVariablePool.

Example: Space considerations

Even more strange are the effects of the following short example:

```
foo. = 'bar' drop foo.1
```

Although apparently very simple, there is no way that an interpreter can release all memory referring to FOO.1. After all, FOO.1 has a different value than FOO.2, FOO.3, etc., so the interpreter must store information that tells it that FOO.1 has the uninitialized value.

These considerations may seem like nit-picking, but they will matter if you drop lots of compound variables for a stem which has previously received a value. Some programming idioms do this, so be aware. If you can do without assigning to the stem variable, then it is possible for the interpreter to regain all memory used for that stem's compound variables.

Instructions

In this section, all instructions in standard REXX are described. Extensions are listed later in this chapter.

First some notes on the terminology. What is called an instruction in this document is equivalent to a "unit" of clauses. That is, each instruction can consist of one or more clauses. For instance, the SAY instruction is always a single instruction, but the IF instruction is a multi-clause instruction. Consider the following script, where each clause has been boxed:

```
if a=b then
say 'hello' else
say 'bye'
```

Last update: 2024/09/04 06:58

Further, the THEN or ELSE parts of this instruction might consist of a DO/END pair, in which case the IF instruction might consists of an virtually unlimited number of clauses.

Then, some notes on the syntax diagrams used in the following descriptions of the instructions. The rules applying to these diagrams can be listed as:

Anything written in courier font in the syntax diagrams indicates that it should occur as-is in the REXX program. Whenever something is written in italic font, it means that the term should be substituted for another value, expression, or terms.

Anything contained within matching pairs of square brackets ([...]) are optional, and may be left out.

Whenever a pair of curly braces is used, it contains two or more subclauses that are separated by the vertical bar (|). It means that the curly braces will be substituted for one of the subclauses it contains.

Whenever the ellipsis (...) is used, it indicates that the immediately preceding subclauses may be repeated zero or more times. The scope of the ellipsis is limited to the contents of a set of square brackets or curly braces, if it occurs there.

Whenever the vertical bar | is used in any of the syntax diagrams, it means that either the term to the left, or the term to the right can be used, but not both, and at least one of the must be used. This "operator" is associative (can be used in sequence), and it has lower priority than the square brackets (the scope of the vertical bar located within a pair of square brackets or curly braces is limited to the text within those square brackets or curly braces.

Whenever a semicolon (;) is used in the syntax diagram, it indicates that a clause separator must be present at the point. It may either be a semicolon character, or an end-of-line.

Whenever the syntax diagram is spread out over more lines, it means that any of the lines can be used, but that the individual lines are mutually exclusive. Consider the syntax:

```
SAY symbol string
```

This is equivalent to the syntax:

```
SAY [symbol | string ]
```

Because in the first of these two syntaxes, the SAY part may be continued at either line.

Sometimes the syntax of an instruction is so complex that parts of the syntax has been extracted, and is shown below in its expanded state. The following is an example of how this looks:

```
SAY something TO someone something : = HI
HELLO BYE
someone : = THE BOSS YOUR NEIGHBOR
```

You can generally identify these situations by the fact that they comes a bit below the real syntax diagram, and that they contains a colon character after the name of the term to be expanded.

In the syntax diagrams, some generic names have been used for the various parts, in order to indicate common attributes for the term. For instance, whenever a term in the syntax diagrams is

called expr, it means that any valid REXX expression may occur instead of that term. The most common such names are:

condition

Indicates that the subclause can be any of the names of the conditions, e.g. SYNTAX, NOVALUE, HALT, etc.

expr

Indicates that the subclause can be any valid REXX expression, and will in general be evaluated as normal during execution.

statement

Indicates that extra clauses may be inserted into the instruction, and that exactly one of them must be a true statement.

string

Indicates that the subclause is a constant string, i.e. either enclosed by single quotes ('...') or double quotes ("...").

symbol

Indicates that the subclause is a single symbol. In general, whenever symbol is used as the name for a subclause, it means that the symbol will not automatically be expanded to the value of the symbol. But instead, some operation is performed on the name of the symbol.

template

Indicates that the subclause is a parsing template. The exact syntax of this is explained in a chapter on tracing, to be written later.

In addition to this, variants may also exist. These variants will have an extra letter or number appended to the name of the subclause, and is used for differing between two or more subclauses having the same "type" in one syntax diagram. In the case of other names for the subclauses, these are explained in the description of the instruction.

The ADDRESS Instruction

```
ADDRESS [ environment [ command ] [ redirection ] ] ; [ [ VALUE ] expr [ redirection ] ] ; redirection : = WITH input_redir [output_redir] [error_redir] WITH input_redir [error_redir] [output_redir] WITH output_redir [input_redir] [error_redir] WITH output_redir [error_redir] [input_redir] WITH error_redir [input_redir] WITH error_redir [output_redir] wITH error_redir [output_redir] input_redir : = INPUT NORMAL INPUT [ NOEOL ] io
```

```
output_redir : = OUTPUT NORMAL OUTPUT [ APPEND | REPLACE ] io
error_redir : = ERROR NORMAL
ERROR [ APPEND | REPLACE ] io
io : = { STREAM | STEM | LIFO | FIFO } symbol
{ STREAM | LIFO | FIFO } string
```

We will discuss redirection later.

The ADDRESS instruction controls where commands to an external environment are sent. If both environment and command are specified, the given command will be executed in the given environment. The effect is the same as issuing an expression to be executed as a command (see section Commands), except that the environment in which it is to be executed can be explicitly specified in the ADDRESS clause. In this case, the special variable RC will be set as usual, and the ERROR or FAILURE conditions might be raised, as for normal commands. Starting with Regina 3.0 the special variables .RC and .RS are set too, according to the ANSI standard.

In other words: All normal commands are ADDRESS statements with a suppressed keyword and environment.

The environment term must be a symbol or a literal string. If it is a symbol, its "name" is used, i.e. it is not tail substituted or swapped for a variable value. The command and expression terms can be any REXX expression. eg.

```
SYSTEM='PATH'
ADDRESS SYSTEM "echo Hello"
```

is equivalent to a plain

```
ADDRESS SYSTEM "echo Hello"
```

or

```
ADDRESS "SYSTEM" "echo Hello"
```

for the external echo command.

A symbol specified as an environment name isn't case-sensitive, whereas a string must match the case. Built-in environments are always uppercased.

REXX maintains a list of environments, the size of this list is at least two. If you select a new environment, it will be put in the front of this list. Note that if command is specified, the contents of the environment stack is not changed. If you omit command, environment will always be put in the front of the list of environments. Regina has an infinite list and never pushes out any entry.

Possible values are listed below. If you supply a command with the ADDRESS statement, the environment is interpreted as a temporary change for just this command.

What happens if you specify an environment that is already in the list, is not completely defined. Strictly speaking, you should end up with both entries in the list pointing to the same environment, but some implementations will probably handle this by reordering the list, leaving the selected environment in the front. This is Regina's behavior. Every environment exists only once. The redirection command below always changes the behavior of one – the given – environment. You can

imagine a set of playing cards in your hand. The operation is to draw one card by name and put it to the front.

If you do not specify any subkeywords or parameters to ADDRESS, the effect is to swap the two first entries in the list of environments. Consequently, executing ADDRESS multiple times will toggle between two environments.

The second syntax form of ADDRESS is a special case of the first form with command omitted. If the first token after ADDRESS is VALUE, then the rest of the clause is taken to be an expression, naming the environment which is to be made the current environment. Using VALUE makes it possible to circumvent the restriction that the name of the new environment must be a symbol or literal string. However, you can not combine both VALUE and command in a single clause.

Example: Examples of the ADDRESS instruction

Let's look at some examples, they can sometimes be combined with a redirection:

```
ADDRESS COMMAND
ADDRESS SYSTEM 'copy' fromfile tofile
ADDRESS system
ADDRESS VALUE newenv
ADDRESS
ADDRESS (oldenv)
```

The first of these sets the environment COMMAND as the current environment.

The second performs the command 'copy' in the environment SYSTEM, using the values of the symbols fromfile and tofile as parameters. Note that this will not set SYSTEM as the current environment.

The third example sets SYSTEM as the current environment (it will be automatically converted to upper case).

The fourth example sets as the current environment the contents of the symbol newenv, pushing SYSTEM down one level in the stack.

The fifth clause swaps the two uppermost entries on the stack; and SYSTEM ends up at the top pushing the environment specified in newenv below it.

The sixth clause is equivalent to the fourth example, but is not allowed by ANSI. Since Regina 3.0 this style is deprecated and can't be used if OPTIONS STRICT_ANSI is in effect. Again, avoid this kind of ADDRESS statement style, and use the VALUE version instead.

Example: The VALUE subkeyword

Let us look a bit closer at the last example. Note the differences between the two clauses:

```
ADDRESS ENV
ADDRESS VALUE ENV
```

The first of these sets the current default environment to ENV, while the second sets it to the value of the symbol ENV.

If you are still confused, don't Panic; the syntax of ADDRESS is somewhat bizarre, and you should not put too much effort into learning all aspects of it. Just make sure that you understand how to use it in simple situations. Chances are that you will not have use for its more complicated variants for quite some time.

Then, what names are legal as environments? Well, that is implementation-specific, but some names seems to be in common use. The name COMMAND is sometimes used to refer to an environment that sends the command to the operating system. Likewise, the name of the operating system is often used for this (CMS, UNIX, etc.). You have to consult the implementation specific documentation for more information about this. Actually, there is not really any restrictions on what constitutes a legal environment name (even the nullstring is legal). Some interpreters will allow you to select anything as the current environment; and if it is an illegal name, the interpreter will complain only when the environment is actually used. Other implementations may not allow you to select an invalid environment name at all.

Regina allows every name as an environment name. Regina gives an error message about wrong names only when the name is used. The error string looks somewhat strange if Regina is used as a separate program, since the extension of the environment name space is only useful when running as part of a program which extends the standard names.

Regina uses three kinds of environments. Some have alias names. The environment names are:

SYSTEM
alias OS2ENVIRONMENT
alias ENVIRONMENT

This is the default environment which is selected at startup. The standard operating system command line interpreter will be loaded to execute the commands. You can use the built-in commands of the command line interpreter, often called shell, or any other program which the command line interpreter can find and load.

COMMAND alias CMD alias PATH

This environment loads the named program directly. You may supply a path if this is needed for the current operating system to load the program, otherwise Regina uses the standard operating system search rules for programs. This is done by searching through the items of the PATH system-environment variable in most operation systems. You can't use built-in shell functionality like system redirections like you can with SYSTEM. Regina's redirections are more powerful and work in either environment.

REXX alias REGINA

This environment uses a new instance of the Regina interpreter program to execute a program. The program has to be a REXX script. This environment has several advantages. The output of a script can be redirected, the process is independent and a risk of a crash is minimized when playing with external libraries, finally, Regina itself tries to find the correct REXX interpreter by itself and does everything to create a new incarnation of Regina.

The definition of REXX says nothing about which environment is preselected when you invoke the interpreter, although TRL defines that one environment is automatically preselected when starting up a REXX script. Note that there is no NONE environment in standard REXX, i.e. an environment that ignores commands, but some interpreters implement the TRACE setting ??? to accomplish this. Regina uses the environment SYSTEM as the preselected environment as mentioned above. More implementation specific details can be found in the section implementation specific documentation for Regina.

The list of environments will be saved across subroutine calls; so the effect of any ADDRESS clauses in a subroutine will cease upon return from the subroutine.

ADDRESS Redirections

ANSI defines redirections for the ADDRESS statement. This feature has been missing from Regina until version 3.0; although you have had the chance to redirect input and output by using LIFO> and >FIFO modifiers on command strings.

These command modifiers still exist and have a higher precedence than the ANSI defined redirections. Note, that LIFO and FIFO can be used by the newer redirection system. But, first of all, some examples show the usage of ADDRESS redirections.

```
ADDRESS SYSTEM "sort" WITH INPUT STEM names. OUTPUT STEM names.
ADDRESS SYSTEM "myprog" WITH INPUT STEM somefood. OUTPUT STREAM Tprg.outT
ERROR STEM oops.
ADDRESS PATH WITH INPUT FIFO TT OUTPUT NORMAL
ADDRESS SYSTEM WITH INPUT FIFO TT OUTPUT FIFO TT ERROR NORMAL
ADDRESS SYSTEM "fgrep TbongoT" WITH INPUT STREAM TfeederT
ADDRESS SYSTEM "sha256sum" WITH INPUT NOEOL FIFO TT
```

The first command instructs the default command line interpreter to call the program called sort. The input for the command is read from the stem names. (note the trailing period) and the output is sent back to the same stem variable after the command terminates. Thus, bothering about the implementation of a fast sort algorithm for a stem is as simple as calling a program which can actually do the sort.

A program called myprog is called in the second case. The input is fetched from the stem somefood. (again note the trailing period), and the standard output of the program is redirected to the stream called prg.out. Any generated error messages via the standard error stream are redirected to the stem called oops.

In the third example, the redirection behavior of the environment PATH is changed for all future uses. The input for all commands addressed to this environment is fetched from the standard stack in FIFO order. After each call the stack will be flushed. The output is sent to the default output stream, which is the current console in most cases. The behavior for error messages is not changed.

The fourth example allows pipes between commands in the environment; SYSTEM for all future uses. The input is fetched from the default stack and sent to the default stack after each command. The stack itself is flushed in between. Each executed program will write to something which is the input to the next called command. The error redirection is set or set back to the initial behavior of writing to the standard error stream.

The fifth example relates to the fourth. The default stack has to be filled with something initially. This is done by the redirection to the stream "feeder" while writing the output of the fgrep command to the default FIFO as declared in example four. After this, a single line with a simple sort command will sort the output of fgrep and place it in the default stack. You can fetch the final output of your pipe cascade by reading the stack contents. This statement overwrites some of the rules of the fourth example temporarily.

The sixth example highlights the fact that when the INPUT comes from the stack or a stem, Regina by default appends an End-Of-Line (EOL) to each item in the stack or stem before passing it to the command. This default behaviour is fine when the input data is to be treated as lines, but not when the data passed to the command must be unmodified. When INPUT comes from a stream, or when the NOEOL flag is set, the INPUT is not modified.

You can see the powerful possibilities of the redirection command. The disadvantage is the loss of a direct overview of what happens after a permanent redirection command has executed.

Its now the time to show you all rules and semantics of the redirection.

Rules for the redirection by the keyword WITH of the ADDRESS statement:

- Every environment has its own default redirection set.
- Every redirection set consists of three independent redirection elements; standard input (INPUT), standard output (OUTPUT) and standard error (ERROR). Users with some experiences with Unix, DOS & Windows or OS/2 may remember the redirection commands of the command line interpreter which can redirect each of the streams, too. This is nearly the same.
- Each redirection element starts with the program-startup streams given to REXX when invoking the interpreter. These can be reset to the startup default by specifying the argument NORMAL for each redirection element.
- The sequence of the redirection elements is irrelevant.
- You can specify each redirection element only once per statement.
- Redirections can be intermixed. This means you can let both the OUTPUT and the ERROR redirection point to the same "thing". The data from the different channels will be put to the assigned "thing" as they arrive. ANSI's point of view isn't very clear at this point. They state to keep the output different for files and put them together after the called program finished while the data shall be mixed at once when using stems.
- Regina always mixes the fetched data at once if possible.
- Redirections from and to the same source/destination try to keep the data consistent. If the INPUT/OUTPUT pair or the INPUT/ERROR pair points to the same destination, the content of the input or output channel is buffered so that writing to the output won't overwrite the input.
- A redirection element is entered by its name (e.g. INPUT), a redirection processor (e.g. STREAM) and a destination symbol (e.g. OUT_FN) following the rules to the redirection processor. This means that you have to enter a dot after a symbol name for a stem, or any symbol for the rest of the processors, in which case the content of the symbol is used as for normal variables.
- Both OUTPUT and ERROR streams can replace or append the data to the destination. Simply append either APPEND or REPLACE immediately after the OUTPUT or ERROR keywords.
- REPLACE is the default.
- The destination is checked or cleared prior to the execution of the command.
- ANSI defines two redirection processors: STEM and STREAM. The processors LIFO and FIFO are allowed extensions to the standard.

The processor STEM uses the content of the symbol destination.0 to access the count of the currently accessible lines. destination is the given destination name, of course. destination.0 must be filled with

a whole, non-negative number in terms of the DATATYPE built-in function. Each of n lines can be addressed by appending the whole numbers one to n to the stem. Example: STEM foo. is given, FOO.0 contains 3. This indicates three content lines. They are the contents of the symbols FOO.1 and FOO.2 and FOO.3.

The processor STREAM uses the content of the symbol destination to use a stream as known in the STREAM built-in function. The usage is nearly equivalent to the commands LINEIN destination or LINEOUT destination for accessing the contents of the file. An empty variable (content set to the empty string) as the content of the destination is allowed and indicates the default input, output or error streams given to the REXX program. This is equivalent to the NORMAL keyword.

The processor LIFO uses the content of the symbol destination as a queue name. New lines are pushed in last-in, first-out order to the queue. An empty destination string is allowed and describes the default queue. Lines are fetched from the queue if this processor is used for the INPUT stream.

The processor FIFO uses the content of the symbol destination as a queue name. New lines are pushed in first-in, first-out order to the queue. An empty destination string is allowed and describes the default queue. Lines are fetched from the queue if this processor is used for the INPUT stream.

On INPUT, all the data in the input stream is read up to either the end of the input data or until the called process terminates. The latter one may be determined after feeding up the input stream of the called process with unused data. Thus, there is no way to say if data is used or not. This isn't a problem with STEMs. But all file related sequential access objects including LIFOs and FIFOs may have lost data between two calls. Imagine an input file (STREAM) with three lines:

One line DELIMITER

Second line and furthermore two processes p1 and p2 called WITH INPUT STREAM f with f containing the three lines above. p1 reads lines up until a line containing DELIMITER and p2 processes the rest. It is very likely that the second process won't fetch any line because the stream may be processed by REXX, and REXX may has put one or more lines ahead into the feeder pipe to the process. This might or might not happen. It is implementation dependent and Regina shows this behavior. The input object is checked for existence and if it is properly set up before the command is started.

In short: INPUT may or may not use the entire input.

Both OUTPUT and ERROR objects are checked for being properly set up just before the command starts. REPLACE is implemented as a deletion just before the command starts. Note that ANSI doesn't force STEM lines to be dropped in case of a replacement. A big stem with thousands of lines will still exist after a replacement operation if the called command doesn't produce any output. Just destination.0 is set to 0.

The redirection of commands is a mystery to many people and it will continue be. You can thank all the people who designed stacks, queues, pipelines and all the little helper utilities of a witch's kitchen of process management.

The ARG Instruction

```
ARG [ template ] [, [ template ] ... ];
```

The ARG instruction will parse the argument strings at the current procedural level into the template.

Parsing will be performed in upper case mode. This clause is equivalent to:

```
PARSE UPPER ARG [ template ] ;
```

For more information, see the PARSE instruction. Note that this is the only situation where a multistring template is relevant.

Example: Beware assignments

The similarity between ARG and PARSE UPPER ARG has one exception. Suppose the PARSE UPPER ARG has an absolute positional pattern as the first element in the template, like:

```
parse upper arg =(foo) bar
```

This is not equivalent to an ARG instruction, because ARG instruction would become an assignment. A simple trick to avoid this problem is just to prepend a placeholder period (.) to the pattern, thus the

equal sign (is no longer the second token in the new ARG instruction. Also, unless the absolute positional pattern is indirect, the equal sign can be removed without changing the meaning of the statement.

The CALL Instruction

```
CALL routine [ parameter ] [, [ parameter ] ... ] ;
{ ON | OFF } condition [ NAME label ] ;
```

The CALL instruction invokes a subroutine, named by routine, which can be internal, built-in, or external; and the three repositories of functions are searched for routine in that order. The token routine must be either a literal string or a symbol (which is taken literally). However, if routine is a literal string, the pool of internal subroutines is not searched. Note that some interpreters may have additional repositories of labels to search.

In a CALL instruction, each parameter is evaluated, strictly in order from left to right, and passed as an argument to the subroutine. A parameter might be left out (i.e. an empty argument), which is not the same as passing the nullstring as argument.

Users often confuse a parameter which is the nullstring with leaving out the parameter. However, this is two very different situations. Consider the following calls to the built-in function TRANSLATE():

```
say translate('abcDEF' ) /* says ABCDEF */
say translate('abcDEF',"") /* says abcDEF */
say translate('abcDEF',,"") /* says ' ' */
```

The TRANSLATE() function is able to differ between receiving the nullstring (i.e. a defined string having zero length), from the situation where a parameter was not specified (i.e. the undefined string). Since TRANSLATE() is one of the few functions where the parameters' default values are very different from the nullstring, the distinction becomes very visible.

Breakage Alert!! - Start

Prior to Version 3.1 of Regina , the following syntactical use of the CALL instruction was valid: CALL routine '(' [parameter] [, [parameter] ...] ')' ; e.g.

```
call myfunc('abcDEF',,"")
```

This syntax is not allowed by ANSI and use of this syntax will now result in Error 37.1. There exists an option introduced in Regina 3.3 which re-enables a similar behaviour, although parameters with individual parentheses are allowed since 3.1. The option is called CALLS_AS_FUNCS and should be enabled using the environment variable called REGINA_OPTIONS. See the description of the instruction OPTIONS for further details.

Breakage Alert!! - End

For the CALL instruction, watch out for interference with line continuation. If there are trailing commas, it might be interpreted as line continuation. Appending a semicolon where appropriate is a common solution to make the desired behaviour obvious. If a CALL instruction uses line continuation between two parameters, two commas are needed: one to separate the parameters, and one to denote line continuation.

A number of settings are stored across internal subroutine calls. An internal subroutine will inherit the values in effect when the call is made, and the settings are restored on exit from the subroutine. These settings are:

- Conditions traps, see chapter Conditions.
- Current trapped condition, see section CTS.
- NUMERIC settings, see section Numeric.
- ADDRESS environments, see section Address.
- TRACE mode, see section Trace and chapter [not yet written].
- The elapse time clock, see section Time.

Also, the OPTIONS settings may or may not be restored, depending on the implementation;

Regina restores the current OPTIONS. Note that external subroutines don't inherit the current

OPTIONS as internal subroutines do. See the section OPTIONS for a detailed explanation. Further, a number of other things may be saved across internal subroutines. The effect on variables are controlled by the PROCEDURE instruction in the subroutine itself. The state of all DO-loops will be preserved during subroutine calls.

Example: Subroutines and trace settings

Subroutines can not be used to set various settings like trace settings, NUMERIC settings, etc. Thus, the following code will not work as intended:

```
say digits() /* says 9, maybe */
call inc_digits
say digits() /* still says 9 */
exit

inc_digits:
numeric digits digits() + 1 return
```

The programmer probably wanted to call a routine which incremented the precision of arithmetic operations. However, since the setting of NUMERIC DIGITS is saved across subroutine calls, the new value set in inc_digits is lost at return from that routine. Thus, in order to work correctly, the NUMERIC instruction must be located in the main routine itself.

Built-in subroutines will have no effect on the settings, except for explicitly defined side effects. Nor will external subroutines change the settings. For all practical purposes, an external subroutine is conceptually equivalent to re-invoking the interpreter in a totally separated process.

If the name of the subroutine is specified by a literal string, then the name will be used as-is; it will not be converted to upper case. This is important because a routine which contains lower case letters can only be invoked by using a literal string as the routine name in the CALL instruction.

Example: Labels are literals

Labels are literal, which means that they are neither tail-substituted nor substituted for the value of the variable. Further, this also means that the setting of NUMERIC DIGITS has no influence on the section of labels, even when the labels are numeric symbols. Consider the following code:

```
call 654.32
exit

654.321:
say here
return

654.32:
say there
return
```

In this example, the second of the two subroutines are always chosen, independent of the setting of NUMERIC DIGITS. Assuming that NUMERIC DIGITS are set to 5, then the number 654.321 is converted to 654.32, but that does not affect labels. Nor would a statement CALL 6.5432E2 call the second label, even though the numeric value of that symbol is equal to that of one of the labels.

The called subroutines may or may not return data to the caller. In the calling routine, the special variable RESULT will be set to the return value or dropped, depending on whether any data was returned or not. Thus, the CALL instruction is equivalent to calling the routine as a function, and assigning the return value to RESULT, except when the routine does not return data.

In REXX, recursive routines are allowed. A minimum number of 100 nested internal and external subroutine invocations, and support for a minimum of 10 parameters for each call are required by REXX. See chapter Limits for more information concerning implementation limits.

When the token following CALL is either ON or OFF, the CALL instruction is not used for calling a subroutine, but for setting up condition traps. In this case, the third token of the clause must be the name of a condition, which setup is to be changed.

If the second token was ON, then there can be either three or five tokens. If the five token version is used, then the fourth token must be NAME and the fifth token is taken to be the symbolic name of a label, which is the condition handler. This name can be either a constant string, or a symbol, which is taken literally. When OFF is used, the named condition trap is turned off.

Note that the ON and OFF forms of the CALL instruction were introduced in TRL2. Thus, they are not likely to be present on older interpreters. More information about conditions and condition traps are given in a chapter Conditions. </code>

The DO/END Instruction

```
D0 [ repetitor ] [ conditional ] ;
    [ clauses ]
    END [ symbol ] ;

repetitor : = symbol = expri [ TO exprt ]
    [ BY exprb ] [ FOR exprf ]
    exprr
    FOREVER

conditional : = WHILE exprw
    UNTIL expru
```

The DO/END instruction is the instruction used for looping and grouping several statements into one block. This is a multi-clause instruction.

The most simple case is when there is no repetitor or conditional it groups zero or more REXX clauses into one conceptual statement. This is most often used to execute multiple clauses in an IF instruction.

e.g.

```
if x = 1 then do
    say 'hello'
    say 'world'
end
```

The repetitor subclause controls the control variable of the loop, or the number of repetitions. The exprr subclause may specify a certain number of repetitions, or you may use FOREVER to go on looping forever.

If you specify the control variable symbol, it must be a variable symbol, and it will get the initial value expri at the start of the loop. At the start of each iteration, including the first, it will be checked whether it has reached the value specified by exprt. At the end of each iteration the value exprb is added to the control variable. The loop will terminate after at most exprf iterations. Note that all these expressions are evaluated only once, before the loop is entered for the first iteration.

You may also specify UNTIL or WHILE, which take a boolean expression. WHILE is checked before each iteration, immediately after the maximum number of iteration has been performed. UNTIL is checked after each iteration, immediately before the control variable is incremented. It is not possible to specify both UNTIL and WHILE in the same DO instruction.

The FOREVER keyword is only needed when there is no conditional, and the repetitor would also be empty if FOREVER was not specified. Actually, you could rewrite this as DO WHILE 1. The two forms are equivalent, except for tracing output.

The subclauses TO, BY, and FOR may come in any order, and their expressions are evaluated in the order in which they occur. However, the initial assignment must always come first. Their order may affect your program if these expressions have any side effects. However, this is seldom a problem, since it is guite intuitive.

Example: Evaluation order

What may prove a real trap, is that although the value to which the control variable is set is evaluated before any other expressions in the repetitor, it is assigned to the control variable after all expressions in the repetitor have been evaluated.

The following code illustrates this problem:

```
ctrl = 1
do ctrl=f(2) by f(3) to f(5)
    call f 6
end
call f 7 exit

f:
    say 'ctrl='ctrl 'arg='arg(1)
    return arg(1)
```

This code produces the following output:

```
ctrl=1 arg=2
ctrl=1 arg=3
ctrl=1 arg=5
ctrl=2 arg=6
ctrl=5 arg=6
ctrl=8 arg=7
```

Make sure you understand why the program produces this output. Failure to understand this may give you a surprise later, when you happen to write a complex DO-instruction, and do not get the expected result.

If the TO expression is omitted, there is no checking for an upper bound of the expression. If the BY subclause is omitted, then the default increment of 1 is used. If the FOR subclause is omitted, then there is no checking for a maximum number of iterations.

Example: Loop convergence For the reasons just explained, the instruction:

```
do ctrl=1
  nop /* and other statements */
end
```

will start with CTRL being 1, and then iterate through 2, 3, 4, ..., and never terminate except by LEAVE, RETURN, SIGNAL, or EXIT.

Although similar constructs in other languages typically provokes an overflow at some point, something "strange" happens in REXX. Whenever the value of ctrl becomes too large, the

incrementation of that variable produces a result that is identical to the old value of ctrl. For NUMERIC DIGITS set to 9, this happens when ctrl becomes 1.00000000E+9. When adding 1 to this number, the result is still 1.00000000E+9. Thus, the loop "converges" at that value.

If the value of NUMERIC DIGITS is 1, then it will "converge" at 10, or 1E+1 which is the "correct" way of writing that number under NUMERIC DIGITS 1. You can in general disregard loop "convergence", because it will only occur in very rare situations.

Example: Difference between UNTIL and WHILE

One frequent misunderstanding is that the WHILE and UNTIL subclauses of the DO/END instruction are equivalent, except that WHILE is checked before the first iteration, while UNTIL is first checked before the second iteration.

This may be so in other languages, but in REXX. Because of the order in which the parts of the loop are performed, there are other differences. Consider the following code:

```
count = 1
do i=1 while count \= 5
    count = count + 1
end
say i count

count = 1
do i=1 until count=5
    count = count + 1
end
say i count
```

After the first loop, the numbers 5 and 5, while in the second loop, the numbers 4 and 5 are written out. The reason is that a WHILE clause is checked after the control variable of the loop has been incremented, but an UNTIL expression is checked before the incrementation.

A loop can be terminated in several ways. A RETURN or EXIT instruction terminates all active loops in the procedure levels terminated. Further, a SIGNAL instruction transferring control (i.e. neither a SIGNAL ON nor SIGNAL OFF) terminates all loops at the current procedural level. This applies even to "implicit" SIGNAL instructions, i.e. when triggering a condition handler by the method of SIGNAL. A LEAVE instruction terminates one or more loops. Last but not least, a loop can terminate itself, when it has reached its specified stop conditions.

Note that the SIGNAL instruction terminates also non-repetitive loops (or rather: DO/END pairs), thus after an SIGNAL instruction, you must not execute an END instruction without having executed its corresponding DO first (and after the SIGNAL instruction). However, as long as you stay away from the ENDs, it is all right according to TRL to execute code within a loop without having properly activated the loop itself.

Note that on exit from a loop, the value of the control variable has been incremented once after the last iteration of the loop, if the loop was terminated by the WHILE expression, by exceeding the number of max iterations, or if the control variable exceeded the stop value. However, the control variable has the value of the last iteration if the loop was terminated by the UNTIL expression, or by an instruction inside the loop (e.g. LEAVE, SIGNAL, etc.).

The following algorithm in REXX code shows the execution of a DO instruction, assuming that expri, exprt, exprb, exprw, exprw, exprw, and symbol have been taken from the syntax diagram of DO.

```
@expri = expri
@exprt = exprt
@exprb = exprb
@exprf = exprf
@iters = 0
symbol = @expri
start of loop:
   if symbol > @extrt then signal after loop
   if @iters > @exprf then signal after loop
   if \exprw then signal after loop
      instructions
end of loop:
   if expru then signal after loop
   symbol = symbol + @exprb
   signal start_of_loop
after loop:
```

Some notes are in order for this algorithm. First, it uses the SIGNAL instruction, which is defined to terminate all active loops. This aspect of the SIGNAL instruction has been ignored for the purpose of illustrating the DO, and consequently, the code shown above is not suitable for nested loops.

Further, the order of the first four statements should be identical to the order in the corresponding subclauses in the repetitor. The code has also ignored that the WHILE and the UNTIL subclauses can not be used in the same DO instruction. And in addition, all variables starting with the at sign (@), are assumed to be internal variables, private to this particular loop. Within instructions, a LEAVE instruction is equivalent to signal after_loop, while a ITERATE instruction is equivalent to signal end_of_loop.

The DROP Instruction

```
DROP symbol [ symbol ... ] ;
```

The DROP instruction makes the named variables uninitialized, i.e. the same state that they had at the startup of the program. The list of variable names are processed strictly from left to right and dropped in that order. Consequently, if one of the variables to be dropped is used in a tail of another, then the order might be significant. E.g. the following two DROP instructions are not equivalent:

```
bar = 'a'
drop bar foo.bar /* drops 'BAR' and 'F00.BAR' */
bar = 'a'
drop foo.bar bar /* drops 'F00.a' and 'BAR'
```

The variable terms can be either a variable symbol or a symbol enclosed in parentheses. The former

form is first tail-substituted, and then taken as the literal name of the symbol to be dropped. The result names the variable to drop. In the latter form, the value of the variable symbol inside the parentheses is retrieved and taken as a space separated list of symbols. Each of these symbols is tail-substituted (if relevant); and the result is taken as the literal name of a variable to be dropped.

However, this process is not recursive, so that the list of names referred to indirectly can not itself contain parentheses. Note that the second form was introduced in TRL2, mainly in order to make INTERPRET unnecessary.

In general, things contained in parentheses can be any valid REXX expression, but this does not apply to the DROP, PARSE, and PROCEDURE instructions.

Example: Dropping compound variables

Note a potential problem for compound variables: when a stem variable is set, it will not set a default value, rather it will assign "all possible variables" in that stem collection at once. So dropping a compound variable in a stem collection for which the stem variable has been set, will set that compound variable to the original uninitialized value; not the value of the stem variable. See section Assign for further notes on assignments. To illustrate consider the code:

```
foo. = 'default'
drop baz bar foo.bar
say foo.bar foo.baz /* says 'FOO.BAR default' */
```

In this example, the SAY instruction writes out the value of the two compound variables FOO.BAR and FOO.BAZ. When performing tail-substitution for these, the interpreter finds that both BAR and BAZ are uninitialized. Further, FOO.BAR has also been made uninitialized, while FOO.BAZ has the value assigned to it in the assignment to the stem variable.

Example: Tail-substitution in DROP

For instance, suppose that the variable FOO has the value bar. After being dropped, FOO will have its uninitialized value, which is the same as its name: FOO. If the variable to be dropped is a stem variable, then both the stem variable and all compound variables of that stem become uninitialized.

```
bar = 123
drop foo.bar /* drops 'F00.123' */
```

Technically, it should be noted that some operations involving dropping of compound variables can be very space consuming. Even though the standard does not operate with the term "default value" for the value assigned to a stem variable, that is the way in which it is most likely to be implemented. When a stem is assigned a value, and some of its compound variables are dropped afterwards, then the interpreter must use memory to store references to the variables dropped. This might seem counter-intuitive at first, since dropping ought to release memory, not allocate more.

There is a parallel between DROP and PROCEDURE EXPOSE. However, there is one important difference, although PROCEDURE EXPOSE will expose the name of a variable enclosed in parentheses before starting to expose the symbols that variable refers to, this is not so for DROP. If DROP had mimicked the behaviour of PROCEDURE EXPOSE in this matter, then the whole purpose of indirect specifying of variables in DROP would have been defeated.

Dropping a variable which does not have a value is not an error. There is no upper limit on the

number of variables that can be dropped in one DROP clause, other than restrictions on the clause length. If an exposed variable is dropped, the variable in the caller is dropped, but the variable remains exposed. If it reassigned a value, the value is assigned to a variable in the caller routine.

The EXIT Instruction

```
EXIT [ expr ] ;
```

Terminates the REXX program, and optionally returns the expression expr to the caller. If specified, expr can be any string. In some systems, there are restrictions on the range of valid values for the expr. Often the return expression must be an integer, or even a non-negative integer. This is not really a restriction on the REXX language itself, but a restriction in the environment in which the interpreter operates, check the system dependent documentation for more information.

If expr is omitted, nothing will be returned to the caller. Under some circumstances that is not legal, and might be handled as an error or a default value might be used. The EXIT instruction behaves differently in a "program" than in an external subroutine. In a "program", it returns control to the caller e.g. the operating system command interpreter. While for an external routine, it returns control to the calling REXX script, independent of the level of nesting inside the external routine being terminated.

| | RETURN | EXIT |
|---|---|-------------------------------|
| At the main level of the program | Exits program | Exits program |
| At an internal subroutine level of the program | Exits subroutine, and returns to caller | Exits program |
| At the main level of an external subroutine | Levite the external clinrolitine | Exits the external subroutine |
| At a subroutine level within an external subroutine | calling rollting within external | Exits the external subroutine |

Actions of RETURN and EXIT Instructions

If terminating an external routine (i.e. returning to the calling REXX script) any legal REXX string value is allowed as a return value. Also, no return value can be returned, and in both cases, this information is successfully transmitted back to the calling routine. In the case of a function call (as opposed to a subroutine call), returning no value will raise SYNTAX condition {44}. The table above describes the actions taken by the EXIT and RETURN instruction in various situations.

The IF/THEN/ELSE Instruction

This is a normal if-construct. First the boolean expression expr is evaluated, and its value must be either 0 or 1 (everything else is a syntax error which raises SYNTAX condition number {34}).

Then, the statement following either THEN or ELSE is executed, depending on whether expr was 1 or 0, respectively.

Note that there must come a statement after THEN and ELSE. It is not allowed to put just a null-clause (i.e. a comment or a label) there. If you want the THEN or ELSE part to be empty, use the NOP instruction. Also note that you can not directly put more than one statement after THEN or ELSE; you have to package them in a DO-END pair to make them a single, conceptual statement.

After THEN, after ELSE, and before THEN, you might put one or more clause delimiters (newlines or semicolons), but these are not required. Also, the ELSE part is not required either, in which case no code is executed if expr is false (evaluates to 0). Note that there must also be a statement separator before ELSE, since the that statement must be terminated. This also applies to the statement after ELSE. However, since statement includes a trailing clause delimiter itself, this is not explicitly shown in the syntax diagram.

Example: Dangling ELSE

Note the case of the "dangling" ELSE. If an ELSE part can correctly be thought of as belonging to more than one IF/THEN instruction pair, it will be parsed as belonging to the closest (i.e. innermost) IF instruction:

```
parse pull foo bar
if foo then
   if bar then
      say 'foo and bar are true'
   else
      say 'one or both are false'
```

In this code, the ELSE instruction is nested to the innermost IF, i.e. to IF BAR THEN.

The INTERPRET Instruction

```
INTERPRET expr ;
```

The INTERPRET instruction is used to dynamically build and execute REXX instructions during runtime. First, it evaluates the expression expr, and then parses and interprets the result as a (possibly empty) list of REXX instructions to be executed. For instance:

```
foo = 'hello, world'
interpret 'say "'foo'!"'
```

executes the statement SAY "hello, world!" after having evaluated the expression following INTERPRET. This example shows several important aspects of INTERPRET. Firstly, it's very easy to get confused by the levels of quotes, and a bit of caution should be taken to nest the quotes correctly. Secondly, the use of INTERPRET does not exactly improve readability.

Also, INTERPRET will probably increase execution time considerably if put inside loops, since the interpreter may be forced to reparse the source code for each iteration. Many optimizing REXX interpreters (and in particular REXX compilers) has little or no support for INTERPRET. Since virtually anything can happen inside it, it is hard to optimize, and it often invalidates assumptions in other parts of the script, forcing it to ignore other possible optimizations. Thus, you should avoid INTERPRET when speed is at a premium.

There are some restrictions on which statements can be inside an INTERPRET statement. Firstly, labels cannot occur there. TRL states that they are not allowed, but you may find that in some implementations labels occurring there will not affect the label symbol table of the program being run. Consider the statement:

```
interpret 'signal there; there: say hallo'
there:
```

This statement transfers control to the label THERE in the program, never to the THERE label inside the expression of the INTERPRET instruction. Equivalently, any SIGNAL to a label THERE elsewhere in the program never transfers control to the label inside the INTERPRET instruction.

However, labels are strictly speaking not allowed inside INTERPRET strings.

Example: Self-modifying Program

There is an idea for a self-modifying program in REXX which is basically like this:

```
string = ''
do i=1 to sourceline()
    string = string ';' sourceline(i)
end

string = transform( string )
interpret string
exit

transform: procedure
    parse arg string
    /* do some transformation on the argument */
    return string
```

Unfortunately, there are several reasons why this program will not work in REXX, and it may be instructive to investigate why. Firstly, it uses the label TRANSFORM, which is not allowed in the argument to INTERPRET. The interpret will thus refer to the TRANSFORM routine of the "outermost" invocation, not the one "in" the INTERPRET string.

Secondly, the program does not take line continuations into mind. Worse, the SOURCELINE() built-in function refers to the data of the main program, even inside the code executed by the INTERPRET instruction. Thirdly, the program will never end, as it will nest itself up till an implementation-dependent limit for the maximum number of nested INTERPRET instructions.

In order to make this idea work better, temporary files should be used.

On the other hand, loops and other multi-clause instructions, like IF and SELECT occur inside an INTERPRET expression, but only if the whole instruction is there; you can not start a structured instruction inside an INTERPRET instruction and end it outside, or vice-versa. However, the instruction SIGNAL is allowed even if the label is not in the interpreted string. Also, the instructions ITERATE and LEAVE are allowed in an INTERPRET, even when they refer to a loop that is external to the interpreted string.

Most of the time, INTERPRET is not needed, although it can yield compact and interesting code. If you

do not strictly need INTERPRET, you should consider not using it, for reasons of compatibility, speed, and readability. Many of the traditional uses of INTERPRET have been replaced by other mechanisms in order to decrease the necessity of INTERPRET; e.g. indirect specification of variables in EXPOSE and DROP, the improved VALUE() built-in function, and indirect specification of patterns in templates.

Only semicolon (;) is allowed as a clause delimiter in the string interpreted by an INTERPRET instruction. The colon of labels can not be used, since labels are not allowed. Nor does specific end-of-line character sequences have any defined meaning there. However, most interpreters probably allow the end-of-line character sequence of the host operating system as alternative clause delimiters. It is interesting to note that in the context of the INTERPRET instruction, an implicit, trailing clause delimiter is always appended to the string to be interpreted.

The ITERATE Instruction

ITERATE [symbol] ;

2025/11/17 15:12

The ITERATE instruction will iterate the innermost, active loop in which the ITERATE instruction is located. If symbol is specified, it will iterate the innermost, active loop having symbol as control variable. The simple DO/END statement without a repetitor and conditional is not affected by ITERATE. All active multiclause structures (DO, SELECT, and IF) within the loop being iterated are terminated.

The effect of an ITERATE is to immediately transfer control to the END statement of the affected loop, so that the next (if any) iteration of the loop can be started. It only affects loops on the current procedural level. All actions normally associated with the end of an iteration is performed.

Note that symbol must be specified literally; i.e. tail substitution is not performed for compound variables. So if the control variable in the DO instruction is FOO.BAR, then symbol must use FOO.BAR if it is to refer to the control variable, no matter the value of the BAR variable.

Also note that ITERATE (and LEAVE) are means of transferring control in the program, and therefore they are related to SIGNAL, but they do not have the effect of automatically terminating all active loops on the current procedural level, which SIGNAL has.

Two types of errors can occur. Either symbol does not refer to any loop active at the current procedural level; or (if symbol is not specified) there does not exist any active loops at the current procedural level. Both errors are reported as SYNTAX condition {28}.

The LEAVE Instruction

LEAVE [symbol] ;

This statement terminates the innermost, active loop. If symbol is specified, it terminates the innermost, active loop having symbol as control variable. As for scope, syntax, errors, and functionality, it is identical to ITERATE, except that LEAVE terminates the loop, while ITERATE lets the loop start on the next iteration normal iteration. No actions normally associated with the normal end of an iteration of a loop is performed for a LEAVE instruction.

Example: Iterating a simple DO/END

In order to circumvent this, a simple DO/END can be rewritten as this:

```
if foo then do until 1
    say 'This is a simple DO/END group'
    say 'but it can be terminated by'
    leave
    say 'iterate or leave'
end
```

This shows how ITERATE has been used to terminate what for all practical purposes is a simple DO/END group. Either ITERATE or LEAVE can be used for this purpose, although LEAVE is perhaps marginally faster.

The NOP Instruction

```
NOP ;
```

The NOP instruction is the "no operation" statement; it does nothing. Actually, that is not totally true, since the NOP instruction is a "real" statement (and a placeholder), as opposed to null clauses. I've only seen this used in two circumstances.

After any THEN or ELSE keyword, where a statement is required, when the programmer wants an empty THEN or ELSE part. By the way, this is the intended use of NOP. Note that you can not use a null clause there (label, comment, or empty lines), since these are not parsed as "independent" statements.

I have seen it used as "trace-bait". That is, when you start interactive trace, the statement immediately after the TRACE instruction will be executed before you receive interactive control. If you don't want that to happen (or maybe the TRACE instruction was the last in the program), you need to add an extra dummy statement. However, in this context, labels and comments can be used, too.

The NUMERIC Instruction

```
NUMERIC DIGITS [ expr ] ;
FORM [ SCIENTIFIC | ENGINEERING | [ VALUE ] expr ] ;
FUZZ [ expr ] ;
```

REXX has an unusual form of arithmetic. Most programming languages use integer and floating point arithmetic, where numbers are coded as bits in the computers native memory words. However, REXX uses floating point arithmetic of arbitrary precision, that operates on strings representing the numbers. Although much slower, this approach gives lots of interesting functionality. Unless number-crunching is your task, the extra time spent by the interpreter is generally quite acceptable and often almost unnoticeable.

The NUMERIC statement is used to control most aspects of arithmetic operations. It has three distinct forms: DIGITS, FORM and FUZZ; which to choose is given by the second token in the instruction:

DIGITS

Is used to set the number of significant digits in arithmetic operations. The initial value is 9, which is also the default value if expr is not specified. Large values for DIGITS tend to slow down some arithmetic operations considerably. If specified, expr must be a positive integer.

FUZZ

Is used in numeric comparisons, and its initial value is 0, which is the also the default value if expr is not specified. Normally, two numbers must have identical numeric values for a number of their most significant digits in order to be considered equal. How many digits are considered is determined by DIGITS. If DIGITS is 4, then 12345 and 12346 are equal, but not 12345 and 12356. However, when FUZZ is non-zero, then only the DIGITS minus FUZZ most significant digits are checked. E.g. if DIGITS is 4 and FUZZ are 2, then 1234 and 1245 are equal, but not 1234 and 1345.

The value for FUZZ must be a non-negative integer, and less than the value of DIGITS. FUZZ is seldom used, but is useful when you want to make comparisons less influenced by inaccuracies. Note that using with values of FUZZ that is close to DIGITS may give highly surprising results.

FORM

Is used to set the form in which exponential numbers are written. It can be set to either SCIENTIFIC or ENGINEERING. The former uses a mantissa in the range 1.000... to 9.999..., and an exponent which can be any integer; while the latter uses a mantissa in the range 1.000... to 999.999..., and an exponent which is dividable by 3. The initial setting is SCIENTIFIC which is also the default value if expr is not specified. Following the subkeyword FORM may be the subkeywords SCIENTIFIC and ENGINEERING, or the subkeyword VALUE. In the latter case, the rest of the statement is considered an expression, which will evaluate to either SCIENTIFIC or ENGINEERING. However, if the first token of the expression following VALUE is neither a symbol nor literal string, then the VALUE subkeyword can be omitted.

The setting of FORM never affects the decision about whether to choose exponential form or normal floating point form; it only affects the appearance of the exponential form once that form has been selected.

Many things can be said about the usefulness of FUZZ. My impression is that it is seldom used in REXX programs. One problem is that it only addresses relative inaccuracy: i.e. that the smaller value must be within a certain range, that is determined by a percentage of the larger value. Often one needs absolute inaccuracy, e.g. two measurements are equal if their difference are less than a certain absolute threshold.

Example: Simulating relative accuracy with absolute accuracy

As explained above, REXX arithmetic has only relative accuracy, in order to obtain absolute accuracy, one can use the following trick:

```
numeric fuzz 3
if a=b then
    say 'relative accuracy'
if abs(a-b)<=500 then
    say 'absolute accuracy'</pre>
```

In the first IF instruction, if A is 100,000, then the range of values for B which makes the expression true is 99,500-100,499, i.e. an inaccuracy of about +-500. If A has the value 10,000,000, then B must

Last update: 2024/09/04 06:58

be within the range 9,950,000-10,049,999; i.e. an inaccuracy of about +-50,000.

However, in the second IF instruction, assuming A is 100,000, the expression becomes true for values of B in the range 99,500-100,500. Assuming that A is 10,000,000, the expression becomes true for values of B in the range 9,999,500-10,000,500.

The effect is largely to force an absolute accuracy for the second example, no matter what the values of A and B are. This transformation has taken place since an arithmetic subtraction is not affected by the NUMERIC FUZZ, only numeric comparison operations. Thus, the effect of NUMERIC FUZZ on the implicit subtraction in the operation = in the first IF has been removed by making the subtraction explicit.

Note that there are some minor differences in how numbers are rounded, but this can be fixed by transforming the expression into something more complex.

To retrieve the values set for NUMERIC, you can use the built-in functions DIGITS(), FORM(), and FUZZ(). These values are saved across subroutine calls and restored upon return.

The OPTIONS Instruction

OPTIONS expr;

The OPTIONS instruction is used to set various interpreter-specific options. Its typical uses are to select certain REXX dialects, enable optimizations (e.g. time versus memory considerations), etc. No standard dictates what may follow the OPTIONS keyword, except that it should be a valid REXX expression, which is evaluated. Currently, no specific options are required by any standard.

The contents of expr is supposed to be word based, and it is the intention that more than one option can be specified in one OPTIONS instruction. REXX interpreters are specifically instructed to ignore OPTIONS words which they do not recognize. That way, a program can use run-time options for one interpreter, without making other interpreters trip when they see those options. An example of OPTION may be:

OPTIONS 4.00 NATIVE_FLOAT

The instruction might instruct the interpreter to start enforcing language level 4.00, and to use native floating point numbers in stead of the REXX arbitrary precision arithmetic. On the other hand, it might also be completely ignored by the interpreter.

It is uncertain whether modes selected by OPTIONS will be saved across subroutine calls. Refer to implementation-specific documentation for information about this.

Example: Drawback of OPTIONS

Unfortunately, the processing of the OPTIONS instruction has a drawback. Since an interpreter is instructed to ignore option-settings that it does not understand, it may ignore options which are essential for further processing of the program. Continuing might cause a fatal error later, although the behaviour that would most precisely point out the problem is a complaint about the non-supported OPTION setting. Consider:

options 'cms bifs'

```
pos = find( haystack, needle )
```

If this code fragment is run on an interpreter that does not support the cms_bifs option setting, then the OPTIONS instruction may still seem to have been executed correctly. However, the second clause will generally crash, since the FIND() function is still not available. Even though the real problem is in the first line, the error message is reported for the second line.

The PARSE Instruction

```
PARSE [ option ] [ CASELESS ] type [ template ] ;
  option = { UPPER | LOWER }
  type = { ARG | LINEIN | PULL | SOURCE | VERSION | VALUE [ expr ] WITH |
VAR symbol }
```

The PARSE instruction takes one or more source strings, and then parses them using the template for directions. The process of parsing is one where parts of a source string are extracted and stored in variables. Exactly which parts, is determined by the patterns specified by template. template can be a number of patterns separated by commas. A complete description of parsing is given in chapter [not yet written].

If the option UPPER is specified, the input source strings are uppercased (based on locale) before being split into the variables specified by template.

If the option LOWER is specified, the input source strings are lowercased (based on locale) before being split into the variables specified by template.

If CASELESS is specified, any character strings in template will be matched against the source strings irrespective of case (based on locale).

Which strings are to be the source of the parsing is defined by the type subclause, which can be any of:

ARG.

The data to use as the source during the parsing is the argument strings given at the invocation of this procedure level. Note that this is the only case where the source may consist of multiple strings.

LINEIN.

Makes the PARSE instruction read a line from the standard input stream, as if the LINEIN() built-in function had been called. It uses the contents of that line (after stripping off end-of-line characters, if necessary) as the source for the parsing. This may raise the NOTREADY condition if problems occurred during the read.

PULL.

Retrieves as the source string for the parsing the topmost line from the stack. If the stack is empty, the default action for reading an empty stack is taken. That is, it will read a whole line from the standard input stream, strip off any end-of-line characters (if necessary), and use that string as the source.

SOURCE.

Last update: 2024/09/04 06:58

The source string for the parsing is a string containing information about how this invocation of the REXX interpreter was started. This information will not change during the execution of a REXX script. The format of the string is:

system invocation filename

Here, the first space-separated word (system) is a single word describing the platform on which the system is running. Often, this is the name of the operating system. The second word describes how the script was invoked. TRL2 suggests that invocation could be COMMAND, FUNCTION, or SUBROUTINE, but notes that this may be specific to VM/CMS.

Everything after the second word is implementation-dependent. It is indicated that it should refer to the name of the REXX script, but the format is not specified. In practice, the format will differ because the format of file names differs between various operating systems. Also, the part after the second word might contain other types of information. Refer to the implementation-specific notes for exact information.

VALUE expr WITH.

This form will evaluate expr and use the result of that evaluation as the source string to be parsed. The token WITH may not occur inside expr, since it is a reserved subkeyword in this context.

VAR symbol.

This form uses the current value of the named variable symbol (after tail-substitution) as the source string to be parsed. The variable may be any variable symbol. If the variable is uninitialized, then a NOTREADY condition will be raised.

VERSION.

This format resembles SOURCE, but it contains information about the version of REXX that the interpreter supports. The string contains five words, and has the following format:

language level date month year

Where language is the name of the language supported by the REXX interpreter. This may seem like overkill, since the language is REXX, but there may be various different dialects of REXX. The word can be just about anything, except for two restrictions, the first four letters should be REXX (in upper case), and the word should not contain any periods. [TRL2] indicates that the remainder of the word (after the fourth character) can be used to identify the implementation.

The second word is the REXX language level supported by the interpreter. Note that this is not the same as the version of the interpreter, although several implementations makes this mistake. Strictly speaking, neither [TRL1] nor [TRL2] define the format of this word, but a numeric format is strongly suggested.

The last three words (date, month, and year) makes up the date part of the string. This is the release date of the interpreter, in the default format of the DATE() built-in function.

Much confusion seems to be related to the second word of PARSE VERSION. It describes the language

level, which is not the same as the version number of the interpreter. In fact, most interpreters have a version numbering which is independent of the REXX language level.

Unfortunately, several interpreters makes the mistake of using this field as for their own version number. This is very unfortunate for two reasons; first, it is incorrect, and second, it makes it difficult to determine which REXX language level the interpreter is supposed to support.

Chances are that you can find the interpreter version number in PARSE SOURCE or the first word of PARSE VERSION.

The format of the REXX language level is not rigidly defined, but TRL1 corresponds to the language level 3.50, while TRL2 corresponds to the language level 4.00. Both implicitly indicate the that language level description is a number, and states that an implementation less than a certain number "may be assumed to indicate a subset" of that language level. However, this must not be taken to literally, since language level 3.50 has at least two features which are missing in language level 4.00 (the Scan trace setting, and the PROCEDURE instruction that is not forced to be the first instruction in a subroutine). [TRH:PRICE] gives a very good overview over the varying functionality of different language levels of REXX up to level 4.00.

With the release of the ANSI REXX Standard [ANSI] in 1996, the REXX language IS now rigidly defined. The language level of ANSI REXX is 5.00. Regina is now compliant to the ANSI Standard. Thus PARSE VERSION will return 5.00.

Note that even though the information of the PARSE SOURCE is constant throughout the execution of a REXX script, this is not necessarily correct for the PARSE VERSION. If your interpreter supports multiple language levels (e.g. through the OPTIONS instruction), then it will have to change the contents of the PARSE VERSION string in order to comply with different language levels. To some extent, this may also apply to PARSE SOURCE, since it may have to comply with several implementation-specific standards.

After the source string has been selected by the type subclause in the PARSE instruction, this string is parsed into the template. The functionality of templates is common for the PARSE, ARG and PULL instructions, and is further explained in chapter [not yet written].

The PROCEDURE Instruction

```
PROCEDURE [ EXPOSE [ varref [ varref ... ] ] ] ;
  varref = { symbol | ( symbol ) }
```

The PROCEDURE instruction is used by REXX subroutines in order to control how variables are shared among routines. The simplest use is without any parameters; then all future references to variables in that subroutine refer to local variables. If there is no PROCEDURE instruction in a subroutine, then all variable references in that subroutine refer to variables in the calling routine's name space.

If the EXPOSE subkeyword is specified too, then any references to the variables in the list following EXPOSE refer to local variables, but to variables in the name space of the calling routine.

Example: Dynamic execution of PROCEDURE

The definition opens for some strange effects, consider the following code:

```
testing:
    say foo
    procedure expose bar
    say foo
```

Here, the first reference to FOO is to the variable FOO in the caller routine's name space, while the second reference to FOO is to a local variable in the called routine's name space. This is difficult to parse statically, since the names to expose (and even when to expose them) is determined dynamically during run-time. Note that this use of PROCEDURE is allowed in [TRL1], but not in [TRL2].

Several restrictions have been imposed on PROCEDURE in [TRL2] in order to simplify the execution of PROCEDURE (and in particular, to ease the implementation of optimizing interpreters and compilers).

The first restriction, to which all REXX interpreters adhere as far as I know, is that each invocation of a subroutine (i.e. not the main program) may execute PROCEDURE at most once. Both TRL1 and TRL2 contain this restriction. However, more than one PROCEDURE instruction may exist "in" each routine, as long as at most one is executed at each invocation of the subroutine.

The second restriction is that the PROCEDURE instruction must be the first statement in the subroutine. This restriction was introduced between REXX language level 3.50 and 4.00, but several level 4.00 interpreters may not enforce it, since there is no breakage when allowing it.

There are several important consequences of this second restriction:

- 1. it implicitly includes the first restriction listed above, since only one instruction can be the first;
- 2. it prohibits selecting one of several possible PROCEDURE instructions; (3) it prohibits using the same variable name twice; first as an exposed and then as a local variable, as indicated in the example above; (4) it prohibits the customary use of PROCEDURE and INTERPRET, where the latter is used to create a level of indirectness for the PROCEDURE instruction. This particular use can be exemplified by:

```
testing:
interpret 'procedure expose' bar
```

where BAR holds a list of variable names which are to be exposed. However, in order to make this functionality available without having to resort to INTERPRET, which is generally considered "bad" programming style, new functionality has been added to PROCEDURE between language levels 3.50 and 4.00. If one of the variables in the list of variables is enclosed in parentheses, that means indirection. Then, the variables exposed are: (1) the variable enclosed in parentheses; (2) the value of that variable is read, and its contents is taken to be a space-separated list of variable names; and (3) all there variable names are exposed strictly in order from left to right.

Example: Indirect exposing

Consider the following example:

```
testing:
procedure expose foo (bar) baz
```

Assuming that the variable BAR holds the value one two, then variables exposed are the following:

FOO, BAR, ONE, TWO, BAZ, in that order. In particular, note that the variable FOO is exposed immediately before the variables which it names are exposed.

Example: Order of exposing

Then there is another fine point about exposing, the variables are hidden immediately after the EXPOSE subkeyword, so they are not initially available when the variable list is processed. Consider the following code:

```
testing:
procedure expose bar foo.bar foo.baz baz
```

which exposes variables in the order specified. If the variable BAR holds the value 123, then FOO.123 is exposed as the second item, since BAR is visible after having already been exposed as the first item. On the other hand, the third item will always expose the variable FOO.BAZ, no matter what the value of BAZ is in the caller, since the BAZ variable is visible only after it has been used in the third item. Therefore, the order in which variables are exposed is important. So, if a compound variable is used inside parentheses in an PROCEDURE instruction, then any simple symbols needed for tail substitution must previously to have been explicitly exposed. Compare this to the DROP instruction.

What exactly is exposing? Well, the best description is to say that it makes all future uses (within that procedural level) to a particular variable name refer to the variable in the calling routine rather than in the local subroutine. The implication of this is that even if it is dropped or it has never been set, an exposed variable will still refer to the variable in the calling routine. Another important thing is that it is the tail-substituted variable name that is exposed. So if you expose FOO.BAR, and BAR has the value 123, then only FOO.123 is exposed, and continues to be so, even if BAR later changes its value to e.g. 234.

Example: Global variables

A problem lurking on new REXX users, is the fact that exposing a variable only exposes it to the calling routine. Therefore, it is incorrect to speak of global variables, since the variable might be local to the calling routine. To illustrate, consider the following code:

```
foo = 'bar'
call sub1
call sub2
exit

sub1: procedure expose foo
    say foo /* first says 'bar', then 'F00' */
    return

sub2: procedure
    say foo /* says 'F00' */
    call sub1
    return
```

Here, the first subroutine call in the "main" program writes out bar, since the variable FOO in SUB1 refers to the FOO variable in the main program's (i.e. its caller routine's) name space. During the second call from the main program, SUB2 writes out FOO, since the variable is not exposed.

However, SUB2 calls SUB1, which exposes FOO, but that subroutine also writes out FOO. The reason for this is that EXPOSE works on the run-time nesting of routines, not on the typographical structure of the code. So the PROCEDURE in SUB1 (on its second invocation) exposes FOO to SUB2, not to the main program as typography might falsely indicate.

The often confusing consequence of the run-time binding of variable names is that an exposed variable of SUB1 can be bound to different global variables, depending on from where it was called. This differs from most compiled languages, which bind their variables independently of from where a subroutine is called. In turn, the consequence of this is that REXX has severe problems storing a persistent, static variable which is needed by one subroutine only. A subroutine needing such a variable (e.g. a count variable which is incremented each time the subroutine is called), must either use an operating system command, or all subroutines calling that subroutine (and their calling routines, etc.) must expose the variable. The first of these solution is very inelegant and non-standard, while the second is at best troublesome and at worst seriously limits the maximum practical size of a REXX program. There are hopes that the VALUE() built-in function will fix this in future standards of REXX.

Another important drawback with PROCEDURE is that it only works for internal subroutines; for external subroutines it either do not work, or PROCEDURE may not even be allowed on the main level of the external subroutine. However, in internal subroutines inside the external subroutines, PROCEDURE is allowed, and works like usual.

The PULL Instruction

```
PULL [ template ] ;
```

This statement takes a line from the top of the stack and parse it into the variables in the template. It will also translate the contents of the line to uppercase.

This statement is equivalent to PARSE UPPER PULL [template] with the same exception as explained for the ARG instruction. See chapter [not yet written] for a description of parsing and chapter Stack for a discussion of the stack.

The PUSH Instruction

```
PUSH [ expr ] ;
```

The PUSH instruction will add a string to the stack. The string added will either be the result of the expr, or the nullstring if expr is not specified.

The string will be added to the top of the stack (LIFO), i.e. it will be the first line normally extracted from the stack. For a thorough discussion of the stack and the methods of manipulating it, see chapter Stack for a discussion of the stack.

The QUEUE Instruction

```
QUEUE [ expr ] ;
```

The QUEUE instruction is identical to the PUSH instruction, except for the position in the stack where the new line is inserted. While the PUSH puts the line on the "top" of the stack, the QUEUE instruction inserts it at the bottom of the stack (FIFO), or in the bottom of the topmost buffer, if buffers are used.

For further information, refer to documentation for the PUSH instruction, and see chapter Stack for general information about the stack.

The RETURN Instruction

```
RETURN [ expr ] ;
```

The RETURN instruction is used to terminate the current procedure level, and return control to a level above. When RETURN is executed inside one or more nesting construct, i.e. DO, IF, WHEN, or OTHERWISE, then the nesting constructs (in the procedural levels being terminated) are terminated too.

Optionally, an expression can be specified as an argument to the RETURN instruction, and the string resulting from evaluating this expression will be the return value from the procedure level terminated, to the caller procedure level. When RETURN is executed with no argument, no return value is returned to the caller, and then a SYNTAX condition {44} is raised if the subroutine was invoked as a function.

Example: Multiple entry points

A routine can have multiple exit points, i.e. a procedure can be terminated by any of several RETURN instructions. A routine can also have multiple entry points, i.e. several routine entry points can be terminated by the same RETURN instruction. However, this is rarer than having multiple exit points, because it is generally perceived that it creates less structured and readable code. Consider the following code:

```
call foo
call bar
call baz
exit
foo:
   if datatype(name, 'w') then
      drop name
   signal baz
bar:
   name = 'foo'
baz:
   if symbol('name') == 'VAR' then
      say 'NAME currently has the value' name
   else
      say 'NAME is currently an unset variable'
   return
```

Although this is hardly a very practical example, it shows how the main bulk of a routine can be used

together with three different entry points. The main part of the routine is the IF statement having two SAY statements. It can be invoked by calling FOO, BAR, or BAZ.

There are several restrictions to this approach. For instance, the PROCEDURE statement becomes cumbersome, but not impossible, to use.

Also note that when a routine has multiple exit points, it may choose to return a return value only at some of those exit points.

When a routine is located at the very end of a source file, there is an implicit RETURN instruction after the last explicit clause. However, according to good programming practice, you should avoid taking advantage of this feature, because it can create problems later if you append new routines to the source file and forget to change the implied RETURN to an explicit one.

If the current procedure level is the main level of either the program or an external subroutine, then a RETURN instruction is equivalent to an EXIT instruction, i.e. it will terminate the REXX program or the external routine. The table in the Exit section shows the actions of both the RETURN and

EXIT instructions depending on the context in which they occur.

The SAY Instruction

```
SAY [ expr ] ;
```

Evaluates the expression expr, and prints the resulting string on the standard output stream. If expr is not specified, the nullstring is used instead. After the string has been written, an implementation-specific action is taken in order to produce an end-of-line.

The SAY instruction is roughly equivalent to

```
call lineout , expr
```

The differences are that there is no way of determining whether the printing was successfully completed if SAY is used, and the special variable RESULT is never set when executing a SAY instruction. Besides, the effect of omitting expr is different. In SAA API, the RXSIOSAY subfunction of the RXSIO exit handler is able to trap a SAY instruction, but not a call to the LINEOUT() built-in function. Further, the NOTREADY condition is never raised for a SAY instruction.

The SELECT/WHEN/OTHERWISE Instruction

```
SELECT ; whenpart [ whenpart ... ] [ OTHERWISE [;] [ statement ... ] ] END ;
  whenpart : WHEN expr [;] THEN [;] statement
```

This instruction is used for general purpose, nested IF structures. An example of the general use of the SELECT instruction is:

```
select
  when expr1 then statement1
  when expr2 then do
```

```
statement2a
statement2b
end
when expr3 then statement3
otherwise
ostatement1
ostatement2
end
```

When the SELECT instruction is executed, the next statement after the SELECT statement must be a WHEN statement. The expression immediately following the WHEN token is evaluated, and must result in a valid boolean value. If it is true (i.e. 1), the statement following the THEN token matching the WHEN is executed, and afterwards, control is transferred to the instruction following the END token matching the SELECT instruction. This is not completely true, since an instruction may transfer control elsewhere, and thus implicitly terminate the SELECT instruction; e.g. LEAVE, EXIT, ITERATE, SIGNAL, or RETURN or a condition trapped by method SIGNAL.

If the expression of the first WHEN is not true (i.e. 0), then the next statement must be either another WHEN or an OTHERWISE statement. In the former case, the process explained above is iterated. In the latter case, the clauses following the OTHERWISE up to the END statement are interpreted.

It is considered a SYNTAX condition, {7} if no OTHERWISE statement when none of the WHENexpressions evaluates to true. In general this can only be detected during runtime. However, if one of the WHENs is selected, the absence of an OTHERWISE is not considered an error.

By the nature of the SELECT instruction, the WHENs are tested in the sequence they occur in the source. If more than one WHEN have an expression that evaluates to true, the first one encountered is selected.

If the programmer wants to associate more than one statement with a WHEN statement, a DO/END pair must be used to enclose the statements, to make them one statement conceptually. However, zero, one, or more statements may be put after the OTHERWISE without having to enclose them in a DO/END pair. The clause delimiter is optional after OTHERWISE, and before and after THEN.

Example: Writing SELECT as IF

SELECT in REXX is just a shorthand notation for nested IF instructions. Thus a SELECT instruction can always be written as set of nested IF statements; but for very large SELECT statements, the corresponding nested IF structure may be too deeply nested for the interpreter to handle.

The following code shows how the SELECT statement shown above can be written as a nested IF structure:

```
if expr1 then statement1
else if expr2 then do
    statement2a
    statement2b
end else if expr3 then statement3
else
    ostatement1 ostatement2
end
```

The SIGNAL Instruction

```
SIGNAL { string | symbol } ;
  [ VALUE ] expr ;
  { ON | OFF } condition [ NAME { string | symbol } ] ;
```

The SIGNAL instruction is used for two purposes: (a) to transfer control to a named label in the program, and (b) to set up a named condition trap.

The first form in the syntax definition transfers control to the named label, which must exist somewhere in the program; if it does not exist, a SYNTAX condition {16} is raised. If the label is multiple defined, the first definition is used. The parameter can be either a symbol (which is taken literally) or a string. If it is a string, then be sure that the case of the string matches the case of the label where it is defined. In practice, labels are in upper case, so the string should contain only uppercase letters too, and no space characters.

The second form of the syntax is used if the second token of the instruction is VALUE. Then, the rest of the instruction is taken as a general REXX expression, which result after evaluation is taken to be the name of the label to transfer control to. This form is really just a special case of the first form, where the programmer is allowed to specify the label as an expression. Note that if the start of expr is such that it can not be misinterpreted as the first form (i.e. the first token of expr is neither a string nor a symbol), then the VALUE subkeyword can be omitted.

Example: Transferring control to inside a loop

When the control of execution is transferred by a SIGNAL instruction, all active loops at the current procedural level are terminated, i.e. they can not continued later, although they can of course be reentered from the normal start. The consequence of this is that the following code is illegal:

```
do forever
    signal there
there:
    nop
end
```

The fact that the jump is altogether within the loop does not prevent the loop from being terminated. Thus, after the jump to the loop, the END instruction is attempted executed, which will result in a SYNTAX condition {10}. However, if control is transferred out of the loop after the label, but before the END, then it would be legal, i.e. the following is legal:

```
do forever
    signal there
there:
    nop
    signal after
end
after:
```

This is legal, simply because the END instruction is never seen during this script. Although both TRL1

and TRL2 allow this construct, it will probably be disallowed in ANSI.

Just as loops are terminated by a SIGNAL instruction, SELECT and IF instructions are also terminated. Thus, it is illegal to jump to a location within a block of statements contained in a WHEN, OTHERWISE, or IF instruction, unless the control is transferred out of the block before the execution reaches the end of the block.

Whenever execution is transferred during a SIGNAL instruction, the special variable SIGL is set to the line number of the line containing the SIGNAL instruction, before the control is transferred. If this instruction extends over several lines, it refers to the first of this. Note that even blanks are part of a clause, so if the instruction starts with a line continuation, the real line of the instruction is different from that line where the instruction keyword is located.

The third form of syntax is used when the second token in the instruction is either ON or OFF. In both cases must the third token in the instruction be then name of a condition (as a constant string or a symbol, which is taken literally), and the setup of that condition trap is changed. If the second token is OFF, then the trap of the named condition is disabled.

If the second token is ON, then the trap of the named condition is enabled. Further, in this situation two more tokens may be allowed in the instruction: the first must be NAME and the second must be the name of a label (either as a constant string or a symbol, which is taken literally). If the five token form is used, then the label of the condition handler is set to the named label, else the name of the condition handler is set to the default, which is identical to the name of the condition itself.

Note that the NAME subclause of the SIGNAL instruction was a new construct in TRL2, and is not a part of TRL1. Thus, older interpreters may not support it.

Example: Naming condition traps

Note that the default value for the condition handler (if the NAME subclause is not specified) is the name of the condition, not the condition handler from the previous time the condition was enabled. Thus, after the following code, the name of the condition handler for the condition SYNTAX is SYNTAX, not FOOBAR:

```
signal on syntax name foobar
signal on syntax
```

Example: Named condition traps in TRL1

A common problem when trying to port REXX code from a TRL2 interpreter to a TRL1 interpreter, is that explicitly named condition traps are not supported. There exist ways to circumvent this, like:

```
syntax_name = 'SYNTAX_HANDLER'
signal on syntax
if 1 + 2 then /* will generate SYNTAX condition */
nop

syntax:
  oldsigl = sigl
  signal value translate(syntax_name)

syntax_handler:
```

```
say 'condition at line' oldsigl 'is being handled...'
exit
```

Here, a "global" variable is used to store the name of the real condition handler, in the absence of a field for this in the interpreter. This works fine, but there are some problems: the variable SYNTAX_NAME must be exposed to everywhere, in order to be available at all times. It would be far better if this value could be stored somewhere from which it could be retrieved from any part of the script, no matter the current state of the call-stack. This can be fixed with programs like GLOBALV under VM/CMS and putenv under Unix.

Another problem is that this destroys the possibility of setting up the condition handler with the default handler name. However, to circumvent this, add a new DEFAULT_SYNTAX_HANDLER label which becomes the new name for the old SYNTAX label.

Further information about conditions and condition traps are given in chapter Conditions.

The TRACE Instruction

```
TRACE [ setting | [ VALUE ] expr ] ;
```

The TRACE instruction is used to set a tracing mode. Depending on the current mode, various levels of debugging information is displayed for the programmer. Also interactive tracing is allowed, where the user can re-execute clauses, change values of variables, or in general, execute REXX code interactively between the statements of the REXX script.

If no parameters are specified, then the default value N is assumed.

If a parameter is given to the TRACE instruction, and the first token in the parameters is not VALUE, then there must only be one token after TRACE, and it must be either a constant string or a symbol (which is taken literally). The value of this token can be either a whole number or a trace setting.

If the first token after TRACE is VALUE, then the remaining parts of the clause is interpreted as an expression, the result of which is used as the trace setting.

If setting is a whole number and the number is positive, then the number specifies how many interactive pauses to skip if interactive tracing is enabled. If interactive tracing is not enabled, this TRACE instruction is ignored.

If setting is a whole, negative number, then tracing is turned off temporarily for a number of clauses determined by the absolute value of number.

If setting is a symbol or string, but not a whole number, then the first character (following any optional question mark (?) characters) is translated to upper case and must be one of the values specified below. The question mark character toggles interactive tracing on or off.

[A]

(All) Traces all clauses before execution.

[C]

(Commands) Traces all command clauses before execution.

[E]

(Errors) Traces any command that would raise the ERROR condition (whether enabled or not) after execution. Both the command clause and the return value is traced.

[F]

(Failures) Trances any command that would raise the FAILURE condition (whether enabled or not) after execution. Both the command clause and the return value is traced.

[1]

(Intermediate) Traces not only all clauses, but also traces all evaluation of expressions; even intermediate results. This is the most detailed level of tracing.

[L]

(Labels) Traces the name of any label clause executed; whether the label was jumped to or not.

[N]

(Normal or Negative) This is the same as the Failure setting.

[0]

(Off) Turns off all tracing.

[R]

(Results) Traces all clauses and the results of evaluating expressions. However, intermediate expressions are not traced.

The Errors and Failures settings are not influenced by whether the ERROR or FAILURE conditions are enabled or not. These TRACE settings will trace the command and return value after the command have been executed, but before the respective condition is raised.

The levels of tracing might be set up graphically, as in the figure below. An arrow indicates that the setting pointed to is a superset of the setting pointed from.

Hierarchy of TRACE settings

According to this figure, Intermediate is a superset of Result, which is a superset of All. Further, All is a superset of both Commands and Labels. Commands is a superset of Errors, which is a superset of Failures. Both Failure and Labels are supersets of Off. Actually, Command is strictly speaking not a superset of Errors, since Errors traces after the command, while Command traces before the command.

Scan is not part of this diagram, since it provides a completely different tracing functionality. Note that Scan is part of TRL1, but was removed in TRL2. It is not likely to be part of newer REXX interpreters.

The UPPER Instruction

```
UPPER symbol [ symbol [ ...] ] ;
```

The UPPER instruction is used to translate the contents of one or more variables to uppercase. The variables are translated in sequence from left to right.

Each symbol is separated by one or more blanks.

While it is more convenient and probably faster than individual calls to TRANSLATE, UPPER is not part of the ANSI standard and is not common in other interpreters so should be avoided. It is provided to ease porting of programs from CMS.

Only simple and compound symbols can be specified. Specification of a stem variable results in an error.

Operators

An operator represents an operation to be carried out between two terms, such as division. There are 5 groups of operators in the REXX Language: Arithmetic, Assignment, Comparative, Concatenation, and Logical Operators. The groups are shown below in descending order of precedence with further details for group. The defined precedence of operators can be overridden by the use of matching pairs of parentheses: ().

Arithmetic Operators

Arithmetic operators can be applied to numeric constants and REXX variables that evaluate to valid REXX numbers. The following operators are grouped in decreasing order of precedence:

| | 5 . | . | 5 | • | |
|-------------------------|---------------|----------|---|---|--|
| - Unary prefix. Same as | 0 – number. | | | | |
| + Unary prefix. Same a | s 0 + number. | | | | |
| ** Power. | | | | | |
| * Multiply. | | | | | |
| / Divide. | | | | | |

% Integer divide. Divide and return the integer part of the division.

// Remainder divide. Divide and return the remainder of the division.

- + Add.
- Subtract

Assignment Operators

Assignment operators are a means to change the value of a variable on the left of the operator.

Basic Assignment Operators

= Assign the value on the right side of the "=" to the variable on the left.

Shortcut Assignment Operators

Shortcut assignments are an alternate syntax for an operation followed by an assignment. i.e.:

```
a = 1; b = 2

a += b \rightarrow \text{equivalent } \mathbf{to} \ a = a + b
```

These operators are invalid with the STRICT_ANSI option. Introduced in v3.9.1.

Arithmetic Assignment

The existing value of the variable on the left must be numeric.

+= Add the numeric value on the right of the "+=" to the existing value of the variable on the left.

```
x += 1 is equivalent to x = x + 1
```

- -= Subtract the value on the right of the "-=" from the existing value of the variable on the left.
- *= Multiply the existing value of the variable on the left of the "*=" by the value on the right.
- /= Divide the existing value of the variable on the left of the "/=" by the value on the right.

%= Integer divide the existing value of the variable on the left of the "%=" by the value on the right."

//= Remainder divide the existing value of the variable on the left of the "//=" by the value on the right.

Logical Assignment

The existing value of the variable on the left must be Boolean; ie 0 or 1.

|= Apply inclusive or to the existing Boolean value of the variable on the left of the "|=" with the value on the right.

&= Apply logical and to the existing Boolean value of the variable on the left of the "&=" with the value on the right.

&= Apply exclusive or to the existing Boolean value of the variable on the left of the "&&=" with the value on the right.

Concatenation Assignment

||= Append the string on the right of the "||=" to the value of the variable on the left with no intervening space.

Concatenation Operators

The concatenation operators combine two strings to form one, by appending the second string to the right side of the first. The REXX concatenation operators are:

(blank) Concatenation of strings with one space between them.

(abuttal) Concatenation of strings with no intervening space.

|| Concatenation of strings with no intervening space.

Examples:

Comparative Operators

The REXX comparative operators compare two terms and return the logical value 1 if the result of the comparison is true, or 0 if the result of the comparison is false. The non-strict comparative operators will ignore leading or trailing blanks for string comparisons, and leading zeros for numeric comparisons. Numeric comparisons are made if both terms to be compared are valid REXX numbers, otherwise string comparison is done. String comparisons are case sensitive, and the shorter of the two strings is padded with blanks.

The following lists the non-strict comparative operators.

- = Equal
- > Greater than.
- < Less than.
- >= Greater than or equal.

- <= Less than or equal
- <>, >< Greater than or less than. Same as Not equal.

The following lists the strict comparative operators. For two strings to be considered equal when using the strict equal comparative operator, both strings must be the same length.

- == Strictly equal
- >> Strictly greater than.
- << Strictly less than.
- >>= Strictly greater than or equal.
- <== Strictly less than or equal.

Negators

Some of the above comparisons can be negated by prefixing a negator character. Regina supports the following characters as negators:

\ Backslash (ANSI Standard)

- ^ Caret
- ~ Tilde
- ¬ Logical Not

Valid negated comparative operators are (any negator character can be used in place of backslash):

- \= Not equal
- \== Not strictly equal
- \> Not greater than
- \>> Not strictly greater than
- \< Not less than
- \<< Not strictly less than

Logical Operators

Logical operators work with the REXX strings 1 and 0, usually as a result of a comparative operator. These operators also only result in logical TRUE; 1 or logical FALSE; 0. The logical operators are shown in decreasing order of precedence.

& And Returns 1 if both terms are 1, otherwise returns 0.

| Inclusive or Returns 1 if either term is 1, otherwise returns 0.

&& Exclusive or Returns 1 if either term is 1 but not if both terms are 1, otherwise returns 0.

\ Logical not Reverses the result; 0 becomes 1 and 1 becomes 0.

(Any negators listed above can be used in place of backslash)

Special Variables

The REXX Language defines a number of special variables which are set by the interpreter during the execution of a program. There are two types of special variables. The first are special variables that are local in scope and can be changed by the programmer. The second are global in scope and cannot be changed by the programmer.

Local Scope - User Writeable

These variables are local in scope and can be changed by the user at any time. The values of these variables will however be set by the interpreter during the execution of the program.

RC - (ANSI)

This variable is set by any executed command including those executed via ADDRESS. Note that RC is not set for commands executed manually while training interactively.

RESULT - (ANSI)

This variable is set by the RETURN instruction in a subroutine that has been CALLed provided that the RETURN instruction contains an expression. RESULT is dropped if the RETURN instruction contains no expression.

SIGL - (ANSI)

Contains the line number of instruction executed that caused a jump to a label.

Global Scope - Read-Only

As these variables begin with a period, they cannot be changed by the programmer. These variables are global in scope.

.MN - (ANSI)

When a SYNTAX condition has been raised, this variable is set to the error message number (including sub-error number) that caused the SYNTAX condition.

.RC - (ANSI)

Contains the same values as the special variable; RC.

.RS - (ANSI)

This variable is an indicator as to whether the last command executed gave rise to a FAILURE or ERROR condition.

.RESULT - (ANSI)

Contains the same values as the special variable; RESULT.

.LINE - (Regina)

This special variable contains the line number of the REXX program.

.FILE - (Regina)

This special variable contains the fully qualified file name of the REXX program.

.ENDOFLINE - (Regina)

This special variable contains the default end of line character sequence for the platform on which Regina is currently running. In general this will be LF (x0d) on Unix/Linux/Posix platforms CR (x0a) on Mac platforms, and CRLF (x0a0d) on all others.

.DIRSEP - (Regina)

This special variable contains the character that is used by the platform to separate directories in a fully qualified filename or directory name. In general this will be / (x2F) on Unix/Linux/Posix/Mac platforms and / (x5C) on all others.

Implementation-Specific Information

Miscellaneous

OPTIONS settings

Are saved across subroutines, just like other pieces of information, like conditions settings, NUMERIC settings, etc. See chapter Options for more information about OPTIONS settings.

Return value

To the program that called Regina is limited to being an integer, when this is required by the operating systems. All current implementations are for operating systems that require this.

Default return value

From a REXX program is 0 under most systems, specifically Unix, OS/2, MS-DOS. Here, VMS deviates, since it uses 1 as the default return value. Using 0 under VMS tends to make VMS issue a warning saying that no error occurred.

Transferring control into a loop

Works fine in Regina, as long as no END, THEN, ELSE, WHEN, or OTHERWISE instructions are executed afterwards; unless the normal entry-point for the construct has been executed after the transfer of control.

PARSE SOURCE information

PARSE VERSION information

Last line of source code

Is implicitly taken to be terminated by an end-of-line sequence in Regina, even if such a sequence is not present in the source code of the REXX script. This applies only to source code. Also, the end-of-string in INTERPRET strings is taken to be implicitly terminated by an end-of-line character sequence.

Moving code MS-DOS to Unix

Is simplified by Regina, since it will accept the MS-DOS type end of line sequences as valid. i.e. any Ctrl-M in front of a Ctrl-J in the source file is ignored on Unix systems by Regina. This applies only to source code.

Labels in INTERPRET

Is handled by Regina in the following way: A label can occur inside an INTERPRET string, but it is ignored, and can never be jumped to in a SIGNAL or CALL instruction.

Implementation of the ADDRESS environment

Most people have problems invoking external programs. This section shows the basic rules, and some

tricks to let you use Regina and other REXX interpreters successfully.

Every call to an external program is executed by an implicit ADDRESS statement.

'echo Hello planet'

is equivalent to

ADDRESS currentenvironment 'echo Hello planet'

The default environment is SYSTEM in Regina and many other REXX interpreters.

Every ADDRESS environment has its own purpose and advantages. It is a good idea to use ADDRESS in front of each command. Everybody knows what happens in this case. And you can choose the best environment for the command.

SYSTEM aka ENVIRONMENT aka OS2ENVIRONMENT

This is the all-purpose solution for every command. The command is passed to the current command interpreter. It is generally the best option for most commands, but is has some disadvantages:

- You don't have control over the different interpreters. You can get ugly errors in Windows NT, 2000, XP or in unices if you don't know how the interpreter interprets your command.
- You have some trouble passing special characters to the command. Have you every tried to pass a ">" sign to a command? You won't get what you expect if you don't know how to quote it to bypass the interpreter.
- You invoke a separate program just to invoke another program. It costs time and memory usage. Choosing another environment may lead to a quicker and safer execution.

Use SYSTEM if you want to use pipelines and redirections of the interpreter or if you want to use a built-in command of the shell. "echo" is a built-in command in command interpreters. Also, the Unix pipeline of commands like "prog1 | prog2 | prog3" cannot be represented shorter in Regina.

COMMAND aka CMD aka PATH

This is the right ADDRESS environment if you know the called program's name but not where it is on disk. One example is "sort" in many systems.

Since Regina has ANSI's extremely useful ADDRESS WITH technique, you can very effectively sort queue contents or stem leaves by:

ADDRESS PATH 'sort' WITH INPUT STEM unsort. OUTPUT STEM sort.

You let Regina find the program 'sort' (or SORT.EXE if you use Windows) and get the fastest way to do it. You don't have to bother about the current command interpreter; Regina acts as one. You can pass every character you want and Regina does its best to let it appear in the called program. If you want to specify a specific program, simply specify the fully qualified filename of the command to execute.

REXX or REGINA

Use this if you want to execute a REXX program in a separate instance of the interpreter. Whereas a normal CALL on an external program will run the external REXX program in the current instance of

Regina, this allows the external REXX program to run in a new, independent instance of Regina.

Use this environment if:

- 1. The called interpreter is unstable and a crash in it should not affect the current execution. A common situation where you want it, is an external program library you can bind with RxFuncAdd. Such a library can crash or terminate the interpreter. The calling interpreter won't be affected by this termination.
- You want to take advantage of the powerful ADDRESS WITH redirection. The general
 mechanism to communicate with external scripts is a queue, but you don't have this in cases
 where you want to pass error messages in a different way or if you use a script which wasn't
 designed to use queues originally.
- 3. The current interpreter shall be reused and you want to take advantage of the second point. You may have different Regina interpreters and you want to use just the current interpreter even if it isn't in your path. Regina tries to load the current interpreter a second time if you use this ADDRESS environment. There is no difference between ADDRESS REXX and ADDRESS REGINA. Regina also attempts to load the same executable that the current instance was started from, but not every system passes enough informations to Regina to find its own executable in all cases.

ADRRESS WITH on Windows

Redirection of program's input and/or output in general is relatively predictable on most operating systems, however mention must be made of behaviour specific to the Windows platform.

Windows and to a lesser degree OS/2, have techniques to hide windows, to start programs in separate windows and other cool features. Florian did some significant testing of this on all different Windows platforms and there is bad news. There is no consistent mechanism to start external programs without error and full control. Sounds strange, is strange. We have the options to:

- use the interpreter (ADDRESS SYSTEM) or not (ADDRESS PATH or CMD)
- start GUI or text mode programs
- choose the interpreter (CMD.EXE or COMMAND.COM)

The main goal was to start GUIs separately and text mode programs under the control of the caller (GUI or text). Regina can be part of a GUI progress and must be treated as GUI in this case. Most people get upset with console windows popping up showing nothing.

Some combinations of the interpreter, the target programs, and the options we can pass along to the system lead to nonstarting, nonstopping, crashing programs. Or we may loose control by means of broken communications to the subprocess (ADDRESS WITH...).

So we had to choose either to let program run safely OR to let program run pretty. Blame the guys who designed Windows, not the Regina crew!

So, if you have a DOS graphical extension known as Windows 95, Windows 98 or Windows Millennium you will get console windows popping up if run from a GUI program. We are sorry for this, we can't change it.

Those Systems with a 32 bit startup kernel known as Windows NT, Windows 2000, Windows XP will hide the console windows when starting a text mode program from a GUI program.

ATTENTION: Your programs might crash or you may loose control either of the called program or of

Regina if you change the interpreter inside your REXX program. Never use

CALL VALUE 'COMSPEC', something, 'SYSTEM'

in your program if you don't know the consequences! Unpredictable behaviour is likely to occur; use at your own peril!

REXX Built-in Functions

This chapter describes the REXX library of built-in functions. It is divided into three parts:

First a general introduction to built-in functions, pointing out concepts, pitfalls, parameter conventions, peculiarities, and possible system dependencies.

Then there is the reference section, which describes in detail each function in the built-in library.

At the end, there is documentation that describes where and how Regina differs from standard REXX, as described in the two other sections. It also lists Regina's extensions to the built-in library.

It is recommended that you read the first part on first on first reading of this documentation, and that you use the second part as reference. The third part is only relevant if you are going to use Regina.

General Information

This section is an introduction to the built-in functions. It describes common behavior, parameter conventions, concepts and list possible system-dependent parts.

The Syntax Format

In the description of the built-in functions, the syntax of each one is listed. For each of the syntax diagrams, the parts written in italic font names the parameters. Terms enclosed in [square brackets] denote optional elements. And the courier font is used to denote that something should be written as is, and it is also used to mark output from the computer. At the right of each function syntax is an indication of where the function is defined.

- (ANSI) ANSI Standard for REXX 1996
- (EXT-ANSI) Extended REXX
- (SAA) System Application Architecture IBM
- (OS/2) IBM OS/2 REXX
- (CMS) REXX on CMS
- (AREXX) AREXX on Amiga
- (REGINA) Additional function provided by Regina

Definitions of the AREXX built-in functions were taken verbatim in 2003 from http://dfduck.homeip.net/dfd/ados/arexx/main.shtml

Note that in standard REXX it is not really allowed to let the last possible parameter be empty if all commas are included, although some implementations allow it. In the following calls:

```
say D2C( 65 )
say D2C( 65, 1 )
say D2C( 65, )
```

The two first return the string consisting of a single character A, while the last should return error. If the last argument of a function call is omitted, you can not safely include the immediately preceding comma.

Precision and Normalization

The built-in library uses its own internal precision for whole numbers, which may be the range from -999999999 to +999999999. That is probably far more than you will ever need in the built-in functions. For most functions, neither parameters nor return values will be affected by any setting of NUMERIC DIGITS. In the few cases where this does not hold, it is explicitly stated in the description of the function.

In general, only parameters that are required to be whole numbers are used in the internal precision, while numbers not required to be whole numbers are normalized according to the setting of NUMERIC DIGITS before use. But of course, if a parameter is a numeric expression, that expression will be calculated and normalized under the settings of NUMERIC DIGITS before it is given to the function as a parameter.

Standard Parameter Names

In the descriptions of the built-in functions, several generic names are used for parameters, to indicate something about the type and use of that parameter, e.g. valid range. To avoid repeating the same information for the majority of the functions, some common "rules" for the standard parameter names are stated here. These rules implicitly apply for the rest of this chapter.

Note that the following list does not try to classify any general REXX "datatypes", but provides a binding between the sub-datatypes of strings and the methodology used when naming parameters.

Length is a non-negative whole number within the internal precision of the built-in functions. Whether it denotes a length in characters or in words, depends on the context.

String can be any normal character string, including the nullstring. There are no further requirements for this parameter. Sometimes a string is called a "packed string" to explicitly show that it usually contains more than the normal printable characters.

Option is used in some of the functions to choose a particular action, e.g. in DATE() to set the format in which the date is returned. Everything except the first character will be ignored, and case does not matter. note that the string should consequently not have any leading space.

Start is a positive whole number, and denotes a start position in e.g. a string. Whether it refers to characters or words depends on the context. The first position is always numbered 1, unless explicitly stated otherwise in the documentation. Note that when return values denotes positions, the number 0

is generally used to denote a nonexistent position.

Padchar must be a string, exactly one character long. That character is used for padding.

Streamid is a string that identifies a REXX stream. The actual contents and format of such a string is implementation dependent.

Number is any valid REXX number, and will be normalized according to NUMERIC settings before it is used by the function.

If you see one of these names having a number appended, that is only to separate several parameters of the same type, e.g. string1, string2 etc. They still follow the rules listed above. There are several parameters in the built-in functions that do not easily fall into the categories above. These are given other names, and their type and functionality will be described together with the functions in which they occur.

Error Messages

There are several errors that might occur in the built-in functions. Just one error message is only relevant for all the built-in functions, that is number 40 (Incorrect call to routine). In fact, an implementation of REXX can choose to use that for any problem it encounters in the built-in functions. Regina also provides further information in errors in built-in functions, as defined by the ANSI standard. This additional information is provided as sub-error messages and usually provide a more detailed explanation of the error.

Depending on the implementation, other error messages might be used as well. Error message number 26 (Invalid whole number) might be used for any case where a parameter should have been a whole number, or where a whole number is out of range. It is implied that this error message can be used in these situations, and it is not explicitly mentioned in the description of the functions.

Other general error messages that might be used in the built-in functions are error number 41 (Bad arithmetic conversion) for any parameter that should have been a valid REXX number. The error message 15 (Invalid binary or hexadecimal string) might occur in any of the conversion routines that converts from binary or hexadecimal format (B2X(), X2B(), X2C(), X2D()). And of course the more general error messages like error message 5 (Machine resources exhausted) can occur.

Generally, it is taken as granted that these error messages might occur for any relevant built-in function, and this will not be restated for each function. When other error messages than these are relevant, it will be mentioned in the text.

In REXX, it is in general not an error to specify a start position that is larger than the length of the string, or a length that refers to parts of a string that is beyond the end of that string. The meaning of such instances will depend on the context, and are described for each function.

Possible System Dependencies

Some of the functions in the built-in library are more or less system or implementation dependent. The functionality of these may vary, so you should use defensive programming and be prepared for any side-effects that they might have. These functions include:

ADDRESS() is dependent on your operating system and the implementation of REXX, since there is no standard for naming environments.

ARG() at the main level (not in subroutines and functions) is dependent on how your implementation handles and parses the parameters it got from the operating system. It is also dependent on whether the user specifies the -a command line switch.

BITAND(), BITOR() and BITXOR() are dependent on the character set of your machine. Seemingly identical parameters will in general return very different results on ASCII and EBCDIC machines. Results will be identical if the parameter was given to these functions as a binary or hexadecimal literal.

C2X(), C2D(), D2C() and X2C() will be affected by the character set of your computer since they convert to or from characters. Note that if C2X() and C2D() get their first parameter as a binary or hexadecimal literal, the result will be unaffected by the machine type. Also note that the functions B2X(), X2B(), X2D() and D2X() are not affected by the character set, since they do not use character representation.

CHARIN(), CHAROUT(), CHARS(), LINEIN(), LINEOUT(), LINES() and STREAM() are the interface to the file system. They might have system dependent peculiarities in several ways. Firstly, the naming of streams is very dependent on the operating system. Secondly, the operation of stream is very dependent on both the operating system and the implementation. You can safely assume very little about how streams behave, so carefully read the documentation for your particular implementation.

CONDITION() is dependent on the condition system, which in turn depends on such implementation dependent things as file I/O and execution of commands. Although the general operation of this function will be fairly equal among systems, the details may differ.

DATATYPE() and TRANSLATE() know how to recognize upper and lower case letters, and how to transform letters to upper case. If your REXX implementation supports national character sets, the operation of these two functions will depend on the language chosen.

DATE() has the options Month, Weekday and Normal, which produce the name of the day or month in text. Depending on how your implementation handles national character sets, the result from these functions might use the correct spelling of the currently chosen language.

DELWORD(), SUBWORD(), WORD(), WORDINDEX(), WORDLENGTH(), WORDPOS() and WORDS() requires the concept of a "word", which is defined as a non-blank characters separated by blanks. However, the interpretation of what is a blank character depends upon the implementation.

ERRORTEXT() might have slightly different wordings, depending on the implementation, but the meaning and numbering should be the same. However, note that some implementations may have additional error messages, and some might not follow the standard numbering. Error messages may also be returned in the user's native language.

QUEUED() refers to the system specific concept of a "stack", which is either internal or external to the implementation. The result of this function may therefore be dependent on how the stack is implemented on your system.

RANDOM() will differ from machine to machine, since the algorithm is implementation dependent. If you set the seed, you can safely assume that the same interpreter under the same operating system and on the same hardware platform will return a reproducible sequence. But if you change to another interpreter, another machine or even just another version of the operating system, the same seed

might not give the same pseudo-random sequence.

SOURCELINE() has been changed between REXX language level 3.50 and 4.00. In 4.00 it can return 0 if the REXX implementation finds it necessary, and any request for a particular line may get a nullstring as result. Before assuming that this function will return anything useful, consult the documentation.

TIME() will differ somewhat on different machines, since it is dependent on the underlying operating system to produce the timing information. In particular, the granularity and accuracy of this information may vary.

VALUE() will be dependent on implementation and operating system if it is called with its third parameter specified. Consult the implementation specific documentation for more information about how each implementation handles this situation.

XRANGE() will return a string, which contents will be dependent on the character set used by your computer. You can safely make very few assumptions about the visual representation, the length, or the character order of the string returned by this function.

The built-in functions marked as AREXX are available by default on Amiga and AROS systems, but the AREXX_BIFS OPTION is required on other system to make these functions available.

As you can see, even REXX interpreters that are within the standard can differ quite a lot in the builtin functions. Although the points listed above seldom are any problem, you should never assume anything about them before you have read the implementation specific documentation. Failure to do so will give you surprises sooner or later.

And, by the way, many implementations (probably the majority) do not follow the standard completely. So, in fact, you should never assume anything at all. Sorry ...

Blanks vs. Spaces

Note that the description differs between "blanks" and the <space> character. A blank is any character that might be used as "whitespace" to separate text into groups of characters. The <space> character is only one of several possible blanks. When this text says "blank" it means any one from a set of characters that are used to separate visual characters into words. When this text says <space>, it means one particular blank, that which is generally bound to the space bar on a normal computer keyboard.

All implementation can be trusted to treat the <space> character as blank. Additional characters that might be interpreted as blanks (and are treated as such by Regina) are <tab> (horizontal tabulator), <ff> (formfeed), <vt> (vertical tabulator), <nl> (newline) and <cr> (carriage return). The interpretation of what is blank will vary between machines, operating systems and interpreters. If you are using support for national character sets, it will even depend on the language selected. So be sure to check the documentation before you assume anything about blank characters.

Some implementations use only one blank character, and perceives the set of blank characters as equivalent to the <space> character. This will depend on the implementation, the character set, the customs of the operating system and various other reasons.

Regina Built-in Functions

Below follows an in depth description of all the functions in the library of built-in functions. Note that all functions in this section are available on all ports of Regina. Each function is designated as being part of the ANSI standard, or from other implementations. Following sections describe those built-in functions that are available on specific ports of Regina, or when Regina is built with certain switches.

ABBREV(long, short [,length]) - (ANSI)

Returns 1 if the string short is strictly equal to the leading characters of the string long, and returns 0 (zero) otherwise. The minimum length which short must have, can be specified as length. If length is unspecified, length is set to the length of short. The nullstring is an abbreviation of any string.

Note that this function is case sensitive, and that leading and trailing spaces are not stripped off before the two strings are compared.

| ABBREV('Foobar','Foo') | 1 |
|--------------------------|------------------------------|
| ABBREV('Foobar','Foo',4) | 0 /*Too short */ |
| ABBREV('Foobar','foo') | 0 /*Different case */ |
| ABBREV('Foobar','',0) | 1 /* " matches any string */ |
| ABBREV(", 'anything', 0) | 0 /* nothing matches " */ |

ABS(number) - (ANSI)

Returns the absolute value of the number, which can be any valid REXX number. Note that the result will be normalized according to the current NUMERIC settings.

| ABS(-42) | 42 |
|----------|-----|
| ABS(100) | 100 |

ADDRESS([option]) - (ANSI)

Returns the current default environment to which commands are sent or optionally specific details about the targets of command input/output and errors. The value is set with the ADDRESS clause, for more information, see documentation on that clause.

If option is not specified the default option is "N". Option can be:

[N]

(Normal) Returns the current default environment.

[1]

(Input) Returns the target details for input as three words: position type resource.

[0]

(Output) Returns the target details for output as three words: position type resource.

[E]

(Error) Returns the target details for errors as three words: position type resource.

position will be one of: INPUT (for option "I"), APPEND or REPLACE

type will be one of: STEM, STREAM, FIFO, LIFO, NORMAL

resource will be the name of the stem, stream or queue or blank

| ADDRESS() | SYSTEM /* Maybe */ | |
|--|----------------------|--|
| ADDRESS('N') | SYSTEM /* Maybe */ | |
| Defaults: | | |
| ADDRESS('I') | INPUT NORMAL | |
| ADDRESS('O') | REPLACE NORMAL | |
| ADDRESS('E') | REPLACE NORMAL | |
| After: ADDRESS SYSTEM WITH INPUT FIFO 'MYQUEUE' OUTPUT STEM mystem. ERROR APPEND STREAM 'my.err' | | |
| ADDRESS('I') | INPUT FIFO MYQUEUE | |
| ADDRESS('O') | REPLACE STEM MYSTEM. | |
| ADDRESS('E') | APPEND STREAM my.err | |

ARG([argno [,option]]) - (ANSI)

Returns information about the arguments of the current procedure level. For subroutines and functions it will refer to the arguments with which they were called. For the "main" program it will refer to the arguments used when the REXX interpreter was called.

Note that under some operating systems, REXX scripts are run by starting the REXX interpreter as a program, giving it the name of the script to be executed as parameter. Then the REXX interpreter might process the command line and "eat" some or all of the arguments and options. Therefore, the result of this function at the main level is implementation dependent. The parts of the command line which are not available to the REXX script might for instance be the options and arguments meaningful only to the interpreter itself.

Also note that how the interpreter on the main level divides the parameter line into individual arguments, is implementation dependent. The standard seems to define that the main procedure level can only get one parameter string, but don't count on it. On all platforms, Regina will receive one parameter string at the main procedural level, unless Regina is started with the -a switch, when multiple parameter strings are passed in.

For more information on how the interpreter processes arguments when called from the operating system, see the documentation on how to run a REXX script.

When called without any parameters, ARG() will return the number of comma-delimited arguments. Unspecified (omitted) arguments at the end of the call are not counted. Note the difference between using comma and using space to separate strings. Only comma-separated arguments will be interpreted by REXX as different arguments. Space-separated strings are interpreted as different parts of the same argument.

Argno must be a positive whole number. If only argno is specified, the argument specified will be returned. The first argument is numbered 1. If argno refers to an unspecified argument (either omitted or argno is greater than the number of arguments), a nullstring is returned.

If option is also specified, the return value will be 1 or 0, depending on the value of option and on whether the numbered parameter was specified or not. Option can be:

[0]

(Omitted) Returns 1 if the numbered argument was omitted or unspecified. Otherwise, 0 is returned.

[E]

(Existing) Returns 1 if the numbered argument was specified, and 0 otherwise.

If called as:

```
CALL FUNCTION 'This' 'is', 'a',, 'test',,
```

| ARG() | 4 /*Last parameter omitted */ |
|------------|-------------------------------------|
| ARG(1) | 'This is' |
| ARG(2) | 'a' |
| ARG(3) | П |
| ARG(9) | " /*Ninth parameter doesn't exist*/ |
| ARG(2,'E') | 1 |
| ARG(2,'0') | 0 |
| ARG(3,'E') | 0 /*Third parameter omitted */ |
| ARG(9,'0') | 1 |

B2C(binstring) - (AREXX)

Converts a string of binary digits(0,1)into the corresponding(packed)character representation. The conversion is the same as though the argument string had been specified as a literal binary string(e.g. '1010'B). Blanks are permitted in the string,but only at byte boundaries. This function is particularly useful for creating strings that are to be used as bit masks.

B2C('00110011') '3' B2C('01100001') 'A'

B2X(binstring) - (ANSI)

Takes a parameter which is interpreted as a binary string, and returns a hexadecimal string which represent the same information. Binstring can only contain the binary digits 0 and 1 . To increase readability, blanks may be included in binstring to group the digits into groups. Each such group must have a multiple of four binary digits, except from the first group. If the number of binary digits in the first group is not a multiple of four, that group is padded at the left with up to three leading zeros, to make it a multiple of four. Blanks can only occur between binary digits, not as leading or trailing characters.

Each group of four binary digits is translated into on hexadecimal digit in the output string. There will

be no extra blanks in the result, and the upper six hexadecimal digits are in upper case.

| B2X('0010 01011100 0011') | '26C3' |
|---------------------------|--------|
| B2X('10 0101 11111111') | '26FF' |
| B2X('0100100 0011') | '243' |

BEEP(frequency [,duration]) - (OS/2)

Sounds the machine's bell. The frequency and duration (in milliseconds) of the tone are specified. If no duration value is specified, it defaults to 1. Not all operating systems can sound their bells with the given specifications.

BEEP(50, 1000)

BITAND(string1 [,[string2] [,padchar]]) - (ANSI)

Returns the result from bytewise applying the operator AND to the characters in the two strings string1 and string2. Note that this is not the logical AND operation, but the bitwise AND operation. String2 defaults to a nullstring. The two strings are left-justified; the first characters in both strings will be AND'ed, then the second characters and so forth.

The behavior of this function when the two strings do not have equal length is defined by the padchar character. If it is undefined, the remaining part of the longer string is appended to the result after all characters in the shorter string have been processed. If padchar is defined, each char in the remaining part of the longer string is logically AND'ed with the padchar (or rather, the shorter string is padded on the right length, using padchar).

When using this function on character strings, e.g. to uppercase or lowercase a string, the result will be dependent on the character set used. To lowercase a string in EBCDIC, use BITAND() with a padchar value of 'bf'x. To do the same in ASCII, use BITOR() with a padchar value of '20'x.

| BITAND('123456'x,'3456'x) | '101456'x |
|---------------------------------|------------------------|
| BITAND('foobar',,'df'x) | 'FOOBAR' /*For ASCII*/ |
| BITAND('123456'x,'3456'x,'f0'x) | '101450'x |

BITCHG(string, bit) - (AREXX)

Changes the state of the specified bit in the argument string . Bit numbers are defined such that bit 0 is the low-order bit of the rightmost byte of the string.

BITCHG('0313'x,4) '0303'x

BITCLR(string, bit) - (AREXX)

Clears (sets to zero) the specified bit in the argument string . Bit numbers are defined such that bit 0 is the low-order bit of the rightmost byte of the string.

BITCLR('0313'x,4) '0303'x

BITCOMP(string1, string2, bit [,pad]) - (AREXX)

Compares the argument strings bit-by-bit, starting at bit number 0. The returned value is the bit number of the first bit in which the strings differ, or -1 if the strings are identical.

| BITCOMP('7F'x,'FF'x) | '7' |
|----------------------|------|
| BITCOMP('FF'x,'FF'x) | '-1' |

BITOR(string1 [, [string2] [,padchar]]) - (ANSI)

Returns the result from bytewise applying the operator OR to the characters in the two strings string1 and string2. Note that this is not the logical OR operation, but the bitwise OR operation.

String2 defaults to a nullstring. The two strings are left-justified; the first characters in both strings will be OR'ed, then the second characters and so forth.

The behavior of this function when the two strings do not have equal length is defined by the padchar character. If it is undefined, the remaining part of the longer string is appended to the result after all characters in the shorter string have been processed. If padchar is defined, each char in the remaining part of the longer string is logically OR'ed with the padchar (or rather, the shorter string is padded on the right length, using padchar).

When using this function on character strings, e.g. to uppercase or lowercase a string, the result will be dependent on the character set used.

| BITOR('12'x) | '12'x |
|----------------------------|--------------------|
| BITOR('15'x,'24'x) | '35'x |
| BITOR('15'x,'2456'x) | '3556'x |
| BITOR('15'x,'2456'x,'F0'x) | '35F6'x |
| BITOR('1111'x,,'4D'x) | '5D5D'x |
| BITOR('pQrS',,'20'x) | 'pqrs' /* ASCII */ |

BITSET(string, bit) - (AREXX)

Sets the specified bit in the argument string to 1. Bit numbers are defined such that bit 0 is the low-order bit of the rightmost byte of the string.

BITTST(string, bit) - (AREXX)

The boolean return indicates the state of the specified bit in the argument string.

Bit numbers are defined such that bit 0 is the low-order bit of the rightmost byte to the string.

BITTST('0313'x,4) '1'

BITXOR(string1[, [string2] [,padchar]]) - (ANSI)

Works like BITAND(), except that the logical function XOR (exclusive OR) is used instead of AND. For more information see BITAND().

| BITXOR('123456'x,'3456'x) | '266256'x |
|---------------------------------|-------------------------|
| BITXOR('FooBar',,'20'x) | 'fOObAR' /*For ASCII */ |
| BITXOR('123456'x,'3456'x,'f0'x) | '2662A6'x |

BUFTYPE() - (CMS)

This function is used for displaying the contents of the stack. It will display both the string and notify where the buffers are displayed. It is meant for debugging, especially interactive, when you need to obtain information about the contents of the stack. It always returns the nullstring, and takes no parameters.

Here is an example of the output from calling BUFTYPE (note that the second and fourth buffers are empty):

```
==> Lines: 4
==> Buffer: 3
"fourth line pushed, in third buffer"
==> Buffer: 2
==> Buffer: 1
"third line pushed, in first buffer"
==> Buffer: 0
"second line pushed, in 'zeroth' buffer" "first line pushed, in 'zeroth' buffer"
==> End of Stack
```

C2B(string) - (AREXX)

Converts the supplied string into the equivalent string of binary digits.

```
C2B('abc') '011000010110001001100011'
```

C2D(string [,length]) - (ANSI)

Returns a whole number, which is the decimal representation of the packed string string, interpreted as a binary number. If length (which must be a non-negative whole number) is specified, it denotes the number of characters in string to be converted, and string is interpreted as a two's complement representation of a binary number, consisting of the length rightmost characters in string. If length is not specified, string is interpreted as an unsigned number.

If length is larger than the length of string, string is sign-extended on the left. i.e. if the most significant bit of the leftmost char of string is set, string is padded with 'ff'x chars at the left side. If the bit is not set, '00'x chars are used for padding.

If length is too short, only the length rightmost characters in string are considered. Note that this will not only in general change the value of the number, but it might even change the sign.

Note that this function is very dependent on the character set that your computer is using.

If it is not possible to express the final result as a whole number under the current settings of NUMERIC DIGITS, and STRICT_ANSI option is in effect, an error is reported. The number to be returned will not be stored in the internal representation of the built-in library, so size restrictions on whole numbers that generally applies for built-in functions, do not apply in this case.

| C2D('foo') | '6713199' /*For ASCII machines */ |
|----------------|-----------------------------------|
| C2D('103'x) | '259' |
| C2D('103'x,1) | '3' |
| C2D('103'x,2) | '259' |
| C2D('0103'x,3) | '259' |
| C2D('ffff'x,2) | '-1' |
| C2D('ffff'x) | '65535' |
| C2D('ffff'x,3) | '65535' |
| C2D('fff9'x,2) | '-6' |
| C2D('ff80'x,2) | '-128' |

C2X(string) - (ANSI)

Returns a string of hexadecimal digits that represents the character string string. Converting is done bytewise, the six highest hexadecimal digits are in uppercase, and there are no blank characters in the result Leading zeros are not stripped off in the result. Note that the behavior of this function is dependent on the character set that your computer is running (e.g. ASCII or EBCDIC).

| C2X('ffff'x) | 'FFFF' |
|-----------------------|----------------------------------|
| C2X('Abc') | '416263' /*For ASCII Machines */ |
| C2X('1234'x) | '1234' |
| C2X('011 0011 1101'b) | '033D' |

CD(directory) - (REGINA)

CHDIR(directory) - (REGINA)

Changes the current process's directory to the directory specified. A more portable, though non-standard alternative is to use the DIRECTORY BIF.

CHDIR('/tmp/aa') /* new directory now /tmp/aa */

CENTER(string, length [, padchar]) - (ANSI)

CENTRE(string, length [, padchar]) - (ANSI)

This function has two names, to support both American and British spelling. It will center string in a

string total of length length characters. If length (which must be a non-negative whole number) is greater than the length of string, string is padded with padchar or <space> if padchar is unspecified. If length is smaller than the length of string character will be removed.

If possible, both ends of string receives (or loses) the same number of characters. If an odd number of characters are to be added (or removed), one character more is added to (or removed from) the right end than the left end of string.

| CENTER('Foobar',10) | ' Foobar ' |
|-------------------------|--------------|
| CENTER('Foobar',11) | ' Foobar ' |
| CENTRE('Foobar',3) | 'oob' |
| CENTER('Foobar',4) | 'ooba' |
| CENTER('Foobar',10,'*') | '**Foobar**' |

CHANGESTR(needle, haystack, newneedle) - (ANSI)

The purpose of this function is to replace all occurrences of needle in the string haystack with newneedle. The function returns the changed string.

If haystack does not contain needle, then the original haystack is returned.

| CHANGESTR('a','fred','c') | 'fred' |
|--|-------------|
| CHANGESTR(",",'x') | П |
| CHANGESTR('a','abcdef','x') | 'xbcdef' |
| CHANGESTR('0','0','1') | '1' |
| CHANGESTR('a','def','xyz') | 'def' |
| CHANGESTR('a','','x') | ш |
| CHANGESTR(",'def','xyz') | 'def' |
| CHANGESTR('abc','abcdef','xyz') | 'xyzdef' |
| CHANGESTR('abcdefg','abcdef','xyz') | 'abcdef' |
| CHANGESTR('abc','abcdefabccdabcd','z') | 'zdefzcdzd' |

CHARIN([streamid] [,[start] [,length]]) - (ANSI)

This function will in general read characters from a stream, and return a string containing the characters read. The streamid parameter names a particular stream to read from. If it is unspecified, the default input stream is used.

The start parameter specifies a character in the stream, on which to start reading. Before anything is read, the current read position is set to that character, and it will be the first character read. If start is unspecified, no repositioning will be done. Independent of any conventions of the operating system, the first character in a stream is always numbered 1. Note that transient streams do not allow repositioning, and an error is reported if the start parameter is specified for a transient stream.

The length parameter specifies the number of characters to read. If the reading did work, the return string will be of length length. There are no other ways to know many characters were read other than checking the length of the return value. After the read, the current read position is moved forward as many characters as was read. If length is unspecified, it defaults to 1. If length is 0, nothing is read, but the file might still be repositioned if start was specified.

Note that this function reads the stream raw. Some operating systems use special characters to differentiate between separate lines in text files. On these systems these special characters will be returned as well. Therefore, never assume that this function will behave identically for text streams on different systems.

What happens when an error occurs or the End-Of-File (EOF) is seen during reading, is implementation dependent. The implementation may choose to set the NOTREADY condition (does not exist in REXX language level 3.50). For more information, see chapter on Stream Input and Output.

(Assuming that the file "/tmp/file" contains the first line: "This is the first line"):

| CHARIN() | 'F' /*Maybe*/ |
|-------------------------|--------------------|
| CHARIN(,,6) | 'Foobar' /*Maybe*/ |
| CHARIN('/tmp/file',,6) | 'This i' |
| CHARIN('/tmp/file',4,6) | 's is t' |

CHAROUT([streamid] [,[string] [,start]]) - (ANSI)

In general this function will write string to a streamid . If streamid is not specified the default output stream will be used.

If start is specified, the current write position will be set to the startth character in streamid, before any writing is done. Note that the current write position can not be set for transient streams, and attempts to do so will report an error. Independent of any conventions that the operating system might have, the first character in the stream is numbered 1. If start is not specified, the current write position will not be changed before writing.

If string is omitted, nothing is written, and the effect is to set the current write position if start is specified. If neither string nor start is specified, the implementation can really do whatever it likes, and many implementations use this operation to close the file, or flush any changes. Check implementation specific documentation for more information.

The return value is the number of characters in string that was not successfully written, so 0 denotes a successful write. Note that in many REXX implementations there is no need to open a stream; it will be implicitly opened when it is first used in a read or write operation.

(Assuming the file referred to by outdata was empty, it will contain the string FoobWow afterwards. Note that there might will not be an End-Of-Line marker after this string, it depends on the implementation.)

| CHAROUT(,'Foobar') | '0' |
|---------------------------|-----|
| CHAROUT(outdata,'Foobar') | '0' |
| CHAROUT(outdata,'Wow',5) | '0' |

CHARS([streamid]) - (ANSI)

Returns the number of characters left in the named streamid , or the default input stream if streamid is unspecified. For transient streams this will always be either 1 if more characters are available, or 0 if the End-Of-File condition has been met. For persistent streams the number of remaining bytes in

the file will be possible to calculate and the true number of remaining bytes will be returned.

However, on some systems, it is difficult to calculate the number of characters left in a persistent stream; the requirements to CHARS() has therefore been relaxed, so it can return 1 instead of any number other than 0. If it returns 1, you can therefore not assume anything more than that there is at least one more character left in the input stream.

| CHARS() | '1' /* more data on def. input stream | |
|------------------|---------------------------------------|--|
| CHARS() | '0' /* EOF for def. input stream */ | |
| CHARS('outdata') | '94' /* maybe */ | |

CLOSE(file) - (AREXX)

Closes the file specified by the given logical name. The returned value is a boolean success flag, and will be 1 unless the specified file was not open. Use OPTIONS AREXX_SEMANTICS for the AREXX behaviour to be executed.

COMPARE(string1, string2 [,padchar]) - (ANSI)

This function will compare string1 to string2, and return a whole number which will be 0 if they are equal, otherwise the position of the first character at which the two strings differ is returned. The comparison is case-sensitive, and leading and trailing space do matter.

If the strings are of unequal length, the shorter string will be padded at the right hand end with the padchar character to the length of the longer string before the comparison. If a padchar is not specified, <space> is used.

| COMPARE('FooBar','Foobar') | '4' |
|---------------------------------|-----|
| COMPARE('Foobar','Foobar') | '0' |
| COMPARE('Foobarrr','Fooba') | '6' |
| COMPARE('Foobarrr','Fooba','r') | '0' |

COMPRESS(string [,list]) - (AREXX)

If the list argument is omitted, the function removes leading, trailing, or embedded blank characters from the string argument. If the optional list is supplied, it specifies the characters to be removed from the string .

| COMPRESS(' why not ') | 'whynot' |
|----------------------------|----------|
| COMPRESS('++12-34-+','+-') | '1234' |

CONDITION([option]) - (ANSI)

Returns information about the current trapped condition. A condition becomes the current trapped condition when a condition handler is called (by CALL or SIGNAL) to handle the condition. The parameter option specifies what sort of information to return:

[C]

(Condition) The name of the current trapped condition is return, this will be one of the condition named legal to SIGNAL ON, like SYNTAX, HALT, NOVALUE, NOTREADY, ERROR or FAILURE.

[D]

(Description) A text describing the reason for the condition. What to put into this variable is implementation and system dependent.

[E]

(Extra) The error code (a single number) and a sub-error code if available (two numbers and a period; eg 40.5) that was generated by the condition.

[1]

(Instruction) Returns either CALL or SIGNAL, depending on which method was current when the condition was trapped.

[S]

(State) The current state of the current trapped condition. This can be one of ON, OFF or DELAY. Note that this option reflect the current state, which may change, not the state at the time when the condition was trapped.

For more information on conditions, consult the chapter Conditions. Note that condition may in several ways be dependent on the implementation and system, so read system and implementation dependent information too.

COPIES(string, copies) - (ANSI)

Returns a string with copies concatenated copies of string. Copies must be a non-negative whole number. No extra space is added between the copies.

| COPIES('Foo',3) | 'FooFooFoo' |
|------------------|------------------------|
| COPIES('*',16) | '************ * |
| COPIES('Bar ',2) | 'Bar Bar ' |
| COPIES(",10000) | 11 |

COUNTSTR(needle, haystack) - (ANSI)

Returns a count of the number of occurrences of needle in haystack that do not overlap.

| COUNTSTR(",") | 0 |
|------------------------|---|
| COUNTSTR('a','abcdef') | 1 |
| COUNTSTR(0,0) | 1 |
| COUNTSTR('a','def') | 0 |
| COUNTSTR('a','') | 0 |
| COUNTSTR(",'def') | 0 |

| COUNTSTR('abc','abcdef') | 1 |
|-----------------------------------|---|
| COUNTSTR('abcdefg','abcdef' | 0 |
| COUNTSTR('abc','abcdefabccdabcd') | 3 |

CRYPT(string, salt) - (REGINA)

Encrypts the given string using the supplied salt and returns the encrypted string. Only the first two characters of salt are used. Not all operating systems support encryption, and on these platforms, the string is returned unchanged. It is also important to note that the encrypted string is not portable between platforms.

CRYPT('a string', '1x') '1xYwPPWI1zRJs' /* maybe */

DATATYPE(string [,option]) - (ANSI)

With only one parameter, this function identifies the "datatype" of string. The value returned will be "NUM" if string is a valid REXX number. Otherwise, "CHAR" is returned. Note that the interpretation of whether string is a valid number will depend on the current NUMERIC settings.

If option is specified too, it will check if string is of a particular datatype, and return either "1" or "0" depending on whether string is or is not, respectively, of the specified datatype. The possible values of option are:

[A]

(Alphanumeric) Consisting of only alphabetic characters (in upper, lower or mixed case) and decimal digits.

[B]

(Binary) Consisting of only the two binary digits 0 and 1. Note that blanks are not allowed within string, as would have been allowed within a binary string. The nullstring is also considered a valid binary value.

[L]

(Lower) Consisting of only alphabetic characters in lower case.

[M]

(Mixed) Consisting of only alphabetic characters, but the case does not matter (i.e. upper, lower or mixed.)

[N]

(Numeric) If string is a valid REXX number, i.e. DATATYPE(string) would return NUM.

[S]

(Symbolic) Consists of characters that are legal in REXX symbols. Note that this test will pass several strings that are not legal symbols. The characters includes plus, minus and the decimal point.

Last update: 2024/09/04 06:58

[U]

(Upper) Consists of only upper case alphabetic characters.

[W]

(Whole) If string is a valid REXX whole number under the current NUMERIC setting. Note that 13.0 is a whole number since the decimal part is zero.

[X]

(Hexadecimal) Consists of hexadecimal digits, i.e. the decimal digits 0-9 and the alphabetic characters A-F in either case (or mixed). Blanks are allowed within string, as long as they appear between pairs of hexadecimal digits. The nullstring is also considered a valid hexadecimal value.

If you want to check whether a string is suitable as a variable name, you should consider using the SYMBOL() function instead, since the Symbolic option only verifies which characters string contains, not the order. You should also take care to watch out for lower case alphabetic characters, which are allowed in the tail of a compound symbol, but not in a simple or stem symbol or in the head of compound symbol.

Also note that the behavior of the options A, L, M and U might depend on the setting of language, if you are using an interpreter that supports national character sets.

| DATATYPE(' - 1.35E-5 ') | 'NUM' |
|---|--------|
| DATATYPE('1E999999999') | 'CHAR' |
| DATATYPE('1E9999999999') | 'CHAR' |
| DATATYPE('!@#&#\$(&*%`')</td><td>'CHAR'</td></tr><tr><td>DATATYPE('FooBar','A')</td><td>'1'</td></tr><tr><td>DATATYPE('Foo Bar','A')</td><td>'0'</td></tr><tr><td>DATATYPE('010010111101','B')</td><td>'1'</td></tr><tr><td>DATATYPE('0100 1011 1101','B')</td><td>'0'</td></tr><tr><td>DATATYPE('foobar','L')</td><td>'1'</td></tr><tr><td>DATATYPE('FooBar','M')</td><td>'1'</td></tr><tr><td>DATATYPE(' -34E3 ','N')</td><td>'1'</td></tr><tr><td>DATATYPE('A_SYMBOL!?!','S')</td><td>'1'</td></tr><tr><td>DATATYPE('1.23.39E+4.5','S')</td><td>'1'</td></tr><tr><td>DATATYPE('Foo bar','S')</td><td>'0'</td></tr><tr><td>DATATYPE('FOOBAR','U')</td><td>'1'</td></tr><tr><td>DATATYPE('123deadbeef','X')</td><td>'1'</td></tr><tr><td></td><td></td></tr></tbody></table> | |

DATE([opt_out [,date [,opt_in[,sep_out[,sep_in]]]]) - (ANSI+)

This function returns information relating to the current local date. If the opt_out character is specified, it will set the format of the return string. The default value for opt out is " N ".

Possible options are:

[B]

(Base) The number of complete days from January 1st 0001 until yesterday inclusive, as a whole number. This function uses the Gregorian calendar extended backwards. Therefore Date('B') // 7 will equal the day of the week where 0 corresponds to Monday and 6 Sunday. (ANSI)

[C]

(Century) The number of days in this century from January 1st -00 until today, inclusive. The return value will be a positive integer. (Regina Extension)

[D]

(Days) The number of days in this year from January 1st until today, inclusive. The return value will be a positive integer. (ANSI)

[E]

(European) The date in European format, i.e. "dd/mm/yy". If any of the numbers is single digit, it will have a leading zero. (ANSI)

[1]

(ISO) Returns the date according the format specified by International Standards Organization Standard ISO 8601:2004. The format will be "yyyy-mm-dd", and each part is padded with leading zero where appropriate. (Regina Extension)

[M]

(Month) The unabbreviated name of the current month, in English. (ANSI)

[N]

(Normal) Return the date with the name of the month abbreviated to three letters, with only the first letter in upper case. The format will be "dd Mmm yyyy", where Mmm is the month abbreviation (in English) and dd is the day of the month, without leading zeros. (ANSI)

[0]

(Ordered) Returns the date in the ordered format, which is "yy/mm/dd". (ANSI)

[S]

(Standard/Sorted) Returns the date according the format specified by International Standards Organization Standard ISO 2014-1976 (E). The format will be "yyyymmdd", and each part is padded with leading zero where appropriate. (ANSI)

[U]

(USA) Returns the date in the format that is normally used in USA, i.e. "mm/dd/yy", and each part is padded with leading zero where appropriate. (ANSI)

[W]

(Weekday) Returns the English unabbreviated name of the current weekday for today. The first letter of the result is in upper case, the rest is in lower case. (ANSI)

[T]

Last update: 2024/09/04 06:58

(time_t) Returns the current UTC date/time in UNIX time_t format. time_t is the number of seconds since January 1st 1970. It always represents the UTC date/time, so any conversion from another date format (which is always assumed to be local time) will result in a time_t value offset by time zone. (Regina Extension)

Note that the "C" option is present in REXX language level 3.50, but was removed in level 4.00. The new "B" option should be used instead. When porting code that use the "C" option to an interpreter that only have the "B" option, you will can use the conversion that January 1st 1900 is day 693595 in the Gregorian calendar.

Note that none of the formats in which DATE() returns its result are affected by the NUMERIC settings. Also note that if there is more than one call to DATE() (or TIME()) in a single clause of REXX code, all of them will use the same basis data for calculating the date (or time).

If the REXX interpreter contains national support, some of these options may return different output for the names of months and weekdays.

Assuming that today is January 6th 1992:

| '727203' |
|--------------|
| '33609' |
| '6' |
| '06/01/92' |
| 'January' |
| '6 Jan 1992' |
| '92/01/06' |
| '19920106' |
| '01/06/92' |
| 'Monday' |
| 694620000 |
| '1992-01-06' |
| |

If the date option is specified, the function provides for date conversions. The optional opt_in specifies the format in which date is supplied. The possible values for opt_in are: BDEOUNSTI. The default value for opt in is N.

When a date is converted to format T, the returned value is the input date with a time of 00:00:00.

| DATE('O','13 Feb 1923') | '23/02/13' |
|--------------------------|------------|
| DATE('O','06/01/50','U') | '50/06/01' |

If the date supplied does not include a century in its format, then the result is chosen to make the year within 50 years past or 49 years future of the current year.

The date conversion capability of the DATE BIF was introduced with the ANSI standard.

If the sep_out option is provided, the character used to separate the components of the returned date can be changed. Any non-alphanumeric character can be used as the separator. This option can only be used when opt out is one of ENOSUI. The default separator for each option is:

| E | " <i>[</i> " |
|---|-------------------|
| N | " " (space) |
| 0 | " <i>[</i> " |
| S | "" (empty string) |
| U | " <i>[</i> " |
| I | u_n |

Assuming that today is January 6th 1992:

| DATE('N',,,,'_') | '6_Jan_1992' |
|--------------------------------|--------------|
| DATE('O','06/01/50','U','') | '500601' |
| DATE('S','13 Feb 1996',N','-') | 1996-02-13 |

If the separator of the date components of date are different to the defaults specified above, then the sep in option needs to be provided to specify what separator is being used.

| DATE('O','06.01.50','U','','.') | '500601' |
|---------------------------------|------------|
| DATE('S','13-02-96',E','-','-') | 1996-02-13 |

The sep_out and sep_in options are extensions to the ANSI standard originally provided by Object REXX.

DELSTR(string, start [,length]) - (ANSI)

Returns string , after the substring of length length starting at position start has been removed. The default value for length is the rest of the string. Start must be a positive whole number, while length must be a non-negative whole number. It is not an error if start or length (or a combination of them) refers to more characters than string holds

| DELSTR('Foobar',4) | 'Foo' |
|----------------------|----------|
| DELSTR('Foobar',4,2) | 'Foor' |
| DELSTR('Foobar',4,4) | 'Foo' |
| DELSTR('Foobar',7) | 'Foobar' |

DELWORD(string,start[,length]) (ANSI)

Removes length words and all blanks between them, from string , starting at word number start . The default value for length is the rest of the string. All consecutive spaces immediately after the last deleted word, but no spaces before the first deleted word is removed. Nothing is removed if length is zero.

The valid range of start is the positive whole numbers; the first word in string is numbered 1. The valid range of length is the non-negative integers. It is not an error if start or length (or a combination of them) refers to more words than string holds.

| DELWORD('This is a test',3) | 'This is ' |
|-------------------------------|---------------|
| DELWORD('This is a test',2,1) | 'This a test' |
| DELWORD('This is a test',2,5) | 'This' |

DELWORD('This is a test',1,3) test' /*No leading space*/

DESBUF() - (CMS)

This function removes all buffers on the stack, it is really just a way of clearing the whole stack for buffers as well as strings. Functionally, it is equivalent to executing DROPBUF with a parameter of 0. (Actually, this is a lie, since DROPBUF is not able to take zero as a parameter. Rather, it is equivalent to executing DROPBUF with 1 as parameter and then executing DROPBUF without a parameter, but this is a subtle point.) It will return the number of buffers left on the stack after the function has been executed. This should be 0 in all cases.

DESBUF() 0

DIGITS() - (ANSI)

Returns the current precision of arithmetic operations. This value is set using the NUMERIC DIGITS statement. For more information, refer to the documentation on NUMERIC DIGITS.

DIRECTORY([new directory]) - (OS/2)

Returns the current directory for the running process, and optionally changes directory to the specified new directory . If the new directory exists, and the change to new directory succeeds, the new directory is returned. If the new directory does not exist or an error occurred changing to that new directory , the empty string is returned.

| DIRECTORY() | '/tmp' /* Maybe */ |
|----------------------|-----------------------|
| DIRECTORY('c:\temp') | 'c:\temp' /* Maybe */ |

D2C(integer [,length]) - (ANSI)

Returns a (packed) string, that is the character representation of integer , which must be a whole number, and is governed by the settings of NUMERIC DIGITS , not of the internal precision of the built-in functions. If length is specified the string returned will be length bytes long, with sign extension. If length (which must be a non-negative whole number) is not large enough to hold the result, an error is reported.

If length is not specified, integer will be interpreted as an unsigned number, and the result will have no leading <nul> characters. If integer is negative, it will be interpreted as a two's complement, and length must be specified.

| D2C(0) | '00'x |
|------------|---|
| D2C(65) | 'A' /* on ASCII machines */ |
| D2C(127) | '7F'x |
| D2C(128) | '80'x |
| D2C(128,3) | '000080'x |
| D2C(-128) | Error 40.13 and SYNTAX condition raised |

| D2C(-10,3) 'fffff | 5'x |
|-------------------|-----|
|-------------------|-----|

D2X(integer [,length]) - (ANSI)

Returns a hexadecimal number that is the hexadecimal representation of integer . If integer is not a whole number under the current settings of NUMERIC DIGITS , and STRICT_ANSI option is in effect, Error 40.35 is reported.

If length is not specified, then integer must be non-negative, and the result will be stripped of any leading zeros.

If length is specified, then the resulting string will be sign-extended to length, truncating leading characters if necessary.

| D2X(0) | '0' |
|--|--|
| טעא(ט) | U |
| D2X(65) | '41' |
| D2X(127) | '7F' |
| D2X(128) | '80' |
| D2X(128,5) | '00080' |
| D2X(-128) | Error 40.13 and SYNTAX condition raised |
| D2X(-128,5) | 'FFF80' |
| D2X(888888) | 'D9038' |
| D2X(888888,3) | '038' |
| D2X(128) D2X(128,5) D2X(-128) D2X(-128,5) D2X(8888888) | '80' '00080' Error 40.13 and SYNTAX condition rais 'FFF80' 'D9038' |

DROPBUF([number]) - (CMS)

This function will remove zero or more buffers from the stack. Called without a parameter, it will remove the topmost buffer from the stack, provided that there were at least one buffer in the stack. If there were no buffers in the stack, it will remove all strings in the stack, i.e. remove the zeroth buffer.

If the parameter number was specified, and the stack contains a buffer with an assigned number equal to number, then that buffer itself, and all strings and buffers above it on the stack will be removed; but no strings or buffers below the numbered buffer will be touched. If number refers to a buffer that does not exist in the stack; no strings or buffers in the stack is touched.

As an extra extension, in Regina the DROPBUF() built-in function can be given a non-positive integer as parameter. If the name is negative then it will convert that number to its absolute value, and remove that many buffers, counted from the top. This is functionally equivalent to repeating DROPBUF() without parameters for so many times as the absolute value of the negative number specifies. Note that using -0 as parameter is equivalent to removing all strings and buffers in the stack, since -0 is equivalent to normal 0. The number is converted during evaluation of parameters prior to the call to the DROPBUF() routine, so the sign is lost.

The value returned from this function is the number of buffers left on the stack after the buffers to be deleted have been removed. Obviously, this will be a non-negative integer. This too, deviates from the behavior of the DROPBUF command under CMS, where zero is always returned.

| DROPBUF(3) | 2 /* remove buffer 3 and 4 */ |
|------------|----------------------------------|
| DROPBUF(4) | 0 /* no buffers on the stack */ |
| DROPBUF() | 4 /* if there where 5 buffers */ |

Last update: 2024/09/04 06:58 **EOF(file) - (AREXX)**

Checks the specified logical file name and returns the boolean value 1(True) if the end-of-file has been reached, and 0(False)otherwise. Use OPTIONS AREXX_SEMANTICS for the AREXX behaviour to be executed.

EOF('infile') '1' /* maybe */

ERRORTEXT(errorno [, lang]) - (ANSI)

Returns the REXX error message associated with error number errorno . If the lang character is specified, it will determine the native language in which the error message is returned. The default value for lang is " N".

Possible options are:

[N]

(Normal) The error text is returned in the default native language.

[S]

(Standard English) The error text is returned in English.

For more information on how Regina supports different native languages, see Native Language Support.

If the error message is not defined, a nullstring is returned.

| ERRORTEXT(20) | 'Symbol expected' |
|---------------|-----------------------------|
| | 'Name or string too long' |
| ERRORTEXT(40) | 'Incorrect call to routine' |

errorno can also be specified as an errorno followed by a sub error number, with a period between. The resulting string will be the text of the sub-error number with place-markers indicating where substitution values would normally be placed.

```
ERRORTEXT(40.24) < bif> argument 1 must be a binary string; found "<value>"
```

Regina also supports messages in several native languages. See the section on Native Language Support for details on how this is configured. With DE as the native language in effect:

| ERRORTEXT(40.24) | Routine <bif>, Argument 1 muß eine Binätzeichenkette sein; "<value>"</value></bif> |
|----------------------|--|
| ERRORTEXT(40.24,'S') | <bif> argument 1 must be a binary string; found "<value>"</value></bif> |

The error messages in REXX might be slightly different between the various implementations. The ANSI standard says that errno must be in the range 0-90, but in some implementations it might be within a less restricted range which gives room for system specific messages. You should in general not assume that the wordings and ordering of the error messages are constant between implementations and systems.

With OPTIONS STRICT ANSI, Regina will return an error if errorno is larger than 90:

| ERRORTEXT(200) | ERRORTEXT argument 1, must have an integer part in the range 0:90 and a |
|----------------|---|
| | ERRORTEXT argument 1, must have an integer part in the range 0:90 and a decimal part no larger than .9; found 200 |

With OPTIONS NOSTRICT_ANSI (the default) Regina treats any errorno larger than 100 as an operating system error. Regina first subtracts 100 from errorno and then obtains the text for errorno from the operating system. This facility is used to replace the now deprecated UNIXERROR BIF.

| ERRORTEXT | 200) Network is down /* system errno 100 | */ |
|-----------|---|----|
| ERRORTEXT | 777) Unknown error /* system errno 677 */ | |

EXISTS(filename) - (AREXX)

Tests whether the specified name of the given filename exists. The filename string may include any portion of a full file path specification. Note that the argument is not a logical file name used in other ARexx file functions. A more portable equivalent of this is to use the 'QUERY EXISTS' command of the STREAM BIF.

EXISTS('c:\temp\infile.txt') | '1' /* maybe */

EXPORT(address, [string], [length] [,pad]) - (AREXX)

Copies data from the (optional) string into a previously-allocated memory area, which must be specified as a 4-byte address. The length parameter specifies the maximum number of characters to be copied; the default is the length of the string. If the specified length is longer than the string, the remaining area is filled with the pad character or nulls('00'x). The returned value is the number of characters copied.

Caution is advised in using this function. Any area of memory can be overwritten, possibly causing a system crash.

See also STORAGE() and IMPORT().

Note that the address specified is subject to a machine's endianess.

EXPORT('0004 0000'x,'The answer') '10'

FILESPEC(option, filespec) - (OS/2)

Returns the specified portion of a passed filespec, depending on the option passed. Possible options are:

[Drive]

The file's drive. On platforms that don't have the concept of a drive letter, returns blank.

[Name]

The file's name. This is the string following the last path delimiter (if there is one).

Last update: 2024/09/04 06:58

[Path]

The file's path. This is the string up to, and including the last path delimiter.

Only the first letter of option is required.

| FILESPEC('Drive','C:\config.sys') | 'C' |
|-------------------------------------|--------------|
| FILESPEC('Name','C:\config.sys') | 'config.sys' |
| FILESPEC('Path','C:\config.sys') | '\' |
| FILESPEC('Drive','/usr/bin/regina') | П |
| FILESPEC('Name','/usr/bin/regina') | 'regina' |
| FILESPEC('Path','/usr/bin/regina') | '/usr/bin/' |

FIND(string, phrase) - (CMS)

Searches string for the first occurrence of the sequence of blank-delimited words phrase, and return the word number of the first word of phrase in string. Multiple blanks between words are treated as a single blank for the comparison. Returns 0 if phrase not found. Deprecated: see WORDPOS().

| FIND('now is the time','is the time') | 2 |
|---------------------------------------|---|
| FIND('now is the time','is the') | 2 |
| FIND('now is the time','is time') | 0 |

FORK() - (REGINA)

This function spawns a new process as a child of the current process at the current point in the program where FORK is called. The program then continues from this point as two separate processes; the parent and the child. FORK returns 0 to the child process, and the process id of the child process spawned to the parent (always non-zero). A negative return value indicates an error while attempting to create the new process. FORK is not available on all platforms. If FORK is not supported, it will always return '1'. It is safe to assume that a return value of '1' means that FORK is not supported. All platforms AFAIK, will never return '1' as a child process id; that number is usually reserved for the first process that starts on a machine.

| FORK() '0' /* To child */ | |
|---------------------------|------------------------------|
| | '3456' /* maybe to parent */ |

FORM() - (ANSI)

Returns the current "form", in which numbers are presented when exponential form is used. This might be either SCIENTIFIC (the default) or ENGINEERING. This value is set through the NUMERIC FORM clause. For more information, see the documentation on NUMERIC FORM.

FORM() 'SCIENTIFIC' /* Maybe */

FORMAT(number [,[before] [,[after] [,[expp] [,[expt]]]]) - (ANSI)

This function is used to control the format of numbers, and you may request the size and format in which the number is written. The parameter number is the number to be formatted, and it must be a

valid REXX number. note that before any conversion or formatting is done, this number will be normalized according to the current NUMERIC settings.

The before and after parameters determines how many characters that are used before and after the decimal point, respectively. Note that before does not specify the number of digits in the integer part, it specifies the size of the field in which the integer part of the number is written. Remember to allocate space in this field for a minus too, if that is relevant. If the field is not long enough to hold the integer part (including a minus if relevant), an error is reported.

The after parameter will dictate the size of the field in which the fractional part of the number is written. The decimal point itself is not a part of that field, but the decimal point will be omitted if the field holding the fractional part is empty. If there are less digits in the number than the size of the field, it is padded with zeros at the right. If there is more digits then it is possible to fit into the field, the number will be rounded (not truncated) to fit the field.

Before must at least be large enough to hold the integer part of number. Therefore it can never be less than 1, and never less than 2 for negative numbers. The integer field will have no leading zeros, except a single zero digit if the integer part of number is empty.

The parameter expp the size of the field in which the exponent is written. This is the size of the numeric part of the exponent, so the "E" and the sign comes in addition, i.e. the real length if the exponent is two more than expp specifies. If expp is zero, it signalizes that exponential form should not be used. Expp must be a non-negative whole number. If expp is positive, but not large enough to hold the exponent, an error is reported.

Expt is the trigger value that decides when to switch from simple to exponential form. Normally, the default precision (NUMERIC DIGITS) is used, but if expt is set, it will override that. Note that if expt is set to zero, exponential form will always be used. However, if expt tries to force exponential form, simple form will still be used if expp is zero. Negative values for expt will give an error.

Exponential form is used if more digits than expt is needed in the integer part, or more than twice expt digits are needed in the fractional part.

Note that the after number will mean different things in exponential and simple form. If after is set to e.g. 3, then in simple form it will force the precision to 0.001, no matter the magnitude of the number. If in exponential form, it will force the number to 4 digits precision.

| FORMAT(12.34,3,4) | ' 12.3400' |
|----------------------|---------------|
| FORMAT(12.34,3,,3,0) | ' 1.234E+001' |
| FORMAT(12.34,3,1) | ' 12.3400' |
| FORMAT(12.34,3,0) | ' 12.3' |
| FORMAT(12.34,3,4) | ' 12' |
| FORMAT(12.34,,,,0) | '1.234E+1' |
| FORMAT(12.34,,,0) | '12.34' |
| FORMAT(12.34,,,0,0) | '12.34' |

FREESPACE(address, length) - (AREXX)

Returns a block of memory of the given length to the interpreter's internal pool. The address argument must be a 4-byte string obtained by a prior call to GETSPACE(), the internal allocator. It is

not always necessary to release internally-allocated memory, since it will be released to the system when the program terminates. However, if a very large block has been allocated, returning it to the pool may avoid memory space problems. The return value is a boolean success flag.

See also GETSPACE()

FREESPACE('00042000'x,32) '1'

FUZZ() - (ANSI)

Returns the current number of digits which are ignored when comparing numbers, during operations like = and >. The default value for this is 0. This value is set using the NUMERIC FUZZ statement, for more information see that.

FUZZ() '0' /* Maybe */

GETCALLER([level]) - (REGINA)

Returns the fully qualified file name of the REXX program that called the current program. The optional argument level specifies the level in Regina's call stack you wish to query. The immediate level is 1, the level above that is 2, etc. If not specified level is 1. Where level exceeds Regina's call stack this function returns the empty string.

| GETCALLER() | 'C:\regina\fred1.rexx' /* (Maybe) */ |
|---------------|--------------------------------------|
| GETCALLER(1) | 'C:\regina\fred1.rexx' /* (Maybe) */ |
| GETCALLER() | " /* this program called from OS */ |
| GETCALLER(55) | '' /* (Probably) */ |

GETCALLSTACK([stem]) - (REGINA)

If the optional argument stem is provided, populates that array with the contents of the current call stack. If no stem argument is provided the current call stack is sent to stderr. Each item in the array contains the line number from which the routine was called followed by the routine name.

GETCALLSTACK('stack.') 2' /* stack.0 (Maybe) */

GETENV(environmentvar) - (REGINA)

Returns the value of the environment variable from the system. If this variable is not defined, a nullstring is returned. It is not possible to use this function to determine whether the variable was unset, or just set to the nullstring.

This function is now obsolete, instead you should use:

VALUE(environmentvar, ,'SYSTEM')

GETPID() - (REGINA)

Returns the process id of the currently running process.

GETSPACE(length) - (AREXX)

Allocates a block of memory of the specified length from the interpreter's internal pool. The returned value is the 4-byte address of the allocated block, which is not cleared or otherwise initialized. Internal memory is automatically returned to the system when the REXX program terminates, so this function should not be used to allocate memory for use by external programs. See also FREESPACE()

GETTID() - (REGINA)

Returns the thread id of the currently running process.

HASH(string) - (AREXX)

Returns the hash attribute of a string as a decimal number, and updates the internal hash value of the string.

IMPORT(address [,length]) - (AREXX)

Creates a string by copying data from the specified 4-byte address. If the length parameter is not supplied, the copy terminates when a null byte is found.

See also EXPORT()

Note that the address specified is subject to a machine's endianess.

INDEX(haystack, needle [,start]) - (CMS)

Returns the character position of the string needle in haystack . If needle is not found, 0 is returned. By default the search starts at the first character of haystack (start is 1). This can be overridden by giving a different start , which must be a positive, whole number. See POS function for an ANSI function that does the same thing.

| INDEX('abcdef','cd') | '3' |
|----------------------|-----|
| INDEX('abcdef','xd') | '0' |

| INDEX('abcdef','bc',3) | '0' |
|------------------------|-----|
| INDEX('abcabc','bc',3) | '5' |
| INDEX('abcabc','bc',6) | '0' |

INSERT(string1, string2 [,position [,length [,padchar]]]) - (ANSI)

Returns the result of inserting string1 into a copy of string2. If position is specified, it marks the character in string2 which string1 it to be inserted after. Position must be a non-negative whole number, and it defaults to 0, which means that string2 is put in front of the first character in string1.

If length is specified, string1 is truncated or padded on the right side to make it exactly length characters long before it is inserted. If padding occurs, then padchar is used, or <space> if padchar is undefined.

| INSERT('first','SECOND') | 'firstSECOND' |
|-----------------------------------|-----------------|
| INSERT('first','SECOND',3) | 'SECfirstOND ' |
| INSERT('first','SECOND',3,10) | 'SECfirst OND ' |
| INSERT('first','SECOND',3,10,'*') | 'SECfirst*OND ' |
| INSERT('first','SECOND',3,4) | 'SECfirsOND ' |
| INSERT('first','SECOND',8) | 'SECOND first' |

JUSTIFY(string, length [,pad]) - (CMS)

Formats blank-delimited words in string, by adding pad characters between words to justify to both margins. That is, to width length (length must be non-negative). The default pad character is a blank.

string is first normalized as though SPACE(string) had been executed (that is, multiple blanks are converted to single blanks, and leading and trailing blanks are removed). If length is less than the width of the normalized string, the string is then truncated on the right and any trailing blank is removed. Extra pad characters are then added evenly from the left to right to provide the required length, and the blanks between words are replaced with the pad character.

| JUSTIFY('The blue sky',14) | 'The blue sky' |
|-------------------------------|----------------|
| JUSTIFY('The blue sky',8) | 'The blue' |
| JUSTIFY('The blue sky',9) | 'The blue' |
| JUSTIFY('The blue sky',9,'+') | 'The++blue' |

LASTPOS(needle, haystack [,start]) - (ANSI)

Searches the string haystack for the string needle, and returns the position in haystack of the first character in the substring that matched needle. The search is started from the right side, so if needle occurs several times, the last occurrence is reported.

If start is specified, the search starts at character number start in haystack. Note that the standard only states that the search starts at the startth character. It is not stated whether a match can partly be to the right of the start position, so some implementations may differ on that point.

| LASTPOS('be', 'To be or not to be') | 17 |
|--|----|
| LASTPOS('to', 'to be or not to be',10) | 3 |

| LASTPOS('is', 'to be or not to be') | 0 |
|---------------------------------------|---|
| LASTPOS('to', 'to be or not to be',0) | 0 |

LEFT(string, length [,padchar]) - (ANSI)

Returns the length leftmost characters in string. If length (which must be a non-negative whole number) is greater than the length of string, the result is padded on the right with <space> (or padchar if that is specified) to make it the correct length.

| LEFT('Foo bar',5) | 'Foo b' |
|------------------------|--------------|
| LEFT('Foo bar',3) | 'Foo' |
| LEFT('Foo bar',10) | 'Foo bar ' |
| LEFT('Foo bar',10,'*') | 'Foo bar***' |

LENGTH(string) - (ANSI)

Returns the number of characters in string.

| LENGTH(") | '0' |
|---------------------|------|
| LENGTH('Foo') | '3' |
| LENGTH('Foo bar') | '7' |
| LENGTH(' foo bar ') | '10' |

LINEIN([streamid][,[line][,count]]) - (ANSI)

Returns a line read from a file. When only streamid is specified, the reading starts at the current read position and continues to the first End-Of-Line (EOL) mark. Afterward, the current read position is set to the character after the EOL mark which terminated the read-operation. If the operating system uses special characters for EOL marks, these are not returned by as a part of the string read.

The default value for streamid is default input stream. The format and range of the string streamid are implementation dependent.

The line parameter (which must be a positive whole number) might be specified to set the current position in the file to the beginning of line number line before the read operation starts. If line is unspecified, the current position will not be changed before the read operation. Note that line is only valid for persistent steams. For transient streams, an error is reported if line is specified. The first line in the stream is numbered 1.

Count specifies the number of lines to read. However, it can only take the values 0 and 1. When it is 1 (which is the default), it will read one line. When it is 0 it will not read any lines, and a nullstring is returned. This has the effect of setting the current read position of the file if line was specified.

What happens when the functions finds a End-Of-File (EOF) condition is to some extent implementation dependent. The implementation may interpret the EOF as an implicit End-Of-Line (EOL) mark is none such was explicitly present. The implementation may also choose to raise the NOTREADY condition flag (this condition is new from REXX language level 4.00).

Whether or not stream must be explicitly opened before a read operation can be performed, is

Last update: 2024/09/04 06:58

implementation dependent. In many implementations, a read or write operation will implicitly open the stream if not already open.

Assuming that the file /tmp/file contains the three lines: "First line", Second line" and "Third line":

| LINEIN('/tmp/file',1) | 'First line' |
|-------------------------|--------------------------------|
| LINEIN('/tmp/file') | 'Second line' |
| LINEIN('/tmp/file',1,0) | " /* But sets read position */ |
| LINEIN('/tmp/file') | 'First line' |
| LINEIN() | 'Hi, there!' /* maybe */ |

LINEOUT([streamid] [,[string] [,line]]) - (ANSI)

Returns the number of lines remaining after having positioned the stream streamid to the start of line line and written out string as a line of text. If streamid is omitted, the default output stream is used. If line (which must be a positive whole number) is omitted, the stream will not be repositioned before the write. If string is omitted, nothing is written to the stream. If string is specified, a system-specific action is taken after it has been written to stream, to mark a new line.

The format and contents of the first parameter will depend upon the implementation and how it names streams. Consult implementation-specific documentation for more information.

If string is specified, but not line, the effect is to write string to the stream, starting at the current write position. If line is specified, but not string, the effect is only to position the stream at the new position. Note that the line parameter is only legal if the stream is persistent; you can not position the current write position for transient streams.

If neither line nor string is specified, the standard requires that the current write position is set the end of the stream, and implementation specific side-effects may occur. In practice, this means that an implementation can use this situation to do things like closing the stream, or flushing the output. Consult the implementation specific documentation for more information.

Also note that the return value of this functions may be of little or no value, If just a half line is written, 1 may still be returned, and there are no way of finding out how much (if any) of string was written. If string is not specified, the return value will always be 0, even if LINEOUT() was not able to correctly position the stream.

If it is impossible to correctly write string to the stream, the NOTREADY flag will be raised. It is not defined whether or not the NOTREADY flag is raised when LINEOUT() is used for positioning, and this is not possible.

Note that if you write string to a line in the middle of the stream (i.e. line is less than the total number of lines in the stream), then the behavior is system and implementation specific. Some systems will truncate the stream after the newly written line, other will only truncate if the newly written line has a different length than the old line which it replaced, and yet other systems will overwrite and never truncate.

In general, consult your system and implementation specific documentation for more information about this function. You can safely assume very little about how it behaves.

| LINEOUT(,'First line') | '1' |
|------------------------|-----|
|------------------------|-----|

| LINEOUT('/tmp/file','Second line',2) | '1' |
|--------------------------------------|-----|
| LINEOUT('/tmp/file','Third line') | '1' |
| LINEOUT('/tmp/file','Fourth line',4) | '0' |

LINES([streamid] [,option]) - (ANSI)

Returns 1 if there is at least one complete line remaining in the named file stream or 0 if no complete lines remain in the file. A complete line is not really as complete as the name might indicate; a complete line is zero or more characters, followed by an End-Of-Line (EOL) marker. So, if you have read half a line already, you still have a "complete" line left. Note that it is not defined what to do with a half-finished line at the end of a file. Some interpreters might interpret the End-Of-File as an implicit EOL mark too, while others might not.

The format and contents of the stream streamid is system and implementation dependent. If omitted, the default input stream will be used.

The ANSI Standard has extended this function from TRL2. It allows an option:

[C]

(Count) Returns the actual number of complete lines remaining in the stream, irrespective of how expensive this operation is.

[N]

(Normal) Returns 1 if there is at least one complete line remaining in the file or 0 if no lines remain. This is the default. To maintain backwards compatibility with older releases of Regina, the OPTION; NOFAST_LINES_BIF_DEFAULT can be used to make the default option behave as though LINES(streamid,'C') was specified.

LINES will only return 0 or 1 for all transient streams, as the interpreter can not reposition in these files, and can therefore not count the number of remaining lines.

As a result, defensive programming indicates that you can safely only assume that this function will return either 0 or a non-zero result. If you want to use the non-zero result to more than just an indicator on whether more lines are available, you must check that it is larger than one. If so, you can safely assume that it hold the number of available lines left.

As with all the functions operating on streams, you can safely assume very little about this function, so consult the system and implementation specific documentation.

| LINES() | '1' /* Maybe */ |
|------------------------|-----------------|
| LINES() | '0' /* Maybe */ |
| LINES('/tmp/file','C') | '2' /* Maybe */ |
| LINES('/tmp/file') | |

LOWER(string [,start [,length [,pad]]]) - (REGINA)

Translates the substring of string that starts at start, and has the length length to lower case. Length defaults to the rest of the string. Start must be a positive whole number, while length can be any non-negative whole number. The default value for start is 1 and for length is the length of string.

It is not an error for start to be larger than the length of string. If length is specified and the sum of length and start minus 1 is greater that the length of string, then the result will be padded with padchars to the specified length. The default value for padchar is the <space> character.

If a specific locale is set (via the -I switch), then the string is set to the correct lowercase values based on that locale.

| LOWER('One Fine Day') | 'one fine day' |
|--------------------------|----------------|
| LOWER('FRED', 2) | 'Fred' |
| LOWER('FRED', 3, 1) | 'FreD' |
| LOWER('FRED',1, 10, '*') | 'fred***** |

MAKEBUF() - (CMS)

Creates a new buffer on the stack, at the current top of the stack. Each new buffer will be assigned a number; the first buffer being assigned the number 1. A new buffer will be assigned a number which is one higher than the currently highest number of any buffer on the stack. In practice, this means that the buffers are numbered, with the bottom-most having the number 1 and the topmost having a number which value is identical to the number of buffers currently in the stack.

The value returned from this function is the number assigned to the newly created buffer. The assigned number will be one more than the number of buffers already in the stack, so the numbers will be "recycled". Thus, the assigned numbers will not necessarily be in sequence.

| MAKEBUF() | 1 /* if no buffers existed */ |
|-----------|-------------------------------|
| MAKEBUF() | 6 /* if 5 buffers existed */ |

MAX(number1 [,number2] ...) - (ANSI)

Takes any positive number of parameters, and will return the parameter that had the highest numerical value. The parameters may be any valid REXX number. The number that is returned, is normalized according to the current NUMERIC settings, so the result need not be strictly equal to any of the parameters.

Actually, the standard says that the value returned is the first number in the parameter list which is equal to the result of adding a positive number or zero to any of the other parameters. Note that this definition opens for "strange" results if you are brave enough to play around with the settings of NUMERIC FUZZ.

| MAX(1,2,3,5,4) | '5' |
|------------------|-------|
| MAX(6) | '6' |
| MAX(-4,.001E3,4) | '4' |
| MAX(1,2,05.0,4) | '5.0' |

MIN(number [,number] ...) - (ANSI)

Like MAX(), except that the lowest numerical value is returned. For more information, see MAX().

| MIN(5,4,3,1,2) | '1' |
|----------------|-----|
|----------------|-----|

| MIN(6) | '6' |
|--------------------|--------|
| MIN(-4,.001E3,4) | '-4' |
| MIN(1,2,05.0E-1,4) | '0.50' |

OPEN(file, filename, ['Append'|'Read'|'Write']) - (AREXX)

Opens a file for the specified operation. The file argument defines the logical name by which the file will be referenced. The filename is the external name of the file, and may include any portions of a full file path.

The function returns a boolean value that indicates whether the operation was successful. There is no limit to the number of files that can be open simultaneously, and all open files are closed automatically when the program exits.

Use OPTIONS AREXX_SEMANTICS for the AREXX behaviour to be executed. See also CLOSE(), READ(), WRITE().

| OPEN('myfile','c:\temp\aa.txt','R') | '1' |
|-------------------------------------|-----|
| OPEN('infile','/tmp/fred.txt') | '1' |

OVERLAY(string1, string2 [,[start] [,[length] [,padchar]]]) -(ANSI)

Returns a copy of string2, totally or partially overwritten by string1. If these are the only arguments, the overwriting starts at the first character in string2.

If start is specified, the first character in string1 overwrites character number start in string2. Start must be a positive whole number, and defaults to 1, i.e. the first character of string1. If the start position is to the right of the end of string2, then string2 is padded at the right hand end to make it start -1 characters long, before string1 is added.

If length is specified, then string2 will be stripped or padded at the right hand end to match the specified length. For padding (of both strings) padchar will be used, or <space> if padchar is unspecified. Length must be non-negative, and defaults to the length of string1.

| OVERLAY('NEW','old-value') | 'NEW-value' |
|-------------------------------------|--------------------|
| OVERLAY('NEW','old-value',4) | 'oldNEWlue' |
| OVERLAY('NEW','old-value',4,5) | 'oldNEW e' |
| OVERLAY('NEW','old-value',4,5,'*') | 'oldNEW**e' |
| OVERLAY('NEW','old-value',4,2) | 'oldNEalue' |
| OVERLAY('NEW','old-value',9) | 'old-valuNEW' |
| OVERLAY('NEW','old-value',12) | 'old-value NEW' |
| OVERLAY('NEW','old-value',12,,'*') | 'old-value**NEW' |
| OVERLAY('NEW','old-value',12,5,'*') | 'old-value**NEW**' |

POOLID() - (REGINA)

Returns the current call level for the current procedure.

| POOLID() | '1' /* top level */ |
|----------|---------------------|
| 1 11 | |

POOLID() '6' /* 6th level call nesting */

POPEN(command [,stem.]) - (REGINA)

Runs the operating system command. If the optional stem. is supplied all output from the command is placed in the specified stem variable as a REXX array. Note that only the command's stdout can be captured.

This command is now deprecated. ADDRESS WITH can do the same thing, and can also capture the command's stderr.

| POPEN('ls -l', 'lists.') | /* LISTS. stem has list */ | |
|--|----------------------------|--|
| ADDRESS SYSTEM 'Is -I' WITH OUTPUT STEM LISTS. | /* same as above */ | |

POS(needle, haystack [,start]) - (ANSI)

Seeks for an occurrence of the string needle in the string haystack. If needle is not found, then 0 is returned. Else, the position in haystack of the first character in the part that matched is returned, which will be a positive whole number. If start (which must be a positive whole number) is specified, the search for needle will start at position start in haystack.

| POS('be','to be or not to be') | 4 |
|--|---|
| POS('to','to be or not to be',10) POS('is','to be or not to be') | |
| | |

PUTENV(environmentvar=[value]) - (REGINA)

Sets the value of the named system environment variable or deletes it. The existing value is returned if the environment variable has a value or if this environment variable is not defined, a nullstring is returned.

If no value is supplied, the system environment variable is deleted. This is the only mechanism available to delete a system environment variable.

| PUTENV('FRED=hello') | " /* If unset */ |
|----------------------|--------------------------------|
| PUTENV('FRED=') | 'hello' /* variable deleted */ |

QUALIFY([streamid]) - (ANSI)

Returns a name for the streamid. The two names are currently associated with the same resource and the result of this function may be more persistently associated with that resource.

QUALIFY('../mypath/fred.the') //home/mark/mypath/fred.the

QUEUED() - (ANSI)

Returns the number of lines currently in the external data queue (the "stack"). Note that the stack is

a concept external to REXX, this function may depend on the implementation and system Consult the system specific documentation for more information.

| | '0' /* Maybe */ |
|----------|------------------|
| QUEUED() | '42' /* Maybe */ |

RANDOM(max) - (ANSI)

RANDOM([min] [,[max] [,seed]]) - (ANSI)

Returns a pseudo-random whole number. If called with only the first parameter, the first format will be used, and the number returned will be in the range 0 to the value of the first parameter, inclusive. Then the parameter max must be a non-negative whole number, not greater than 100000.

If called with more than one parameter, or with one parameter, which is not the first, the second format will be used. Then min and max must be non-negative whole numbers, and max can not be less than min, and the difference max - min can not be more than 100000. If one or both of them is unspecified, the default for min is 0, and the default for max is 999.

If seed is specified; (it must be a non-negative whole number) you may control which numbers the pseudo-random algorithm will generate. If you do not specify it, it will be set to some "random" value at the first call to RANDOM() (typically a function of the time). When specifying seed, it will effect the result of the current call to RANDOM().

The standard does not require that a specific method is to be used for generating the pseudo-random numbers, so the reproducibility can only be guaranteed as long as you use the same implementation on the same machine, using the same operating system. If any of these change, a given seed may produce a different sequence of pseudo-random numbers.

Note that depending on the implementation, some numbers might have a slightly increased chance of turning up than other. If the REXX implementation uses a 32 bit pseudo-random generator provided by the operating system and returns the remainder after integer dividing it by the difference of min and max, low numbers are favored if the 2^32 is not a multiple of that difference. Supposing that the call is RANDOM(100000) and the pseudo-random generator generates any 32 bit number with equal chance, the change of getting a number in the range 0-67296 is about 0.000010000076, while the changes of getting a number in the range 67297-100000 is about 0.000009999843.

A much worse problem with pseudo-random numbers are that they sometimes do not tend to be random at all. Under one operating system (name withheld to protect the guilty), the system's pseudo-random routine returned numbers where the last binary digit alternated between 0 and 1. On that machine, RANDOM(1) would return the series 0, 1, 0, 1, 0, 1, 0, 1 etc., which is hardly random at all. You should therefore never trust the pseudo-random routine to give you random numbers.

Note that due to the special syntax, there is a big difference between using RANDOM(10) and RANDOM(10,). The former will give a pseudo-random number in the range 0-10, while the latter will give a pseudo-random number in the range 10-999.

Also note that it is not clear whether the standard allows min to be equal to max, so to program compatible, make sure that max is always larger than min.

| RANDOM() | '123' /*Between 0 and 999 */ | ٦ |
|----------|------------------------------|---|
|----------|------------------------------|---|

| RANDOM(10) | '5' /*Between 0 and 10 */ | |
|-----------------|---|--|
| RANDOM(,10) | '3' /*Between 0 and 10 */ | |
| RANDOM(20,30) | '27' /*Between 20 and 30 */ | |
| RANDOM(,,12345) | '765' /*Between 0 and 999, and sets seed */ | |

RANDU([seed]) - (AREXX)

Returns a uniformly-distributed pseudo random number between 0 and 1. The number of digits of precision in the result is always equal to the current NUMERIC DIGITS setting. With the choice of suitable scaling and translation values, RANDU()can be used to generate pseudo random numbers on an arbitrary interval.

The optional seed argument is used to initialize the internal state of the random number generator. See also RANDOM()

| RANDU() | '0.371902021' |
|-----------|------------------------------|
| RANDU(45) | '0.873' /*numeric digits 3*/ |

READCH(file, length) - (AREXX)

Reads the specified number of characters from the given logical file and returns them. The length of the returned string is the actual number of characters read, and may be less than the requested length if, for example, the end-of-file was reached.

See also READLN()

READCH('infile',10) 'a string o'

READLN(file) - (AREXX)

Reads characters from the given logical file into a string until a "newline" character is found. The returned string does not include the "newline".

See also READCH()

READLN('infile') 'a string of chars'

REVERSE(string) - (ANSI)

Returns a string of the same length as string, but having the order of the characters reversed.

| REVERSE('FooBar') | 'raBooF' |
|---------------------|------------|
| REVERSE(' Foo Bar') | 'raB ooF ' |
| REVERSE('3.14159') | '95141.3' |

RIGHT(string, length[,padchar]) - (ANSI)

Returns the length rightmost characters in string. If length (which must be a non-negative whole

number) is greater than the length of string the result is padded on the left with the necessary number of padchars to make it as long as length specifies. Padchar defaults to <space>.

| RIGHT('Foo bar',5) | 'o bar' |
|-------------------------|---------------|
| RIGHT('Foo bar',3) | 'bar' |
| RIGHT('Foo bar',10) | ' Foo bar' |
| RIGHT('Foo bar',10,'*') | ''***Foo bar' |

RXFUNCADD(externalname, library, internalname) - (SAA)

Registers the internalname in library as an external function callable from with the current program by referencing externalname. library is a REXX external function package in the format of shared library or dynamic link library (DLL). library and internalname are case-sensitive. library is the base name of the shared library or dynamic link library. On platforms that support DLLs, the full name of the external function package is library.dll. On Unix environments, the full name of the shared library is lib library.a (AIX), lib library.sl (HPUX) or lib library.so (most other Unixes).

External function packages are searched for in the location where shared libraries or DLLs are normally found by the operating system. DLLs are normally located in directories specified in the PATH or LIBPATH environment variables. Shared libraries are normally searched for in LD_LIBRARY_PATH or LIBPATH environment variables.

This function returns 0 if the function is registered successfully; non-zero otherwise.

RXFUNCADD('SQLLoadFuncs', 'rexxsql', 'SQLLoadFuncs') 0

RXFUNCDROP(externalname) - (SAA)

Removes the specified externalname from the list of external functions available to be called. This function returns 0 if the function was successfully dropped.

RXFUNCDROP('SQLLoadFuncs') 0

RXFUNCERRMSG() - (REGINA)

Returns the error message associated with the last call to RXFUNCADD. This function is generally used immediately after a failed call to RXFUNCADD to determine why it failed.

|RXFUNCERRMSG()|rexxsql.dll not found' /* Maybe */

RXFUNCQUERY(externalname) - (SAA)

Returns 0 if the externalname is already registered, or 1 if the externalname is not registered.

RXFUNCQUERY('SQLLoadFuncs') 1 /* Maybe */

RXQUEUE(command [,queue|timeout]) - (OS/2)

This function interfaces to the Regina internal or external queue mechanism. If OPTIONS

INTERNAL QUEUES is set, all operations on queues are internal to the interpreter.

[C]

(Create) Request the interpreter or rxstack to create a new named queue. If the queue name already exists, a new unique queue name is generated. The name of the queue that was created (either the specified queue or the system-generated queue) is returned. All queue names are case-insensitive; i.e. the queue name FRED and fred are the same.

[D]

(Delete) Deletes the specified queue. The default queue; SESSION becomes the current queue.

[G]

(Get) Returns the current queue name.

[S]

(Set) Sets the current queue name to that queue specified. The previously current queue is returned. It is valid to set a queue name to a queue that has not been created.

[T]

(Timeout) Sets the timeout period (in milliseconds) to wait for something to appear on the current queue (as set by RXQUEUE('S', queue)). By default, when a line is read from a queue with a PULL command, it either returns immediately with the top line in the stack, or it will wait for a line to be entered by the user via the process' stdin. If 0 is specified, Regina will wait forever for a line to be ready on the stack.

An error will result if an attempt is made to set a timeout on an internal queue; timeouts only make sense on external queues (ie those with a '@' in them that use the rxstack process).

| 'S0738280' |
|------------|
| 'FRED' |
| 'S88381' |
| 'S88381' |
| 'SESSION' |
| 'SESSION' |
| '0' |
| |

SEEK(file, offset, ['Begin'|'Current'|'End') - (AREXX)

Moves to a new position in the given logical file, specified as an offset from an anchor position. The default anchor is Current. The returned value is the new position relative to the start of the file.

| SEEK('infile',10,'B') | '10' |
|-----------------------|-------------------------|
| SEEK('infile',0,'E') | '356' /* file length */ |

SHOW(option, [name], [pad]) - (AREXX)

Returns the names in the resource list specified by the option argument, or tests to see whether an entry with the specified name is available. The currently implemented options keywords are Clip, Files, Libraries, and Ports, which are described below.

Clip. Examines the names in the Clip List.

Files. Examines the names of the currently open logical file names.

Libraries. Examines the names in the Library List, which are either function libraries or function hosts.

Ports. Examine the names in the system Ports List.

If the name argument is omitted, the function returns a string with the resource names separated by a blank space or the pad character, if one was supplied. If the name argument is given, the returned boolean value indicates whether the name was found in the resource list. The name entries are case-sensitive.

Only the Files option is valid on all platforms. All other values for option are only applicable to the Amiga and AROS ports.

SIGN(number) - (ANSI)

Returns either -1 , 0 or 1 , depending on whether number is negative, zero, or positive, respectively. Number must be a valid REXX number, and are normalized according to the current settings of NUMERIC before comparison.

| SIGN(-12) | '-1' |
|-------------------|------|
| SIGN(42) | '1' |
| SIGN(-0.00000012) | '-1' |
| SIGN(0.000) | '0' |
| SIGN(-0.0) | '0' |

SLEEP(seconds) - (CMS)

Pauses for the supplied number of seconds.

SLEEP(5) /* sleeps for 5 seconds */

SOURCELINE([lineno]) - (ANSI)

If lineno (which must be a positive whole number) is specified, this function will return a string containing a copy of the REXX script source code on that line. If lineno is greater than the number of lines in the REXX script source code, an error is reported.

If lineno is unspecified, the number of lines in the REXX script source code is returned.

Note that from REXX language level 3.50 to 4.00, the requirements of this function were relaxed to simplify execution when the source code is not available (compiled or pre-parsed REXX). An implementation might make two simplifications: to return 0 if called without a parameter. If so, any call to SOURCELINE() with a parameter will generate an error. The other simplification is to return a

nullstring for any call to SOURCELINE() with a legal parameter.

Note that the code executed by the INTERPRET clause can not be retrieved by SOURCELINE().

| SOURCELINE() | '42' /*Maybe */ | |
|----------------|-------------------------------|--|
| SOURCELINE(1) | '/* This REXX script will */' | |
| SOURCELINE(23) | 'var = 12' /*Maybe */' | |

SPACE(string[, [length] [,padchar]]) - (ANSI)

With only one parameter string is returned, stripped of any trailing or leading blanks, and any consecutive blanks inside string translated to a single <space> character (or padchar if specified).

Length must be a non-negative whole number. If specified, consecutive blanks within string are replaced by exactly length instances of <space> (or padchar if specified). However, padchar will only be used in the output string, in the input string, blanks will still be the "magic" characters. As a consequence, if there exist any padchars in string, they will remain untouched and will not affect the spacing.

| SPACE(' Foo bar ') | 'Foo bar' |
|-------------------------|-----------|
| SPACE(' Foo bar ',2) | 'Foo bar' |
| SPACE(' Foo bar ',,'*') | 'Foo*bar' |
| SPACE('Foo bar',3, '-') | 'Foo—bar' |
| SPACE('Foo bar',,'o') | 'Fooobar' |

STATE(streamid) - (CMS)

Returns 0 if the streamid exists, or 1 if it does not. Use STREAM(streamid, 'C', 'QUERY EXISTS') for portability.

STORAGE([address], [string], [length], [pad]) - (AREXX)

Calling STORAGE() with no arguments returns the available system memory. If the address argument is given, it must be a 4-byte string, and the function copies data from the optional string into the indicated memory area. The length parameter specifies the maximum number of bytes to be copied, and defaults to the length of the string. If the specified length is longer than the string, the remaining area is filled with the pad character or nulls('00'x.)

The returned value is the previous contents of the memory area. This can be used in a subsequent call to restore the original contents.

Caution is advised in using this function. Any area of memory can be overwritten, possibly causing a system crash.

| STORAGE() | '248400' |
|------------------------------------|------------------------|
| STORAGE('0004 0000'x,'The answer') | 'question' /* maybe */ |

STREAM(streamid[,option[,command]]) (ANSI)

This function was added to REXX in language level 4.00. It provides a general mechanism for doing operations on streams. However, very little is specified about how the internal of this function should work, so you should consult the implementation specific documentation for more information.

The streamid identifies a stream. The actual contents and format of this string is implementation dependent.

The option selects one of several operations which STREAM() is to perform. The possible operations are:

[C]

(Command) If this option is selected, a third parameter must be present, command, which is the command to be performed on the stream. The contents of command is implementation dependent. For Regina, the valid commands follow. Commands consist of one or more space separated words.

[D]

(Description) Returns a description of the state of streamid. The return value is implementation dependent.

[S]

(Status) Returns a state which describes the state of streamid. The standard requires that it is one of the following: ERROR, NOTREADY, READY and UNKNOWN. The meaning of these are described in the chapter; Stream Input and Output.

Note that the options Description and Status really have the same function, but that Status in general is implementation independent, while Description is implementation dependent. The command specifies the command to be performed on streamid. The possible operations are:

[READ]

Open for read access. The file pointer will be positioned at the start of the file, and only read operations are allowed. This command is Regina-specific; use OPEN READ in its place.

[WRITE]

Open for write access and position the current write position at the end of the file. An error is returned if it was not possible to get appropriate access. This command is Regina-specific; use OPEN WRITE in its place.

[APPEND]

Open for append access and position the current write position at the end of the file. An error is returned if it was not possible to get appropriate access. This command is Regina-specific; use OPEN WRITE APPEND in its place.

[UPDATE]

Open for append access and position the current write position at the end of the file. An error is

returned if it was not possible to get appropriate access. This command is Regina-specific; use OPEN BOTH in its place.

[CREATE]

Open for write access and position the current write position at the start of the file. An error is returned if it was not possible to get appropriate access. This command is Regina-specific; use OPEN WRITE REPLACE in its place.

[CLOSE]

Close the stream, flushing any pending writes. An error is returned if it was not possible to get appropriate access.

[FLUSH]

Flush any pending write to the stream. An error is returned if it was not possible to get appropriate access.

[STATUS]

Returns status information about the stream in human readable form that Regina stores about the stream.

[FSTAT]

Returns status information from the operating system about the stream. This consists of at least 8 words:

Device Number Under DOS, Win32, OS/2, this represents the disk number, with 0 being Drive A.

Inode Number Under DOS, Win32, OS/2, this is zero.

Permissions User/Group/Other permissions mask. Consists of 3 octal numbers with 4 representing read, 2 representing write, and 1 representing execute. Therefore a value of 750 is read/write/execute for user, read/execute for group, and no permissions for other.

Number Links Under DOS, Win32, OS/2, this will always be 1.

User Name The owner of the stream. Under DOS, Win32, OS/2, this will always be "USER".

Group Name The group owner of the stream. Under DOS, Win32, OS/2, this will always be "GROUP".

Size Size of stream in bytes.

Stream Type One or more of the following:

RegularFile a normal file.

Directory a directory. BlockSpecial a block special file. FIFO usually a pipe.

SymbolicLink a symbolic link. If the stream is a symbolic link, the the details returned are details about the link, not the file the link points to.

Socket a socket

SpecialName a named special file.

CharacterSpecial a character special file.

[RESET]

Resets the stream after an error. Only streams that are resettable can be reset.

[READABLE]

Returns 1 if the stream is readable by the user or 0 otherwise.

[WRITABLE]

Returns 1 if the stream is writable by the user or 0 otherwise.

[EXECUTABLE]

Returns 1 if the stream is executable by the user or 0 otherwise.

[QUERY]

Returns information about the named stream. If the named stream does not exists, then the empty string is returned. This command is further broken down into the following subcommands:

DATETIME returns the date and time of last modification of the stream in

REXX US Date format; MM-DD-YY HH:MM:SS.

EXISTS returns the fully-qualified file name of the specified stream.

HANDLE returns the internal file handle of the stream. This will only return a valid value if the stream was opened explicitly or implicitly by Regina.

SEEK READ CHAR returns the current read position of the open stream expressed in characters.

SEEK READ LINE returns the current read position of the open stream expressed in lines.

SEEK WRITE CHAR returns the current write position of the open stream expressed in characters.

SEEK WRITE LINE returns the current write position of the open stream expressed in lines.

SEEK SYS returns the current read position of the open stream as the operating reports it. This is expressed in characters.

SIZE returns the size, expressed in characters, of the persistent stream.

STREAMTYPE returns the type of the stream. One of TRANSIENT,

PERSISTENT or UNKNOWN is returned.

TIMESTAMP returns the date and time of last modification of the stream. The format of the string returned is YYYY-MM-DD HH:MM:SS.

CREATETIME returns the date and time the stream was created in time_t format. If the file system does not support create time, this will return the stream's last modification time.

MODIFYTIME returns the date and time the stream was last modified in time t format.

ACCESSTIME returns the date and time the stream was last accessed in time_t format. If the file system does not support access time, this will return the stream's last modification time.

You can use POSITION in place of SEEK in the above options.

[OPEN]

Opens the stream in the optional mode specified. If no optional mode is specified, the default is OPEN BOTH .

READ The file pointer will be positioned at the start of the file, and only read operations are allowed.

WRITE Open for write access and position the current write pointer at the end of the file. On platforms where it is not possible to open a file for write without also allowing reads, the read pointer will be positioned at the start of the file. An error is returned if it was not possible to get appropriate access.

BOTH Open for read and write access. Position the current read pointer at the start of the file, and the current write pointer at the end of the file. An error is returned if it was not possible to get appropriate access.

WRITE APPEND Open for write access and position the write pointer at the end of the file. On platforms where it is not possible to open a file for write without also allowing reads, the read pointer will be positioned at the start of the file.

WRITE REPLACE Open for write access and position the current write position at the start of the file. On platforms where it is not possible to open a file for write without also allowing reads, the read pointer will be positioned at the start of the file. This operation will clear the contents of the file. An error is returned if it was not possible to get appropriate access.

BOTH APPEND Open for read and write access. Position the current read position at the start of the file, and the current write position at the end of the file. An error is returned if it was not possible to get appropriate access.

BOTH REPLACE Open for read and write access. Position both the current read and write pointers at the start of the file. An error is returned if it was not possible to get appropriate access.

[SEEK position READ|WRITE [CHAR|LINE]]

Positions the file's read or write pointer in the file to the specified position. SEEK is a synonym for POSITION.

position A position can be of the following forms. [relative]offset.

relative can be one of:

- = The file pointer is moved to the specified offset relative to the start of the file. This is the default.
- < The file pointer is moved to the specified offset relative to the end of the file.

- The file pointer is moved backwards relative to the current position.
- + The file pointer is moved forwards relative to the current position.

offset is a positive whole number.

READ The read file pointer will be positioned.

WRITE The write file pointer is positioned.

CHAR The offset specified in position above is in terms of characters.

LINE The offset specified in position above is in terms of lines.

Assume a file; '/home/mark/myfile' last changed March 30th 2002 at 15:07:56, with 100 lines, each line 10 characters long, and the following command executed in sequence.

| STREAM('myfile','C','QUERY EXISTS') | '/home/mark/myfile' |
|--|-----------------------|
| STREAM('myfile','C','QUERY SIZE') | 1100 |
| STREAM('myfile','C','QUERY TIMESTAMP') | 2002-03-30 15:07:56 |
| STREAM('myfile','C','QUERY DATETIME') | 03-30-02 15:07:56 |
| STREAM('myfile','D') | |
| STREAM('myfile','S') | UNKNOWN |
| STREAM('myfile','C','QUERY SEEK READ') | |
| STREAM('myfile','C','OPEN READ') | READY: |
| STREAM('myfile','D') | |
| STREAM('myfile','S') | READY |
| STREAM('myfile','C','QUERY SEEK READ') | 1 |
| STREAM('myfile','C','CLOSE') | UNKNOWN |
| STREAM('myfile','C','STATUS') | |
| STREAM('myfile','C','FSTAT') | 773 35006 064 1 mark |
| | mark 1100 RegularFile |
| STREAM('myfile','C','READABLE') | 1 |
| STREAM('myfile','C','WRITABLE') | 1 |
| STREAM('myfile','C','EXECUTABLE') | 0 |
| | |

STRIP(string [,[option] [,char]]) - (ANSI)

Returns string after possibly stripping it of any number of leading and/or trailing characters. The default action is to strip off both leading and trailing blanks. If char (which must be a string containing exactly one character) is specified, that character will be stripped off instead of blanks.

Inter-word blanks (or chars if defined, that are not leading of trailing) are untouched. If option is specified, it will define what to strip. The possible values for option are:

[L]

(Leading) Only strip off leading blanks, or chars if specified.

[T]

(Trailing) Only strip off trailing blanks, or chars if specified.

[B]

(Both) Combine the effect of L and T, that is, strip off both leading and trailing blanks, or chars if it is specified. This is the default action.

| STRIP(' Foo bar ') | 'Foo bar' |
|---------------------------|-------------|
| STRIP(' Foo bar ','L') | 'Foo bar ' |
| STRIP(' Foo bar ','t') | ' Foo bar' |
| STRIP(' Foo bar ','Both') | 'Foo bar' |
| STRIP('0.1234500',,'0') | '.12345' |
| STRIP('0.1234500 ',,'0') | '.1234500 ' |

SUBSTR(string, start [,length [,padchar]]) - (ANSI)

Returns the substring of string that starts at start , and has the length length . Length defaults to the rest of the string. Start must be a positive whole, while length can be any non-negative whole number.

It is not an error for start to be larger than the length of string. If length is specified and the sum of length and start minus 1 is greater that the length of string, then the result will be padded with padchars to the specified length. The default value for padchar is the <space> character.

| CLIDCED/IFoo borl 2) | la barl |
|---------------------------|----------|
| SUBSTR('Foo bar',3) | 'o bar' |
| SUBSTR('Foo bar',3,3) | 'o b' |
| SUBSTR('Foo bar',4,6) | ' bar ' |
| SUBSTR('Foo bar',4,6,'*') | ' bar**' |
| SUBSTR('Foo bar',9,4,'*') | '****' |

SUBWORD(string , start [, length]) - (ANSI)

Returns the part of string that starts at blank delimited word start (which must be a positive whole number). If length (which must be a non-negative whole number) is specified, that number of words are returned. The default value for length is the rest of the string.

It is not an error to specify length to refer to more words than string contains, or for start and length together to specify more words than string holds. The result string will be stripped of any leading and trailing blanks, but inter-word blanks will be preserved as is.

| SUBWORD('To be or not to be',4) | 'not to be' |
|-----------------------------------|-------------|
| SUBWORD('To be or not to be',4,2) | 'not to' |
| SUBWORD('To be or not to be',4,5) | 'not to be' |
| SUBWORD('To be or not to be',1,3) | 'To be or' |

SYMBOL(string) - (ANSI)

Checks if the string is a valid symbol (a positive number or a possible variable name), and returns a three letter string indicating the result of that check. If string is a symbol, and names a currently set

variable, VAR is returned, if string is a legal symbol name, but has not a been given a value (or is a constant symbol, which can not be used as a variable name), LIT is returned to signify that it is a literal. Else, if string is not a legal symbol name the string BAD is returned.

Watch out for the effect of "double expansion". string is interpreted as an expression evaluating naming the symbol to be checked, so you might have to quote the parameter.

| SYMBOL('Foobar') | 'VAR' /* Maybe */ |
|-----------------------|-------------------|
| SYMBOL('Foo bar') | 'BAD' |
| SYMBOL('Foo.Foo bar') | 'BAD' |
| SYMBOL('3.14') | 'LIT' |
| SYMBOL('.Foo→bar') | 'BAD' |

TIME([option_out [,time [,option_in]]]) - (ANSI)

Returns a string containing information about the local time. To get the time in a particular format, an option_out can be specified. The default option_out is Normal . The meaning of the possible options are:

[C]

(Civil) Returns the time in civil format. The return value might be "hh:mmXX", where XX are either am or pm. The hh part will be stripped of any leading zeros, and will be in the range 1-12 inclusive. (ANSI)

[E]

(Elapsed) Returns the time elapsed in seconds since the internal stopwatch was started. The result will have leading zeros if the result is less than zero. The output will be a floating point number with six digits after the decimal point. (ANSI)

[H]

(Hours) Returns the number of complete hours that have passed since last midnight in the form "hh". The output will have no leading zeros, and will be in the range 0-23. (ANSI)

[]]

(Job) Returns the number of seconds of CPU time the currently running process has currently used. The result will have leading zeros if the result is less than zero, and will have 6 decimal places. (Regina Extension)

[L]

(Long) Returns the exact time, down to the microsecond. This is called the long format. The output might be "hh:mm:ss.mmmmm". Be aware that most computers do not have a clock of that accuracy, so the actual granularity you can expect, will be about a few milliseconds. The hh, mm and ss parts will be identical to what is returned by the options H, M and S respectively, except that each part will have leading zeros as indicated by the format. (ANSI)

[M]

(Minutes) Returns the number of complete minutes since midnight, in a format having no leading

Last update: 2024/09/04 06:58

spaces or zeros. (ANSI)

[N]

(Normal) The output format is "hh:mm:ss", and is padded with zeros if needed. The hh, mm and ss will contain the hours, minutes and seconds, respectively. Each part will be padded with leading zeros to make it double-digit. (ANSI)

[0]

(Offset) Returns the number of microseconds between UTC time and local time. Where local daylight savings is in effect, this offset may be adjusted by the addition of 1 hour. (Not all systems reliably provide dayight savings time indication). This option was added with the ANSI Standard. (ANSI)

[R]

(Reset) Returns the value of the internal stopwatch just like the E option, and using the same format. In addition, it will reset the stopwatch to zero after its contents has been read. (ANSI)

[S]

(Seconds) Returns the number of complete seconds since midnight, in a format having no leading spaces or zeros. (ANSI)

[T]

(time_t) Returns the current UTC date/time in UNIX time_t format. time_t is the number of seconds since January 1st 1970. It always represents the UTC date/time, so any conversion from another time format (which is always assumed to be local time) will result in a time_t value offset by time zone. (Regina Extension)

Note that the time is never rounded, only truncated. As shown in the examples below, the seconds do not get rounded upwards, even though the decimal part implies that they are closer to 59 than to 58. The same applies for the minutes, which are closer to 33 than to 32, but is truncated to 32. None of the formats will have leading or trailing spaces.

Assuming that the time is exactly 14:32:58.987654 on March 30th 2002, the following will be true:

| TIME('C') | '2:32pm' |
|-----------|----------------------------------|
| TIME('E') | '0.01200' /* Maybe */ |
| TIME('H') | '14' |
| TIME('L') | '14:32:58.987654' |
| TIME('M') | '872' |
| TIME('N') | '14:32:58' |
| TIME('R') | '0.430221' /* Maybe */ |
| TIME('S') | '52378' |
| TIME('O') | 36000000000 /* East Coast Aus */ |
| TIME('J) | 5.342000 /* Maybe */ |

If the time option is specified, the function provides for time conversions. The optional option_in specifies the format in which time is supplied. The possible values for option_in are: CHLMNST. The default value for option_in is N.

When a time is converted to format T, the returned value is the input time for the current date.

| TIME('C','11:27:21') | '11:27am' |
|-------------------------|------------------------|
| TIME('N','11:27am','C') | '11:27:00' |
| TIME('T') | 1256475220 /* Maybe */ |

The time conversion capability of the TIME BIF was introduced with the ANSI standard.

TRACE([setting]) - (ANSI)

Returns the current value of the trace setting. If the string setting is specified, it will be used as the new setting for tracing, after the old value have be recorded for the return value. Note that the setting is not an option, but may be any of the trace settings that can be specified to the clause TRACE, except that the numeric variant is not allowed with TRACE(). In practice, this can be a word, of which only the first letter counts, optionally preceded by a question mark.

| TRACE() | 'C' /* Maybe */ |
|------------|-----------------|
| TRACE('N') | 'C' |
| TRACE('?') | 'N' |

TRANSLATE(string [,[tableout] [,[tablein] [,padchar]]]) - (ANSI)

Performs a translation on the characters in string . As a special case, if neither tablein nor tableout is specified, it will translate string from lower case to upper case. Note that this operation may depend on the language chosen, if your interpreter supports national character sets.

Two translation tables might be specified as the strings tablein and tableout. If one or both of the tables are specified, each character in string that exists in tablein is translated to the character in tableout that occupies the same position as the character did in tablein. The tablein defaults to the whole character set (all 256) in numeric sequence, while tableout defaults to an empty set.

Characters not in tablein are left unchanged.

If tableout is larger than tablein, the extra entries are ignored. If it is smaller than tablein it is padded with padchar to the correct length. Padchar defaults to <space>.

If a character occurs more than once in tablein, only the first occurrence will matter.

| TRANSLATE('FooBar') | 'FOOBAR' |
|---|----------|
| TRANSLATE('FooBar','ABFORabfor','abforABFOR') | 'fOObAR' |
| TRANSLATE('FooBar','abfor') | 1 1 |
| TRANSLATE('FooBar','abfor',,'#') | '###### |

TRIM(string) - (AREXX)

Removes trailing blanks from the string argument. A more portable option is to use the Trailing option of the STRIP BIF.

| TRIM(' | abc | ') | 'abc' |
|--------|-----|----|-------|
|--------|-----|----|-------|

Last update: 2024/09/04 06:58

TRUNC(number [,length]) - (ANSI)

Returns number truncated to the number of decimals specified by length . Length defaults to 0, that is return an whole number with no decimal part.

The decimal point will only be present if the is a non-empty decimal part, i.e. length is non-zero. The number will always be returned in simple form, never exponential form, no matter what the current settings of NUMERIC might be. If length specifies more decimals than number has, extra zeros are appended. If length specifies less decimals than number has, the number is truncated. Note that number is never rounded, except for the rounding that might take place during normalization.

| TRUNC(12.34) | '12' |
|------------------|-----------|
| TRUNC(12.99) | '12' |
| TRUNC(12.34,4) | '12.3400' |
| TRUNC(12.3456,2) | '12.34' |

UNAME([option]) - (REGINA)

Returns details about the current platform. This function is basically a wrapper for the Unix command; uname. Valid values for option are:

[A]

(All) The default. Returns a string with the all following option values. Equivalent to: UNAME('S') UNAME('N') UNAME('R') UNAME('V') UNAME('M').

[S]

(System) The name of the operating system.

[N]

(Nodename) The name of the machine.

[R]

(Release) The release of the operating system.

[V]

(Version) The version of the operating system.

[M]

(Machine) The machine's hardware type.

Example running Linux Redhat 6.1 on 'boojum', Athalon K7

| UNAME('S') | Linux |
|------------|----------|
| UNAME('N') | boojum |
| UNAME('R') | 2.2.1220 |

| UNAME('V') | #1 Mon Sep 27 10:40:35 EDT 1999 |
|------------|---------------------------------|
| UNAME('M') | i686 |

Example running Windows NT 4.0 on 'VM NT', Intel Pentium

| UNAME('S') | WINNT |
|------------|-------|
| UNAME('N') | VM_NT |
| UNAME('R') | 0 |
| UNAME('V') | 4 |
| UNAME('M') | i586 |

UNIXERROR(errorno) - (REGINA)

This function returns the string associated with the errno error number that errorno specifies. When some UNIX interface function returns an error, it really is a reference to an error message which can be obtained through UNIXERROR.

This function is just an interface to the strerror() function call in UNIX, and the actual error messages might differ with the operating system.

This function is now obsolete, instead you should use:

ERRORTEXT(100 + errorno)

UPPER(string [,start [,length [,pad]]]) - (AREXX/REGINA)

Translates the substring of string that starts at start, and has the length length to upper case. Length defaults to the rest of the string. Start must be a positive whole number, while length can be any non-negative whole number. The default value for start is 1 and for length is the length of string.

It is not an error for start to be larger than the length of string. If length is specified and the sum of length and start minus 1 is greater that the length of string, then the result will be padded with padchars to the specified length. The default value for padchar is the <space> character.

If a specific locale is set (via the -I switch), then the string is set to the correct uppercase values based on that locale.

While this BIF is an AREXX BIF, it is not necessary to have OPTIONS AREXX_BIFS set to use it. The optional arguments are Regina extensions.

| UPPER('One Fine Day') | 'ONE FINE DAY' |
|--------------------------|----------------|
| UPPER('fred', 2) | 'fRED' |
| UPPER('fred', 1, 1) | 'Fred' |
| UPPER('fred',1, 10, '*') | 'FRED***** |

USERID() - (REGINA)

Returns the name of the current user. A meaningful name will only be returned on those platforms that support multiple users, otherwise an empty string is returned.

USERID() 'mark' /* Maybe */

VALUE(symbol [,[value], [pool]]) - (ANSI)

This function expects as first parameter string symbol, which names an existing variable. The result returned from the function is the value of that variable. If symbol does not name an existing variable, the default value is returned, and the NOVALUE condition is not raised. If symbol is not a valid symbol name, and this function is used to access an normal REXX variable, an error occurs. Be aware of the "double-expansion" effect, and quote the first parameter if necessary.

If the optional second parameter is specified, the variable will be set to that value, after the old value has been extracted.

The optional parameter pool might be specified to select a particular pool of variables to search for symbol. The contents and format of pool is implementation dependent. The default is to search in the variables at the current procedural level in REXX. Which pools that are available is implementation dependent, but typically one can set variables in application programs or in the operating system.

Note that if VALUE() is used to access variables in pools outside the REXX interpreter, the requirements to format (a valid symbol) will not in general hold. There may be other requirements instead, depending on the implementation and the system. Depending on the validity of the name, the value, or whether the variable can be set or read, the VALUE() function can give error messages when accessing variables in pools other than the normal. Consult the implementation and system specific documentation for more information.

If it is used to access compound variables inside the interpreter the tail part of this function can take any expression, even expression that are not normally legal in REXX scripts source code.

The valid value of pool in Regina is one of ENVIRONMENT, SYSTEM, OS2ENVIRONMENT, or CALLER; the latter referring to the most immediate, higher level poo, and the 3 former referring to the external environment. pool can also be a number representing the call level to search, with the first level being 1. It is therefore possible to get and set the value of a variable in a higher call level procedure from the current one without the need to EXPOSE the variable. This and the POOLID() BIF which returns the current call level are Regina extensions.

By using this function, it is possible to perform an extra level of interpretation of a variable.

| VALUE('FOO') | 'bar' |
|-------------------------------|--------------------------------|
| VALUE('FOO','new') | 'bar' |
| VALUE('FOO') | 'new' |
| VALUE('USER','root','SYSTEM') | 'guest' /* If SYSTEM exists */ |
| VALUE('USER',,'SYSTEM') | 'root' |

VERIFY(string, ref [,[option] [,start]]) - (ANSI)

With only the first two parameters, it will return the position of the first character in string that is not also a character in the string ref . If all characters in string are also in ref , it will return 0 .

If option is specified, it can be one of:

[N]

(Nomatch) The result will be the position of the first character in string that does not exist in ref, or zero if all exist in ref. This is the default option.

[M]

(Match) Reverses the search, and returns the position of the first character in string that exists in ref. If none exists in ref, zero is returned.

If start (which must be a positive whole number) is specified, the search will start at that position in string. The default value for start is 1.

| VERIFY('foobar','barfo') '0' VERIFY('foobar','barfo','M') '1' VERIFY('foobar','fob','N') '5' VERIFY('foobar','barf','N',3) '3' VERIFY('foobar','barf','N',4) '0' | | |
|--|-------------------------------|-----|
| VERIFY('foobar','fob','N') '5' VERIFY('foobar','barf','N',3) '3' | VERIFY('foobar','barfo') | '0' |
| VERIFY('foobar','barf','N',3) '3' | VERIFY('foobar','barfo','M') | '1' |
| | VERIFY('foobar','fob','N') | '5' |
| VERIFY('foobar','barf','N',4) '0' | VERIFY('foobar','barf','N',3) | '3' |
| | VERIFY('foobar','barf','N',4) | '0' |

WORD(string, wordno) - (ANSI)

Returns the blank delimited word number wordno from the string string . If wordno (which must be a positive whole number) refers to a non-existing word, then a nullstring is returned. The result will be stripped of any blanks. See 3.1.6 for characters that delimit a word.

| WORD('To be or not to be',3) | 'or' |
|------------------------------|-------|
| WORD('To be or not to be',4) | 'not' |
| WORD('To be or not to be',8) | 11 |

WORDINDEX(string, wordno) - (ANSI)

Returns the character position of the first character of blank delimited word number wordno in string , which is interpreted as a string of blank delimited words. If number (which must be a positive whole number) refers to a word that does not exist in string , then 0 is returned. See 3.1.6 for characters that delimit a word.

| WORDINDEX('To be or not to be',3) | '7' |
|-----------------------------------|------|
| WORDINDEX('To be or not to be',4) | '10' |
| WORDINDEX('To be or not to be',8) | '0' |

WORDLENGTH(string, wordno) - (ANSI)

Returns the number of characters in blank delimited word number number in string. If number (which must be a positive whole number) refers to an non-existent word, then 0 is returned. Trailing or leading blanks do not count when calculating the length. See 3.1.6 for characters that delimit a word.

| WORDLENGTH('To be or not to be',3) | '2' |
|------------------------------------|-----|
| WORDLENGTH('To be or not to be',4) | '3' |
| WORDLENGTH('To be or not to be',0) | '0' |

Last update: 2024/09/04 06:58

WORDPOS(phrase, string [,start]) - (ANSI)

Returns the word number in string which indicates at which phrase begins, provided that phrase is a subphrase of string. If not, 0 is returned to indicate that the phrase was not found. A phrase differs from a substring in one significant way; a phrase is a set of words, separated by any number of blanks.

For instance, "is a" is a subphrase of "This is a phrase". Notice the different amount of whitespace between "is" and "a".

If start is specified it sets the word in string at which the search starts. The default for start is 1. See 3.1.6 for characters that delimit a word.

| WORDPOS('or not','to be or not to be') | |
|---|-----|
| WORDPOS('not to','to be or not to be') | |
| WORDPOS('to be','to be or not to be') | |
| WORDPOS('to be','to be or not to be',3) | '6' |

WORDS(string) - (ANSI)

Returns the number of blank delimited words in the string . See 3.1.6 for characters that delimit a word.

| WORDS('To be or not to be') | |
|-----------------------------|--|
| WORDS('Hello world') | |
| WORDS(") | |

WRITECH(file, string) - (AREXX)

Writes the string argument to the given logical file. The returned value is the actual number of characters written.

WRITECH('outfile','Testing') '7'

WRITELN(file, string) - (AREXX)

Writes the string argument to the given logical file with a "newline" appended. The returned value is the actual number of characters written, including the "newline" character(s).

| WRITELN('outfile','Testing') | '8' /* Unix */ |
|------------------------------|----------------|
| WRITELN('outfile','Testing') | '9' /* DOS */ |

XRANGE([start] [,end]) - (ANSI)

Returns a string that consists of all the characters from start through end, inclusive. The default value for character start is '00'x, while the default value for character end is 'ff'x. Without any parameters, the whole character set in "alphabetic" order is returned. Note that the actual representation of the output from XRANGE() depends on the character set used by your computer.

If the value of start is larger than the value of end, the output will wrap around from 'ff'x to '00'x. If start or end is not a string containing exactly one character, an error is reported.

| XRANGE('A','J') | 'ABCDEFGHIJ' |
|---------------------|---------------------|
| XRANGE('FC'x) | 'FCFDFEFF'x |
| XRANGE(,'05'x) | '000102030405'x |
| XRANGE('FD'x,'04'x) | 'FDFEFF0001020304'x |

X2B(hexstring) - (ANSI)

Translate hexstring to a binary string. Each hexadecimal digits in hexstring will be translated to four binary digits in the result. There will be no blanks in the result.

| X2B('') | П |
|----------------------|---|
| X2B('466f6f 426172') | '010001100110111101101111010000100110000101 |
| X2B('46 6f 6f') | '010001100110111101101111' |

X2C(hexstring) - (ANSI)

Returns the (packed) string representation of hexstring. The hexstring will be converted bytewise, and blanks may optionally be inserted into the hexstring between pairs or hexadecimal digits, to divide the number into groups and improve readability. All groups must have an even number of hexadecimal digits, except the first group. If the first group has an odd number of hexadecimal digits, it is padded with an extra leading zero before conversion.

| X2C('') | 11 | |
|----------------------|----------------------------------|--|
| X2C('466f6f 426172') | 'FooBar' /* on ASCII machines */ | |
| X2C('46 6f 6f') | 'Foo' /* on ASCII machines */ | |

X2D(hexstring [,length]) - (ANSI)

Returns a whole number that is the decimal representation of hexstring . If length is specified, then hexstring is interpreted as a two's complement hexadecimal number consisting of the number rightmost hexadecimal numerals in hexstring . If hexstring is shorter than number , it is padded to the left with <NUL> characters (that is: '00'x).

If length is not specified, hexstring will always be interpreted as an unsigned number. Else, it is interpreted as an signed number, and the leftmost bit in hexstring decides the sign.

If it is not possible to express the final result as a whole number under the current settings of NUMERIC DIGITS, and STRICT_ANSI option is in effect, error 40.35 is reported. The number to be returned will not be stored in the internal representation of the built-in library, so size restrictions on whole numbers that generally applies for built-in functions, do not apply in this case.

| X2D('03 24') | '792' |
|---------------|---------|
| X2D('0310') | '784' |
| X2D('ffff') | '65535' |
| X2D('ffff',5) | '65535' |
| X2D('ffff',4) | '-1' |

| 1 | X2D('ff80',3) | '-128' |
|---|----------------|--------|
| | X2D('12345',3) | '837' |

Implementation specific documentation for Regina

Deviations from the Standard

For those built-in functions where the last parameter can be omitted, Regina allows the last comma to be specified, even when the last parameter itself has been omitted.

The error messages are slightly redefined in two ways. Firstly, some of the have a slightly more definite text, and secondly, some new error messages have been defined.

The environments available are described in chapter [not yet written].

Parameter calling

Stream I/O

Conditions

National character sets

Blanks

Stacks have the following extra functionality: DROPBUF(), DESBUF() and MAKEBUF() and BUFTYPE().

Random()

Sourceline

Time

Character sets

Interpreter Internal Debugging Functions

ALLOCATED([option])

Returns the amount of dynamic storage allocated, measured in bytes. This is the memory allocated by the malloc() call, and does not concern stack space or static variables.

As parameter it may take an option, which is one of the single characters:

[A]

It will return a string that is the number of bytes of dynamic memory currently allocated by the interpreter.

[C]

Returns a number that is the number of bytes of dynamic memory that is currently in use (i.e. not leaked).

[L]

Returns the number of bytes of dynamic memory that is supposed to have been leaked.

[S]

This is the default value if you do not specify an option. Returns a string that is nicely formatted and contains all the other three options, with labels. The format of this string is:

"Memory: Allocated=XXX, Current=YYY, Leaked=ZZZ".

This function will only be available if the interpreter was compiled with the TRACEMEM preprocessor macro defined.

DUMPTREE()

Prints out the internal parse tree for the REXX program currently being executed. This output is not very interesting unless you have good knowledge of the interpreter's internal structures.

DUMPVARS()

This routine dumps a list of all the variables currently defined. It also gives a lot of information which is rather uninteresting for most users.

LISTLEAKED()

List out all memory that has leaked from the interpreter. As a return value, the total memory that has been listed is returned. There are several option to this function:

[N]

[A]

[L]

Do not list anything, just calculate the memory.

TRACEBACK()

List all memory allocations currently in use, not only that which has been marked as leaked. Only list

Last update: 2024/09/04 06:58

the memory that has been marked as leaked. This is the default option.

Prints out a traceback. This is the same routine which is called when the interpreter encounters an error. Nice for debugging, but not really useful for any other purposes.

REXX VMS Interface Functions

F\$CVSI F\$CVTIME F\$CVUI F\$DIRECTORY F\$ELEMENT F\$EXTRACT F\$FAO F\$FILE_ATTRIBUTES
F\$GETDVI F\$GETJPI F\$GETQUI F\$GETSYI F\$IDENTIFIER F\$INTEGER F\$LENGTH F\$LOCATE F\$LOGICAL
F\$MESSAGE F\$MODE F\$PARSE F\$PID F\$PRIVILEGE F\$PROCESS F\$SEARCH F\$SETPRV F\$STRING
F\$TIME F\$TRNLNM F\$TYPE F\$USER

RexxUtil for Regina

Regina 3.5 and above provides Patrick McPhee's Regutil external function package as part of the Regina distribution. The documentation for Regutil is supplied in a separate document.

Conditions

In this chapter, the REXX concept of "conditions" is described. Conditions allow the programmer to handle abnormal control flow, and enable him to assign special pieces of REXX code to be executed in case of certain incidences.

In the first section the concept of conditions is explained.

Then, there is a description of how a standard condition in REXX would work, if it existed.

In the third section, all the existing conditions in REXX are presented, and the differences compared to the standard condition described in the previous section are listed.

The fourth sections contains a collections of random notes on the conditions in REXX.

The last section describes differences, extensions and peculiarities in Regina on the of subject conditions, and the lists specific behavior.

What are Conditions

In this section, the concept of "conditions" are explained: What they are, how they work, and what they mean in programming.

What Do We Need Conditions for?

Terminology

First, let's look at the terminology used in this chapter. If you don't get a thorough understanding of these terms, you will probably not understand much of what is said in the rest of this chapter.

[Incident:]

A situation, external or internal to the interpreter, which it is required to respond to in certain predefined manners. The interpreter recognizes incidents of several different types. The incident will often have a character of "suddenness", and will also be independent of the normal control flow.

[Event:]

Data Structure describing one incident, used as a descriptor to the incident itself.

[Condition:]

Names the REXX concept that is equivalent to the incident.

[Raise a Condition:]

The action of transforming the information about an incident into an event. This is done after the interpreter senses the condition. Also includes deciding whether to ignore or produce an event.

[Handle a Condition:]

The act of executing some pre-defined actions as a response to the event generated when a condition was raised.

[(Condition) Trap:]

Data Structure containing information about how to handle a condition.

[(Trap) State:]

Part of the condition trap.

[(Condition) Handler:]

Part of the condition trap, which points to a piece of REXX code which is to be used to handle the condition.

[(Trap) Method:]

Part of the condition trap, which defined how the condition handler is to be invoked to handle the condition.

[Trigger a Trap:]

The action of invoking a condition handler by the method specified by the trap method, in order to handle a condition.

[Trap a Condition:]

Last update: 2024/09/04 06:58

Short of trigger a trap for a particular condition.

[Current Trapped Condition:]

The condition currently being handled. This is the same as the most recent trapped condition on this or higher procedure level.

[(Pending) Event Queue:]

Data Structure storing zero or more events in a specific order. There are only one event queue. The event queue contains events of all condition types, which have been raised, but not yet handled.

[Default-Action:]

The pre-defined default way of handling a condition, taken if the trap state for the condition raised is OFF.

[Delay-Action:]

The pre-defined default action taken when a condition is raised, and the trap state is DELAY.

The Mythical Standard Condition

REXX Language Level 4.00 has six different conditions, and REXX Language Level 5.00 has seven. However, each of these is a special case of a mythical, non-existing, standard condition. In order to better understand the real conditions, we start by explaining how a standard condition work.

In the examples below, we will call our non-existing standard condition MYTH. Note that these examples will not be executable on any REXX implementation.

Information Regarding Conditions (data structures)

There are mainly five conceptual data structures involved in conditions.

[Event queue.]

There is one interpreter-wide queue of pending conditions. Raising a condition is identical to adding information about the condition to this queue (FIFO). The order of the queue is the same order in which the conditions are to be handled.

Every entry in the queue of pending conditions contains some information about the event: the line number of the REXX script when the condition was raised, a descriptive text and the condition type.

[Default-Action.]

To each, there exists information about the default-action to take if this condition is raised but the trap is in state OFF. This is called the "default-action". The standard default-action is to ignore the condition, while some conditions may abort the execution.

[Delay-Action.]

Each condition will also have delay-action, which tells what to do if the condition is raised when condition trap is in state DELAY. The standard delay-action is to queue the condition in the queue of pending conditions, while some conditions may ignore it.

[Condition traps.]

For each condition there is a trap which contains three pieces of status information: the state; the handler; and the method. The state can be ON, OFF or DELAY.

The handler names the REXX label in the start of the REXX code to handle the event. The method can be either SIGNAL or CALL, and denotes the method in which the condition is to be handled. If the state is OFF, then neither handler nor method is defined.

[Current Trapped Condition.]

This is the most recently handled condition, and is set whenever a trap is triggered. It contains information about method, which condition, and a context-dependent description. In fact, the information in the current trapped condition is the same information that was originally put into the pending event queue.

Note that the event queue is a data structure connected to the interpreter itself. You operate on the same event queue, independent of subroutines, even external ones. On the other hand, the condition traps and the current trapped condition are data structures connected to each single routine. When a new routine is called, it will get its own condition traps and a current trapped condition. For internal routines, the initial values will be the same values as those of the caller. For external routines, the values are the defaults.

The initial value for the event queue is to be empty. The default-action and the delay-action are static information, and will always retain their values during execution. The initial values for the condition traps are that they are all in state OFF. The initial value for the current trapped condition is that all information is set to the nullstring to signalize that no condition is currently being trapped.

How to Set up a Condition Trap

How do you set the information in a condition trap? You do it with a SIGNAL or CALL clause, with the ON or OFF subkeyword. Remember that a condition trap contain three pieces of information?

Here are the rules for how to set them:

- To set the trap method, use either SIGNAL or CALL as keyword.
- To set state to ON or OFF, use the appropriate subkeyword in the clause. Note that there is no clause or function in REXX, capable of setting the state of a trap to DELAY.
- To set the condition handler, append the term "NAME handler" to the command. Note that this term is only legal if you are setting the state to ON; you can not specify a handler when setting the state to OFF.

The trap is said to be "enabled" when the state is either ON or DELAY, and "disabled" when the state is OFF. Note that neither the event queue, nor the current trapped condition can be set explicitly by REXX clauses. They can only be set as a result of incidents, when raising and trapping conditions. It sounds very theoretical, doesn't it? Look at the following examples, which sets the trap MYTH:

Last update: 2024/09/04 06:58

```
/* 1 */ SIGNAL ON MYTH NAME TRAP_IT
/* 2 */ SIGNAL OFF MYTH
/* 3 */ CALL ON MYTH NAME MYTH_TRAP
/* 4 */ CALL ON MYTH
/* 5 */ CALL OFF MYTH
```

Line 1 sets state to ON, method to SIGNAL and handler to TRAP_IT. Line 2 sets state to OFF, handler and method becomes undefined. Line 3 sets state to ON, method to CALL, and handler to MYTH_TRAP. Line 4 sets state to ON, method to CALL and handler to MYTH (the default). Line 5 sets state to OFF, handler and method become undefined.

Why should method and handler become undefined when the trap in state OFF? For two reasons: firstly, these values are not used when the trap is in state OFF; and secondly, when you set the trap to state ON, they are redefined. So it really does not matter what they are in state OFF.

What happens to this information when you call a subroutine? All information about traps are inherited by the subroutine, provided that it is an internal routine. External routines do not inherit any information about traps, but use the default values. Note that the inheritance is done by copying, so any changes done in the subroutine (internal or external), will only have effect until the routine returns.

How to Raise a Condition

How do you raise a condition? Well, there are really no explicit way in REXX to do that. The conditions are raised when an incident occurs. What sort of situations that is, depends on the context. There are in general three types of incidents, classified by the origin of the event:


Internal origin. The incident is only dependent on the behaviour of the REXX script. The SYNTAX condition is of this type.

External origin. The REXX script and the interpreter has really no control over when this incident. It happens completely independent of the control of the REXX script or interpreter. The HALT condition is of this type.

Mixed origin. The incident is of external origin, but the situation that created the incident, was an action by the REXX script or the interpreter. The ERROR condition is of this type: the incident is a command returning error, but it can only occur when the interpreter is executing commands.

For conditions trapped by method CALL, standard REXX requires an implementation to at least check for incidents and raise condition at clause boundaries. (But it is allowed to do so elsewhere too; although the actual triggering must only be performed at clause boundaries.) Consequently, you must be prepared that in some implementations, conditions trappable by method CALL might only be raised (and the trap triggered) at clause boundaries, even if they are currently trapped by method SIGNAL.

The seven standard conditions will be raised as result of various situations, read the section describing each one of them for more information.



The triggering of a condition

When an incident occurs and the condition is raised, the interpreter will check the state of the condition trap for that particular condition at the current procedure level.

If the trap state is OFF, the default-action of the condition is taken immediately. The "standard" default-action is to ignore the condition.

If the trap state is DELAY, the action will depend on the delay-action of that condition. The standard delay-action is to ignore, then nothing further is done. If the delay-action is to queue, the interpreter continues as if the state was ON.

If the state of the trap is ON, an event is generated which describes the incident, and it is queued in the pending event queue. The further action will depend on the method of trapping.

If the method is CALL, the state of the trap will be set to DELAY. Then the normal execution is resumed. The idea is that the interpreter will check the event queue later (at a clause boundary), and trigger the appropriate trap, if it finds any events in the event queue.

Else, if method of trapping is SIGNAL, then the action taken is this: First set the trap to state OFF, then terminate clause the interpreter was executing at this procedure level. Then it explicitly trigger the condition trap.

This process has be shown in the figure above. It shows how an incident makes the interpreter raise a

condition, and that the state of the condition trap determines what to do next. The possible outcomes of this process are: to take the default-action; to ignore if delay-action is not to queue; to just queue and the continue execution; or to queue and trigger the trap.

How to Trigger a Condition Trap

What are the situations where a condition trap might be triggered? It depends on the method currently set in the condition trap.

If the method is SIGNAL, then the interpreter will explicitly trigger the relevant trap when it has raised the condition after having sensed the incident. Note that only the particular trap in question will be triggered in this case; other traps will not be triggered, even if the pending event queue is non-empty.

In addition, the interpreter will at each clause boundary check for any pending events in the event queue. If the queue is non-empty, the interpreter will not immediately execute the next normal statement, but it will handle the condition(s) first. This procedure is repeated until there are no more events queued. Only then will the interpreter advance to execute the next normal statement.

Note that the REXX standard does not require the pending events to be handled in any particular order, although the model shown in this documentation it will be in the order in which the conditions were raised. Consequently, if one clause generates several events that raise conditions before or at the next clause boundary, and these conditions are trapped by method CALL. Then, the order on which the various traps are triggered is implementations-dependent. But the order in which the different instances of the same condition is handled, is the same as the order of the condition indicator queue.

Trapping by Method SIGNAL

Assume that a condition is being trapped by method SIGNAL, that the state is ON and the handler is MYTH TRAP. The following REXX clause will setup the trap correctly:

SIGNAL ON MYTH NAME MYTH_TRAP

Now, suppose the MYTH incident occurs. The interpreter will sense it, queue an event, set the trap state to OFF and then explicitly trigger the trap, since the method is SIGNAL. What happens when the trap is triggered?

It collects the first event from the queue of pending events. The information is removed from the queue.

The current trapped condition is set to the information removed from the pending event queue.

Then, the interpreter simulates a SIGNAL clause to the label named by trap handler of the trap for the condition in question.

As all SIGNAL clauses, this will have the side-effects of setting the SIGL special variable, and terminating all active loops at the current procedure level.

That's it for method SIGNAL. If you want to continue trapping condition MYTH, you have to execute a

new SIGNAL ON MYTH clause to set the state of the trap to ON. But no matter how quick you reset the trap, you will always have a short period where it is in state OFF. This means that you can not in general use the method SIGNAL if you really want to be sure that you don't loose any MYTH events, unless you have some control over when MYTH condition may arise.

Also note that since the statement being executed is terminated; all active loops on the current procedure level are terminated; and the only indication where the error occurred is the line number (the line may contain several clauses), then it is in general impossible to pick up the normal execution after a condition trapped by SIGNAL. Therefore, this method is best suited for a "graceful death" type of traps. If the trap is triggered, you want to terminate what you were doing, and pick up the execution at an earlier stage, e.g. the previous procedure level.

Trapping by Method CALL

Assume that the condition MYTH is being trapped by method CALL, that the state is ON and the handler is MYTH HANDLER.

The following REXX clause will setup the trap correctly:

CALL ON MYTH NAME MYTH HANDLER

Now, suppose that the MYTH incident occurs. When the interpreter senses that, it will raise the MYTH condition. Since the trap state is ON and the trap method is CALL, it will create an event and queue it in the pending event queue and set the trap state to DELAY. Then it continues the normal execution. The trap is not triggered before the interpreter encounters the next clause boundary. What happens then?

At the every clause boundaries, the interpreter check for any pending events in the event queue. If one is found, it is handled. This action is done repeatedly, until the event queue is empty.

It will simulate a normal function call to the label named by the trap handler. As with any CALL clause, this will set the special variable SIGL to the line of from which the call was made. This is done prior to the call. Note that this is the current line at the time when the condition was raised, not when it was triggered. All other actions normally performed when calling a subroutine are done. Note that the arguments to the subroutine are set to empty.

However, just before execution of the routine starts, it will remove the first event in the pending event queue, the information is instead put into the current trapped condition. Note that the current trapped condition is information that is saved across subroutine calls. It is set after the condition handler is called, and will be local to the condition handler (and functions called by the condition handler). To the "caller" (i.e. the procedure level active when the trap was triggered), it will seem as if the current trapped condition was never changed.

Then the condition handler finishes execution, and returns by executing the RETURN clause. Any expression given as argument to RETURN will be ignored, i.e. the special variable RESULT will not be set upon return from a condition handler.

At the return from the condition handler, the current trapped condition and the setup of all traps are restored, as with a normal return from subroutine. As a special case, the state of the trap just triggered, will not be put back into DELAY state, but is set to state ON.

Afterward (and before the next normal clause), the interpreter will again check for more events in the event queue, and it will not continue on the REXX script before the queue is empty.

During the triggering of a trap by method CALL at a clause boundary, the state of the trap is not normally changed, it will continue to be DELAY, as was set when the condition was raised. It will continue to be in state DELAY until return from the condition handler, at which the state of the trap in the caller will be changed to ON. If, during the execution of the condition trap, the state of the condition being trapped is set, that change will only last until the return from the condition handler.

Since new conditions are generally delayed when an condition handler is executing, new conditions are queued up for execution. If the trap state is changed to ON, the pending event queue will be processed as named at the next clause boundary. If the state is changed to OFF, the default action of the conditions will be taken at the next clause boundary.

The Current Trapped Condition

The interpreter maintains a data structure called the current trapped condition. It contains information relating the most recent condition trapped on this or higher procedure level. The current trapped condition is normally inherited by subroutines and functions, and restored after return from these.

When trapped by method SIGNAL the current trapped condition of the current procedure level is set to information describing the condition trapped.

When trapped by method CALL, the current trapped condition at the procedure level which the trap occurred at, is not changed. Instead, the current trapped condition in the condition handler is set to information describing the condition.

The information stored in the current trapped condition can be retrieved by the built-in function CONDITION(). The syntax format of this function is:

CONDITION(option)

where option is an option string of which only the first character matters. The valid options are: Condition name, Description, Instruction and State. These will return: the name of the current trapped condition; the descriptive text; the method; and the current state of the condition, respectively. The default option is Instruction. See the documentation on the built-in functions. See also the description of each condition below.

Note that the State option do not return the state at the time when the condition was raised or the trap was triggered. It returns the current state of the trap, and may change during execution. The other information in the current trapped condition may only change when a new condition is trapped at return from subroutines.

The Real Conditions

We have now described how the standard condition and condition trap works in REXX. Let's look at the seven conditions defined which do exist. Note that none of these behaves exactly as the standard condition.

The SYNTAX condition

The SYNTAX condition is of internal origin, and is raised when any syntax or runtime error is discovered by the REXX interpreter. It might be any of the situations that would normally lead to the abortion of the program and the report of a REXX error message, except error message number 4 (Program interrupted), which is handled by the HALT condition.

There are several differences between this condition and the standard condition:

It is not possible to trap this condition with the method CALL, only method SIGNAL. The reason for this is partly that method CALL tries to continue execution until next boundary before triggering the trap. That might not be possible with syntax or runtime errors.

When this condition is trapped, the special variable RC is set to the REXX error number of the syntax or runtime error that caused the condition. This is done just before the setting of the special variable SIGL.

The default action of this condition if the trap state is OFF, is to abort the program with a traceback and error message.

There is not delay-action for condition SYNTAX, since it can not be trapped by method CALL, and consequently never can get into state DELAY.

The descriptive text returned by CONDITION() when called with the Description option for condition SYNTAX, is implementation dependent, and may also be a nullstring. Consult the implementation-specific documentation for more information.

The HALT condition

The HALT condition of external origin, which is raised as a result of an action from the user, normally a combination of keys which tries to abort the program. Which combination of keys will vary between operating systems. Some systems might also simulate this event by other means than key combinations. In general ^C and ^-Break key combinations will generate this condition. The differences between HALT and the standard condition are:

The default-action for the HALT condition is to abort execution, as though a REXX runtime error number 4 (Program interrupted) had been reported. But note that SYNTAX will never be raised if HALT is not trapped.

The delay-action of this condition is to ignore, not queue.

The standard allows the interpreter to limit the search for situations that would set the HALT condition, to clause boundaries. As a result, the response time from pressing the key combination to actually raising the condition or triggering the trap may vary, even if HALT is trapped by method SIGNAL. If a clause for some reason has blocked execution, and never finish, you may not be able to break the program.

The descriptive text returned by CONDITION() when called with the Description option for condition HALT, is implementation dependent, and may also be a nullstring. In general, it will describe the way in which the interpreter was attempted halted, in particular if there are more than one way to do raise

Last update: 2024/09/04 06:58

a HALT condition. Consult the implementation documentation for more information.

The ERROR condition

The ERROR is a condition of mixed origin, it is raised when a command returns a return value which indicates error during execution. Often, commands return a numeric value, and a particular value is considered to mean success. Then, other values might raise the ERROR condition.

Differences between ERROR and the standard condition:

The delay action of ERROR is to ignore, not to queue.

The special variable RC is always set before this condition is raised. So even if it is trapped by method SIGNAL, you can rely on RC to be set to the return value of the command.

Unfortunately, there is no universal standard on return values. As stated, they are often numeric, but some operating system use non-numeric return values. For those which do use numeric values, there are no standard telling which values and ranges are considered errors and which are considered success. In fact, the interpretation of the value might differ between commands within the same operating system.

Therefore, it is up to the REXX implementation to define which values and ranges that are considered errors. You must expect that this information can differ between implementations as well as between different environments within one implementation.

The descriptive text returned by CONDITION() when called with the Description option for condition ERROR, is the command which caused the error. Note that this is the command as the environment saw it, not as it was entered in the REXX script source code.

The FAILURE condition

The FAILURE is a condition of mixed origin, it is raised when a command returns a return value which indicates failure during execution, abnormal termination, or when it was impossible to execute a command. It is a subset of the ERROR condition, and if it is in state OFF, then the ERROR condition will be raised instead. But note that an implementation is free to consider all return codes from commands as ERRORs, and none as FAILURES. In that case, the only situation where a FAILURE would occur, is when it is impossible to execute a command.

Differences between FAILURE and the standard condition:

The delay action of FAILURE is to ignore, not to queue.

The special variable RC is always set before this condition is raised. So even if it is trapped by method SIGNAL, you can rely on RC to be set to the return value of the command, or the return code that signalize that the command was impossible to execute.

As for ERROR, there is no standard the defines which return values are failures and which are errors. Consult the system and implementation independent documentation for more information.

The descriptive text returned by CONDITION() when called with the Description option for condition

FAILURE, is the command which caused the error. Note that this is the command as the environment saw it, not as it was entered in the REXX script source code.

The NOVALUE condition

The NOVALUE condition is of internal origin. It is raised in some circumstances if the value of an unset symbol (which is not a constant symbol) is requested. Normally, this would return the default value of the symbol. It is considered bad programming practice not to initialize variables, and setting the NOVALUE condition is one method of finding the parts of your program that uses this programming practice.

Note however, there are only three instances where this condition may be raised: that is when the value of an unset (non-constant) symbol is used requested: in an expression; after the VAR subkeyword in a PARSE clause; and as an indirect reference in either a template, a DROP or a PROCEDURE clause. In particular, this condition is not raised if the VALUE() or SYMBOL() builtin functions refer to an unset symbol.

Differences between NOVALUE and the standard condition are:

It may only be trapped by method SIGNAL, never method CALL. This requirement might seem somewhat strange, but the idea is that since an implementation is only forced to check for conditions trapped by method CALL at clause boundaries, incidences that may occur at any point within clauses (like NOVALUE) can only be trapped by method SIGNAL. (However, condition NOTREADY can occur within a clause, and may be trapped by method CALL so this does not seem to be absolute consistent.)

There is not delay-action for condition NOVALUE, since it can not be trapped by method CALL, and consequently never can get into state DELAY.

The descriptive text returned by calling CONDITION() with the Description option, is the derived (i.e. tail has be substituted if possible) name of the variable that caused the condition to be raised.

The NOTREADY condition

The condition NOTREADY is a condition of mixed origin. It is raised as a result of problems with stream I/O. Exactly what causes it, may vary between implementations, but some of the more probable causes are: waiting for more I/O on transient streams; access to streams not allowed; I/O operation would block if attempted; etc. See the chapter; Stream Input and Output for more information.

Differences between NOTREADY and the standard condition are:

It will be ignored rather than gueued if condition trap is in state DELAY.

This condition differs from the rest in that it can be raised during execution of a clause, but can still be trapped by method CALL.

The descriptive text returned by CONDITION() when called with the Description option for condition NOTREADY, is the name of the stream which caused the problem. This is probably the same string that you used as the first parameter to the functions that operates on stream I/O. For the default streams (default input and output stream), the string returned by CONDITION() will be the nullstring.

Note that if the NOTREADY trap is in state DELAY, then all I/O for files which has tried to raise

NOTREADY within the current clause will be simulated as if operation had succeeded.

The LOSTDIGITS condition

The condition LOSTDIGITS was introduced in Language Level 5.00. It is raised as a result of any arithmetic operation which results in the loss of any digits. i.e. If the number of significant digits in the result of an arithmetic operation would exceed the currently defined number of digits via NUMERIC DIGITS, then the LOSTDIGITS condition is raised.

Differences between LOSTDIGITS and the standard condition are:

It may only be trapped by method SIGNAL, never method CALL.

There is not delay-action for condition NOVALUE, since it can not be trapped by method CALL, and consequently never can get into state DELAY.

The descriptive text returned by CONDITION() when called with the Description option for condition NOTREADY, is the name of the stream which caused the problem. This is probably the same string that you used as the first parameter to the functions that operates on stream I/O. For the default streams (default input and output stream), the string returned by CONDITION() will be the nullstring.

Further Notes on Conditions

Conditions under Language Level 3.50

The concept of conditions was very much expanded from REXX language level 3.50 to level 4.00. Many of the central features in conditions are new in level 4.00, these include:

The CALL method is new, previously only the SIGNAL method was available, which made it rather difficult to resume execution after a problem. As a part of this, the DELAY state has been added too.

The condition NOTREADY has been added, to allow better control over problems involving stream I/O.

The built-in function CONDITION() has been added, to allow extraction of information about the current trapped condition.

Pitfalls when Using Condition Traps

There are several pitfalls when using conditions:

Remember that some information are saved across the functions. Both the current trapped condition and the settings of the traps. Consequently, you can not set a trap in a procedure level from a lower level. (i.e. calling a subroutine to set a trap is will not work.)

Remember that SIGL is set when trapped by method CALL. This means that whenever a condition

might be trapped by CALL, the SIGL will be set to a new value. Consequently, never trust the contents of the SIGL variable for more than one clause at a time. This is very frustrating, but at least it will not happen often. When it do happen, though, you will probably have a hard time debugging it.

Also remember that if you use the PROCEDURE clause in a condition handler called by method CALL, remember to EXPOSE the special variable SIGL if you want to use it inside the condition handler. Else it will be shadowed by the PROCEDURE.

The Correctness of this Description

In this description of conditions in REXX, I have gone further in the description of how conditions work, their internal data structures, the order in which things are executed etc., than the standard does. I have tried to interpret the set of distinct statements that is the documentation on condition, and design a complete and consistent system describing how such conditions work. I have done this to try to clarify an area of REXX which at first glance is very difficult and sometimes non-intuitive.

I hope that the liberties I have taken have helped describe conditions in REXX. I do not feel that the adding of details that I have done in any way change how conditions work, but at least I owe the reader to list which concepts that are genuine REXX, and which have been filled in by me to make the picture more complete. These are not a part of the standard REXX.

REXX does not have anything called a standard condition. There just "are" a set of conditions having different attributes and values. Sometimes there are default values to some of the attributes, but still the are no default condition.

The terms "event" and "incident" are not used. Instead the term "condition" is somewhat overloaded to mean several things, depending on the situation. I have found it advantageous to use different terms for each of these concepts.

Standard REXX does not have condition queue, although a structure of such a kind is needed to handled the queuing of pending conditions when the trap state is DELAY.

The values default-action and delay-action are really non-existing in the Standard REXX documentation. I made them up to make the system more easy to explain.

The two-step process of first raising the flag, and then (possibly at a later stage) triggering the trap, is not really a REXX concept. Originally, REXX seems to allow implementations to select certain places of the interpreter where events are sought for. All standard conditions that can be called by method CALL, can be implemented by checking only at clause boundaries.

Consequently, a REXX implementation can choose to trigger the trap immediately after a condition are raised (since conditions are only raised immediately before the trap would trigger anyway). This is also the common way used in language level 3.50, when only method SIGNAL was implemented.

Unfortunately, the introduction of the state DELAY forces the interpreter to keep a queue of pending conditions, so there is nothing to gain on insisting that raising should happen immediately before triggering. And the picture is even more muddled when the NOTREADY condition is introduced. Since it explicitly allows raising of condition to be done during the clause, even though the triggering of the trap must happen (if method is CALL) at the end of the clause.

I really hope that these changes has made the concept of conditions easier to understand, not harder.

Please feel free to flame me for any of these which you don't think is representative for REXX.

Conditions in Regina

Here comes documentation that are specific for the Regina implementation of REXX.

How to Raise the HALT condition

The implementation connect the HALT condition to an external event, which might be the pressing of certain key combination. The common conventions of the operating system will dictate what that combination of keystrokes is.

Below is a list, which describes how to invoke an event that will raise the HALT condition under various the operating systems which Regina runs under.

Under various variants of the Unix operating system, the HALT event it connected to the signal "interrupt" (SIGINT). Often this signal is bound to special keystrokes. Depending on your version of Unix, this might be <ctrl>-<c> (mostly BSD-variants) or the key (mostly System V). It is also possible to send this signal from the command line, in general using the program kill(1); or from program, in general using the call signal(3). Refer to your Unix documentation for more information.

Under VAX/VMS, the key sequence <ctrl>-<c> is used to raise the HALT condition in the interpreter.

Possible Future extensions

Here is a list of possible future extensions to REXX which has not been implemented into Regina. Some of these exist in other implementations of REXX, and some of them are just suggestions or ideas thrown around by various people.

Another extension could have been included, but have been left out so far. It is the delay-action, which in standard REXX can be either to ignore or to queue. There is at least one other action that make sense: to replace. That is, when a trap is in state DELAY, and a new condition has been raised, the pending queue is emptied, before the new condition is queued. That way, the new condition will effectively replace any conditions already in the queue.

If there are several new conditions raised while the condition handler is executing (and the trap state is DELAY), only the very last of them is remembered.

It should be possible to set the state for a trap to DELAY, so that any new instances of the condition is handles by the delay-action. As a special case, the SYNTAX condition trap might not be set in state DELAY

Stream Input and Output

And the streams thereof shall be turned into pitch

Isaiah 33:21

For every one that asketh receivedth; and he that seeketh findth;

and to him that knocketh it shall be opened.

Matthew 7:8

This chapter treats the topic of input from and output to streams using the built-in functions. An overview of the other parts of the input/output (I/O) system is also given but not discussed in detail. At the end of the chapter there are sections containing implementation-specific information for this topic.

Background and Historical Remarks

Stream I/O is a problem area for languages like REXX. They try to maintain compatibility for all platforms (i.e. to be non-system-specific), but the basic I/O capabilities differ between systems, so the simplest way to achieve compatibility is to include only a minimal, common subset of the functionality of all platforms. With respect to the functionality of the interface to their surrounding environment, non-system-specific script languages like REXX are inherently inferior to system specific script languages which are hardwired to particular operating systems and can benefit from all their features.

Although REXX formally has its own I/O constructs, it is common for some platforms that most or all of the I/O is performed as operating system commands rather than in REXX. This is how it was originally done under VM/CMS, which was one of the earliest implementations and which did not support REXX's I/O constructs. There, the EXECIO program and the stack (among other methods) are used to transfer data to and from a REXX program.

Later, the built-in functions for stream I/O gained territory, but lots of implementations still rely on special purpose programs for doing I/O. The general recommendation to REXX programmers is to use the built-in functions instead of special purpose programs whenever possible; that is the only way to make compatible programs.

REXX's Notion of a Stream

REXX regards a stream as a sequence of characters, conceptually equivalent to what a user might type at the keyboard. Note that a stream is not generally equivalent to a file. [MCGH:DICT] defines a file as "a collection of related records treated as a unit," while [OX:CDICT] defines it as "Information held on backing store [...] in order (a) to enable it to persist beyond the time of execution of a single job and/or (b) to overcome space limitations in main memory." A stream is defined by [OX:CDICT] as "a flow of data characterized by relative long duration and constant rate."

Thus, a file has a flavor of persistency, while a stream has a flavor of sequence and momentarily. For

a stream, data read earlier may already have been lost, and the data not yet read may not be currently defined; for instance the input typed at a keyboard or the output of a program. Even though much of the REXX literature use these two terms interchangeably (and after all, there is some overlap), you should bear in mind that there is a difference between them.

In this documentation, the term "file" means "a collection of persistent data on secondary storage, to which random access and multiple retrieval are allowed." The term "stream" means a sequential flow of data from a file or from a sequential device like a terminal, tape, or the output of a program. The term stream is also used in its strict REXX meaning: a handle to/from which a flow of data can be written/read.

Short Crash-Course

REXX I/O is very simple, and this short crash course is probably all you need in a first-time reading of this chapter. But note that that, we need to jump a bit ahead in this section.

To read a line from a stream, use the LINEIN() built-in function, which returns the data read. To write a stream, use the LINEOUT() built-in function, and supply the data to be written as the second parameter. For both operations, give the name of the stream as the first parameter. Some small examples:

```
contents = linein( 'myfile.txt' )
call lineout 'yourfile.txt', 'Data to be written'
```

The first of these reads a line from the stream myfile.txt, while the second writes a line to the stream yourfile.txt. Both these calls operate on lines and they use a system specific end-of-line marker as a delimiter between lines. The marker is tagged on at the end of any data written out, and stripped off any data read.

Opening a stream in REXX is generally done automatically, so you can generally ignore that in your programs. Another useful method is repositioning to a particular line:

```
call linein 'myfile.txt', 12, 0 call lineout 'yourfile.txt',, 13
```

Where the first of these sets the current read position to the start of line 12 of the stream; the second sets the current write position to the start of line 13. Note that the second parameter is empty, that means no data is to be written. Also note that the current read and write positions are two independent entities; setting one does not affect the other.

The built-in functions CHARIN() and CHAROUT() are similar to the ones just described, except that they are character-oriented, i.e. the end-of-line delimiter is not treated as a special character.

Examples of use are:

```
say charin( 'myfile.txt', 10 )
call charout 'logfile', 'some data'
```

Here, the first example reads 10 characters, starting at the current input position, while the second writes the eleven characters of "some data" to the file, without an end-of-file marker afterward. It is

possible to reposition character-wise too, some examples are:

```
call charin 'myfile',, 8 call charout 'foofile,, 10
```

These two clauses repositions the current read and write positions of the named files to the 8th and 10th characters, respectively.

Naming Streams

Unlike most programming languages, REXX does not use file handles; the name of the stream is also in general the handle (although some implementations add an extra level of indirection). You must supply the name to all I/O functions operating on a stream. However, internally, the REXX interpreter is likely to use the native file pointers of the operating system, in order to improve speed. The name specified can generally be the name of an operating system file, a device name, or a special stream name supported by your implementation.

The format of the stream name is very dependent upon your operating system. For portability concerns, you should try not to specify it as a literal string in each I/O call, but set a variable to the stream name, and use that variable when calling I/O functions. This reduces the number of places you need to make changes if you need to port the program to another system. Unfortunately, this approach increases the need for PROCEDURE EXPOSE, since the variable containing the files name must be available to all routines using file I/O for that particular file, and all their non-common ancestors.

Example: Specifying file names

The following code illustrates a portability problem related to the naming of streams. The variable filename is set to the name of the stream operated on in the function call.

```
filename = '/tmp/MyFile.Txt'
say ' first line is' linein( filename ) say 'second line is' linein(
filename ) say ' third line is' linein( filename )
```

Suppose this script, which looks like it is written for Unix, is moved to a VMS machine. Then, the stream name might be something like SYS\$TEMP:MYFILE.TXT, but you only need to change the script at one particular point: the assignment to the variable filename; as opposed to three places if the stream name is hard-coded in each of the three calls to LINEIN().

If the stream name is omitted from the built-in I/O functions, a default stream is used: input functions use the default input stream, while output functions use the default output stream. These are implicit references to the default input and output streams, but unfortunately, there is no standard way to explicitly refer to these two streams. And consequently, there is no standard way to refer to the default input or output stream in the built-in function STREAM().

However, most implementations allow you to access the default streams explicitly through a name, maybe the nullstring or something like stdin and stdout. However, you must refer to the implementation-specific documentation for information about this.

Also note that standard REXX does not support the concept of a default error stream. On operating systems supporting this, it can probably be accessed through a special name; see system-specific

information. The same applies for other special streams.

Sometimes the term "default input stream" is called "standard input stream," "default input devices," "standard input," or just "stdin."

The use of stream names instead of stream descriptors or handles is deeply rooted in the REXX philosophy: Data structures are text strings carrying information, rather than opaque data blocks in internal, binary format. This opens for some intriguing possibilities. Under some operating systems, a file can be referred to by many names. For instance, under Unix, a file can be referred to as foobar, ./foobar and ././foobar. All which name the same file, although a REXX interpreter may be likely to interpret them as three different streams, because the names themselves differ. On the other hand, nothing prevents an interpreter from discovering that these are names for the same stream, and treat them as equivalent (except concerns for processing time). Under Unix, the problem is not just confined to the use of ./ in file names, hard-links and soft-links can produce similar effects, too.

Example: Internal file handles

Suppose you start reading from a stream, which is connected to a file called foo. You read the first line of foo, then you issue a command, in order to rename foo to bar. Then, you try to read the next line from foo. The REXX program for doing this under Unix looks something like:

```
signal on notready line1 = linein( 'foo' ) 'mv foo bar'
line2 = linein( 'foo' )
```

Theoretically, the file foo does not exist during the second call, so the second read should raise the NOTREADY condition. However, a REXX interpreter is likely to have opened the stream already, so it is performing the reading on the file descriptor of the open file. It is probably not going to check whether the file exists before each I/O operation (that would require a lot of extra checking). Under most operating systems, renaming a file will not invalidate existing file descriptors. Consequently, the interpreter is likely to continue to read from the original foo file, even though its has changed.

Example: Unix temporary files

On some systems, you can delete a file, and still read from and write to the stream connected to that file. This technique is shown in the following Unix specific code:

```
tmpfile = '/tmp/myfile' call lineout tmpfile, '' call lineout tmpfile,, 1
'rm' tmpfile
call lineout tmpfile, 'This is the first line'
```

Under Unix, this technique is often used to create temporary files; you are guaranteed that the file will be deleted on closing, no matter how your program terminates. Unix deletes a file whenever there are no more references to it. Whether the reference is from the file system or from an open descriptor in a user process is irrelevant. After the rm command, the only reference to the file is from the REXX interpreter. Whenever it terminates, the file is deleted-since there are no more references to it.

Example: Files in different directories

Here is yet another example of how using the filename directly in the stream I/O functions may give strange effects. Suppose you are using a system that has hierarchical directories, and you have a function CHDIR() which sets a current directory; then consider the following code:

```
call chdir '../dir1'
call lineout 'foobar', 'written to foobar while in dir1' call chdir
'../dir2'
call lineout 'foobar', 'written to foobar while in dir2'
```

Since the file is implicitly opened while you are in the directory dir1, the file foobar refers to a file located there. However, after changing the directory to dir2, it may seem logical that the second call to LINEOUT() operates on a file in dir2, but that may not be the case. Considering that these clauses may come a great number of lines apart, that REXX has no standard way of closing files, and that REXX only have one file table (i.e. open files are not local to subroutines); this may open for a significant astonishment in complex REXX scripts.

Whether an implementation treats ././foo and ./foo as different streams is system-dependent; that applies to the effects of renaming or deleting the file while reading or writing, too. See your interpreter's system-specific documentation.

Most of the effects shown in the examples above are due to insufficient isolation between the filename of the operating system and the file handle in the REXX program. Whenever a file can be explicitly opened and bound to a file handle, you should do that in order to decrease the possibilities for strange side effects.

Interpreters that allow this method generally have an OPEN() function that takes the name of the files to open as a parameter, and returns a string that uniquely identifies that open file within the current context; e.g. an index into a table of open files. Later, this index can be used instead of the filename.

Some implementations allow only this indirect naming scheme, while others may allow a mix between direct and indirect naming. The latter is likely to create some problems, since some strings are likely to be both valid direct and indirect file ids.

Persistent and Transient Streams

REXX knows two different types of streams: persistent and transient. They differ conceptually in the way they can be operated, which is dictated by the way they are stored. But there is no difference in the data you can read from or write to them (i.e. both can used for character- or line-wise data), and both are read and written using the same functions.

[Persistent streams]

(often referred to just as "files") are conceptually stored on permanent storage in the computer (e.g. a disk), as an array of characters. Random access to and repeated retrieval of any part of the stream are allowed for persistent streams. Typical example of persistent streams are normal operating system files.

[Transient streams]

are typically not available for random access or repeated retrieval, either because it is not stored permanently, but read as a sequence of data that is generated on the fly; or because they are available from a sequential storage (e.g. magnetic tape) where random access is difficult or impossible. Typical examples of transient streams are devices like keyboards, printers, communication interfaces, pipelines, etc.

REXX does not allow any repositioning on transient streams; such operations are not conceptually meaningful; a transient stream must be treated sequentially. It is possible to treat a persistent stream as a transient stream, but not vice versa. Thus, some implementations may allow you to open a persistent stream as transient. This may be useful for files to which you have only append access, i.e. writes can only be performed at the end of file. Whether you can open a stream in a particular mode, or change the mode of a stream already open depends on your implementation.

Example: Determining stream type

Unfortunately, there is no standard way to determine whether a given file is persistent or transient. You may try to reposition for the file, and you can assume that the file is persistent if the repositioning succeeded, like in the following code:

```
streamtype: procedure
  signal on notready
  call linein arg(1), 1, 0
  return 'persistent' /* unless file is empty */

notready:
  return 'transient'
```

Although the idea in this code is correct, there are unfortunately a few problems. First, the NOTREADY condition can be raised by other things than trying to reposition a transient stream; e.g. by any repositioning of the current read position in an empty file, if you have write access only, etc. Second, your implementation may not have NOTREADY, or it may not use it for this situation.

The best method is to use a STREAM() function, if one is available. Unfortunately, that is not very compatible, since no standard stream commands are defined.

Opening a Stream

In most programming languages, opening a file is the process of binding a file (given by a file name) to an internal handle. REXX is a bit special, since conceptually, it does not use stream handles, just stream names. Therefore, the stream name is itself also the stream handle, and the process of opening streams becomes apparently redundant. However, note that a number of implementations allow explicit opening, and some even require it.

REXX may open streams "on demand" when they are used for the first time. However, this behavior is not defined in TRL, which says the act of opening the stream is not a part of REXX [TRL2]. This might be interpreted as open-on-demand or that some system-specific program must be executed to open a stream.

Although an open-on-demand feature is very practical, there are situations where you need to open streams in particular modes. Thus, most systems have facilities for explicitly opening a file. Some REXX interpreters may require you to perform some implementation-specific operation before accessing streams, but most are likely to just open them the first time they are referred to in an I/O operation.

There are two main approaches to explicit opening of streams. The first uses a non-standard built-in function normally called OPEN(), which generally takes the name of the file to open as the first

parameter, and often the mode as the second parameter. The second approach is similar, but uses the standard built-in function STREAM() with a Command option.

Example: Not closing files

Since there are no open or close operation, a REXX interpreter never knows when to close a stream, unless explicitly told so. It can never predict when a particular stream is to be used next, so it has to keep the current read and write positions in case the stream is to be used again. Therefore, you should always close the streams when you are finished using them. Failure to do so, will fill the interpreter with data about unneeded streams, and more serious, it may fill the file table of your process or system. As a rule, any REXX script that uses more than a couple of streams, should close every stream after use, in order to minimize the number of simultaneously open streams. Thus, the following code might eventually crash for some REXX interpreters:

```
do i=1 to 300
   call lineout 'file.'||i, 'this is file number' i
end
```

A REXX interpreter might try to defend itself against this sort of open-many-close-none programming, using of various programming techniques; this may lead to other strange effects. However, the main responsibility for avoiding this is with you, the REXX script programmer.

Note that if a stream is already open for reading, and you start writing to it, your implementation may have to reopen it in order to open for both reading and writing. There are mainly two strategies for handling this. Either the old file is closed, and then reopened in the new mode, which may leave you with read and write access to another file. Or a new file handle is opened for the new mode, which may leave you with read and write access to two different files.

These are real-world problems which are not treated by the ideal description of TRL. A good implementation should detect these situations and raise NOTREADY.

Closing a Stream

As already mentioned, REXX does not have an explicit way of opening a stream. Nor does it have an explicit way of closing a stream. There is one semi-standard method: If you call LINEOUT(), but omit both the data to be written and the new current write position, then the implementation is defined to set the current write position to the end-of-file. Furthermore, it is allowed by TRL to do something "magic" in addition. It is not explicitly defined what this magic is, but TRL suggests that it may be closing the stream, flushing the stream, or committing changes done previously to the stream.

In SAA, the definition is strengthened to state that the "magic" is closing, provided that the environment supports that operation.

A similar operating can be performed by calling CHAROUT() with neither data nor a new position. However, in this case, both TRL and SAA leave it totally up to the implementation whether or not the file is to be closed. One can wonder whether the changes for LINEOUT() in SAA with respect to TRL should also have been done to CHAROUT(), but that this was forgotten.

TRL2 does not indicate that LINEIN() or CHARIN() can be used to close a string. Thus, the closest one gets to a standard way of closing input files is to call e.g. LINEOUT(); although it is conceptually

suspect to call an output routine for an input file. The historical reasons for this omission are perhaps that flushing output files is vital, while the concept of flushing is irrelevant for input files; flushing is an important part of closing a file, and that explains why closing is only indicated for output files.

Thus, the statement:

```
call lineout 'myfile.txt'
```

might be used to close the stream myfile.txt in some implementations. However, it is not guaranteed to close the stream, so you cannot depend on this for scripts of maximum portability, but it's better than nothing. However, note that if it closes the stream, then also the current read position is affected. If it merely flushes the stream, then only the current write position is likely to be affected.

Character-wise and Line-wise I/O

Basically, the built-in REXX library offers two strategies of reading and writing streams: line-wise and character-wise. When reading line-wise, the underlying storage method of the stream must contain information which describes where each line starts and ends.

Some file systems store this information as one or more special characters; while others structure the file in a number of records; each containing a single line. This introduces a slightly subtle point; even though a stream foo returns the same data when read by LINEIN() on two different machines; the data read from foo may differ between the same two machines when the stream is read by CHARIN(), and vice versa. This is so because the end-of-line markers can vary between the two operating systems.

Example: Character-wise handling of EOL

Suppose a text file contains the following three lines (ASCII character set is assumed):

```
first second third
```

and you first read it line-wise and then character-wise. Assume the following program:

```
file = 'DATAFILE'
foo = ''
do i=1 while chars(file)>0
  foo = foo || c2x(charin(file))' '
end

say foo
```

When the file is read line-wise, the output is identical on all machines, i.e. the three lines shown above. However, the character-wise reading will be dependent on your operating system and its file system, thus, the output might e.g. be any of:

66 69 72 73 74 73 65 6F 63 6E 64 74 68 69 72 64 66 69 72 73 74 0A

```
66 69 72 73 74 0A
73 65 6F 63 6E 64 0A
74 68 69 72 64 0A
66 69 72 73 74 0D 0A
73 65 6F 63 6E 64 0D 0A
74 68 69 72 64 0D 0A
```

If the machine uses records to store the lines, the first one may be the result; here, only the data in the lines of the file is returned. Note that the boxes in the output are put around the data generated by the actual line contents. What is outside the boxes is generated by the end-of-line character sequences.

The second output line is typical for Unix machines. They use the newline ASCII character as line separator, and that character is read immediately after each line. The last line is typical for MS-DOS, where the line separator character sequence is a carriage return following by a newline (ASCII '0D'x and '0A'x).

For maximum portability, the line-wise built-in functions (LINEIN(), LINEOUT() and LINES()) should only be used for line-wise streams. And the character-wise built-in functions (CHARIN(), CHAROUT() and CHARS()) should only be used for character-wise data. You should in general be very careful when mixing character- and line-wise data in a single stream; it does work, but may easily lead to portability problems.

The difference between character- and line-wise streams are roughly equivalent to the difference between binary and text streams, but the two concepts are not totally equivalent. In a binary file, the data read is the actual data stored in the file, while in a text file, the character sequences used for denoting end-of-line and end-of-file markers may be translated to actions or other characters during reading.

The end-of-file marker may be differently implemented on different systems. On some systems, this marker is only implicitly present at the end-of-file-which is calculated from the file size (e.g. Unix). Other systems may put a character signifying end-of-file at the end (or even in the middle) of the file (e.g. <Ctrl-Z> for MS-DOS). These concepts vary between operating systems, interpreters should handle each concept according to the customs of the operating system. Check the implementation-specific documentation for further information. In any case, if the interpreter treats a particular character as end-of-file, then it only gives special treatment to this character during line-wise operations. During character-wise operations, no characters have special meanings.

Reading and Writing

Four built-in functions provide line- and character-oriented stream reading and writing capabilities:

CHARIN(), CHAROUT(), LINEIN(), LINEOUT().

[CHARIN()]

is a built-in function that takes up to three parameters, which are all optional: the name of the stream to read from, the start point, and the number of characters to read. The stream name defaults to the default input stream, the start point defaults to the current read position, the number of characters to read defaults to one character. Leave out the second parameter in order to avoid all repositioning. During execution, data is read from the stream specified, and returned as the return value.

[LINEIN()]

is a built-in function that takes three parameters too, and they are equivalent to the parameters of CHARIN(). However, if the second parameter is specified, it refer to a line position, rather than a character position; it refers to the character position of the first character of that line. Further, the third parameter can only be 0 or 1, and refers to the number of lines to read; i.e. you cannot read more than one line in each call. The line read is returned by the function, or the nullstring if no reading was requested.

[LINEOUT()]

is a built-in function that takes three parameters too, the first is the name of the stream to write to, and defaults to the default output stream. The second parameter is the data to be written to the file, and if not specified, no writing occurs. The third parameter is a line-oriented position in the file; if the third parameter is specified, the current position is repositioned at before the data (if any) is written. If data is written, an end-of-line character sequence is appended to the output stream.

[CHAROUT()]

is a built-in function that is used to write characters to a file. It is identical to LINEOUT(), except that the third parameter refers to a character position, instead of a line position. The second difference is that an end-of-line character sequence is not appended at the end of the data written.

Example: Counting lines, words, and characters

The following REXX program emulates the core functionality of the wc program under Unix. It counts the number of lines, words, and characters in a file given as the first argument.

```
file = arg(1)
parse value 0 0 0 with lines words chars
do while lines(file)>0
    line = linein(file)
    lines = lines + 1
    words = words + words(line)
    chars = chars + length(line)
end

say 'lines='lines 'words='words 'chars='chars
```

There are some problems. For instance, the end-of-line characters are not counted, and a last improperly terminated line is not counted either.

Determining the Current Position

Standard REXX does not have any seek call that returns the current position in a stream. Instead, it provides two calls that returns the amount of data remaining on a stream. These two built-in functions are LINES() and CHARS().

The LINES() built-in function returns the number of complete lines left on the stream given as its first parameter. The term "complete lines" does not really matter much, since an implementation can assume the end-of-file to implicitly mean an end-of-line.

The CHARS() built-in function returns the number of character left in the stream given as its first parameter.

This is one of the concepts where REXX I/O does not map very well to C I/O and vice versa. While REXX reports the amount of data from the current read position to the end of stream, C reports the amount of data from the start of the file to the current position. Further, the REXX method only works for input streams, while the C method works for both input and output files. On the other hand, C has no basic constructs for counting remaining or reposition at lines of a file.

Example: Retrieving current position

So, how does one find the current position in a file, when only allowed to do normal repositioning? The trick is to reposition twice, as shown in the code below.

```
ftell: procedure
  parse arg filename
  now = chars(filename)
  call charin filename, 0, 1
  total = chars(filename)
  call charin filename, 0, total-now
  return total-now
```

Unfortunately, there are many potential problems with this code. First, it only works for input files, since there is no equivalent to CHARS() for output files. Second, if the file is empty, none of the repositioning work, since it is illegal to reposition at or after end-of-file for input files—and the end-of-file is the first position of the file. Third, if the current read position of the file is at the end of file (e.g. all characters have been read) it will not work for similar reasons as for the second case. And fourth, it only works for persistent files, since transient files do not allow repositioning.

Example: Improved ftell function An improved version of the code for the ftell routine (given above), which tries to handle these problems is:

```
ftell: procedure
  parse arg filename
  signal on notready name not_persist
  now = chars(filename)
  signal on notready name is_empty
  call charin filename, 0, 1
  total = chars()
  if now>0 then
     call charin filename, 0, total-now+1
  else
    if total>0 then
     call charin filename, 1, total
    else
      nop /* empty file, should have raised NOTREADY */
  return total-now+1
```

```
not_presist:
    say filename 'is not persistent';
    return 0

is_empty:
    say filename 'is empty';
    return 0
```

The same method can be used for line-oriented I/O too, in order to return the current line number of an input file. However, a potential problem in that case is that the routine leaves the stream repositioned at the start of the current line, even if it was initially positioned to the middle of a line. In addition, the line-oriented version of this ftell routine may prove to be fairly inefficient, since the interpreter may have to scan the whole file twice for end-of-line character sequences.

Positioning Within a File

REXX supports two strategies for reading and writing streams: character-wise, and line-wise, this section describes how a program can reposition the current positions for each these strategies. Note that positioning is only allowed for persistent streams.

For each open file, there is a current read position or a current write position, depending on whether the file is opened for reading or writing. If the file is opened for reading and writing simultaneously, it has both a current read position and a current write position, and the two are independent and in general different. A position within a file is the sequence number of the byte or line that will be read or written in the next such operation.

Note that REXX starts numbering at one, not zero. Therefore, the first character and the first line of a stream are both numbered one. This differs from several other programming languages, which starts numbering at zero.

Just after a stream has been opened, the initial values of the current read position is the first character in the stream, while the current write position is the end-of-file, i.e. the position just after the last character in the stream. Then, reading will return the first character (or line) in the stream, and writing will append a new character (or line) to the stream.

These initial values for the current read and write positions are the default values. Depending on your REXX implementation, other mechanisms for explicitly opening streams (e.g. through the STREAM() built-in function) may be provided, and may set other initial values for these positions. See the implementation-specific documentation for further information.

When setting the current read position, it must be set to the position of an existing character in the stream; i.e. a positive value, not greater than the total number of characters in the stream. In particular, it is illegal to set the current read position to the position immediately after the last character in the stream; although this is legal in many other programming languages and operating systems, where it is known as "seeking to the end-of-file".

When setting the current write position, it too must be set to the position of an existing character in the stream. In addition, and unlike the current read position, the current write position may also be set to the position immediately following the last character in the stream. This is known as

"positioning at the end-of-file", and it is the initial value for the current write position when a stream is opened. Note that you are not allowed to reposition the current write position further out beyond the end-of-file-which would create a "hole" in the stream-even though this is allowed in many other languages and operating systems.

Depending on your operating system and REXX interpreter, repositioning to after the end-of-file may be allowed as an extension, although it is illegal according to TRL2. You should avoid this technique if you wish to write portable programs.

REXX only keeps one current read position and one current write position for each stream. So both line-wise and character-wise reading as well as positioning of the current read position will operate on the same current read position, and similarly for the current write position.

When repositioning line-wise, the current write position is set to the first character of the line positioned at. However, if positioning character-wise so that the current read position is in the middle of a line in the file, a subsequent call to LINEIN() will read from (and including) the current position until the next end-of-line marker. Thus, LINEIN() might under some circumstances return only the last part of a line. Similarly, if the current write position has been positioned in the middle of an existing line by character-wise positioning, and LINEOUT() is called, then the line written out becomes the last part of the line stored in the stream.

Note that if you want to reposition the current write position using a line count, the stream may have to be open for read, too. This is because the interpreter may have to read the contents of the stream in order to find where the lines start and end. Depending on your operating system, this may even apply if you reposition using character count.

Example: Repositioning in empty files

Since the current read position must be at an existing character in the stream, it is impossible to reposition in or read from an empty stream. Consider the following code:

```
filename = '/tmp/testing'
call lineout filename,, 1 /* assuming truncation */
call linein filename, 1, 0
```

One might believe that this would set the current read and write positions to the start of the stream. However, assume that the LINEOUT() call truncates the file, so that it is zero bytes long. Then, the last call can never be legal, since there is no byte in the file at which it is possible to position the current read position. Therefore, a NOTREADY condition is probably raised.

Example: Relative repositioning

It is rather difficult to reposition a current read or write position relative to the current position. The only way to do this within the definition of the standard is to keep a counter which tells you the current position. That is, if you want to move the current read position five lines backwards, you must do it like this:

```
filename = '/tmp/data'
linenum = 0;
say linein(filename,10);
linenum = 10
do while random(100)>3
```

```
say linein(filename);
linenum = linenum+1
end

call linein(filename, linenum-5,0);
linenum = linenum-5
```

Here, the variable linenum is updated for each time the current read position is altered. This may not seem to difficult, and it is not in most cases. However, it is nearly impossible to do this in the general case, since you must keep an account of both line numbers and character numbers. Setting one may invalidate the other: consider the situation where you want to reposition the current read position to the 10th character before the 100th line in the stream. Except from mixing line-wise and characterwise I/O (which can have strange effects), this is nearly impossible. When repositioning characterwise, the line number count is invalidated, and vice versa.

The "only" proper way of handling this is to allow one or more (non-standard) STREAM() built-in function operations that returns the current character and line count of the stream in the interpreter.

Example: Destroying linecount

This example shows how overwriting text to the middle of a file can destroy the line count. In the following code, we assume that the file foobar exists, and contains ten lines which are "first line", second line, etc. up to "tenth line". Then consider the following code:

```
filename = 'foobar'
say linein(filename, 5) /* says 'fifth line' */
say linein(filename) /*
says 'sixth line' */
say linein(filename) /* says 'seventh line' */
call lineout filename, 'This is a very long line', 5
say linein(filename, 5) /* says 'This is a very long line' */
say linein(filename) /* says 'venth line' */
say linein(filename) /* says 'eight line' */
```

As you can see from the output of this example, the call to LINEOUT() inserts a long line and overwrites the fifth and sixth lines completely, and the seventh line partially. Afterward, the sixth line is the remaining part of the old seventh line, and the new seventh line is the old eighth line, etc.

Errors: Discovery, Handling, and Recovery

TRL2 contains two important improvements over TRL1 in the area of handling errors in stream I/O: the NOTREADY condition and the STREAM() built-in function. The NOTREADY condition is raised whenever a stream I/O operation did not succeed. The STREAM() function is used to retrieve status information about a particular stream or to execute a particular operation for a stream.

You can discover that an error occurred during an I/O operation in one of the following ways: a) it may trigger a SYNTAX condition; b) it may trigger a NOTREADY condition; or c) it may just not return that data it was supposed to. There is no clear border between which situations should trigger SYNTAX and which should trigger NOTREADY. Errors in parameters to the I/O functions, like a negative start

position, is clearly a SYNTAX condition, while reading off the end-of-file is equally clearly a NOTREADY condition. In between lay more uncertain situations like trying to position the current write position after the end-of-file, or trying to read a non-existent file, or using an illegal file name.

Some situations are likely to be differently handled in various implementations, but you can assume that they are handled as either SYNTAX or NOTREADY. Defensive, portable programming requires you to check for both. Unfortunately, NOTREADY is not allowed in TRL1, so you have to avoid that condition if you want maximum compatibility. And due to the very lax restrictions on implementations, you should always perform very strict verification on all data returned from any file I/O built-in function.

If neither are trapped, SYNTAX will terminate the program while NOTREADY will be ignored, so the implementor's decision about which of these to use may even depend on the severity of the problem (i.e. if the problem is small, raising SYNTAX may be a little too strict). Personally, I think SYNTAX should be raised in this context only if the value of a parameter is outside its valid range for all contexts in which the function might be called.

Example: General NOTREADY condition handler

2025/11/17 15:12

Under TRL2 the "correct" way to handle NOTREADY conditions and errors from I/O operations is unfortunately very complex. It is shown in this example, in order to demonstrate the procedure:

```
myfile = 'MYFILE.DAT'
signal on syntax name syn handler
call on notready name IO_handler
do i=1 to 10 until res=0
   res = lineout(myfile, 'line #'i)
  if (res=0) then
      say 'Call to LINEOUT() didn"t manage to write out data'
end
exit
IO handler:
syn handler:
   file = condition('D')
   say condition('C') 'raised for file' file 'at line' sigl':'
   say ' ' sourceline(sigl)
  say ' State='stream(file,'S') 'reason:' stream(file,'D')
   call lineout( condition( 'D' )) /* try to close */
   if condition('C') == 'SYNTAX' then
     exit 1
   else
     return
```

Note the double checking in this example: first the condition handler is set up to trap any NOTREADY conditions, and then the return code from LINEOUT() is checked for each call.

As you can see, there is not really that much information that you can retrieve about what went wrong. Some systems may have additional sources from which you can get information, e.g. special

Last update: 2024/09/04 06:58

commands for the STREAM() built-in function, but these are non-standard and should be avoided when writing compatible programs.

Common Differences and Problems with Stream I/O

This section describes some of the common traps and pitfalls of REXX I/O.

Where Implementations are Allowed to Differ

TRL is rather relaxed in its specifications of what an interpreter must implement of the I/O system. It recognizes that operating systems differ, and that some details must be left to the implementor to decide, if REXX is to be effectively implemented. The parts of the I/O subsystem of REXX where implementations are allowed to differ, are:

The functions LINES() and CHARS() are not required to return the number of lines or characters left in a stream. TRL says that if it is impossible or difficult to calculate the numbers, these functions may return 1 unless it is absolutely certain that there are no more data left. This leads to some rather kludgey programming techniques.

Implementations are allowed to ignore closing streams, since TRL does not specify a way to do this. Often, the closing of streams is implemented as a command, which only makes it more incompatible.

Check the implementation-specific documentation before using the function LINEOUT(file) for closing files.

The difference in the action of closing and flushing a file, can make a REXX script that works under one implementation crash under another, so this feature is of very limited value if you are trying to write portable programs.

TRL says that because the operating system environments will differ a lot, and an efficient and useful interpreter is the most important goal, implementations are allowed to deviate from the standard in any respect necessary in the domain of I/O [TRL2]. Thus, you should never assume anything about the I/O system, as the "rules" listed in TRL are only advisory.

Where Implementations might Differ anyway

In the section above, some areas where the standard allows implementations to differ are listed. In an ideal world, that ought to be the only traps that you should need to look out for, but unfortunately, the world is not ideal. There are several areas where the requirements set up by the standard is quite high, and where implementations are likely to differ from the standard.

These areas are:

Repositioning at (for the current write position) or beyond the end-of-file may be allowed. On some systems, to prohibit that would require a lot of checking, so some systems will probably skip that check. At least for some operating systems, the act of repositioning after end-of-file is a useful feature.

Under Unix, it can be used for creating a dynamically sized random access file; do not bother about how much space is allocated for the file, just position to the correct "sloth" and write the data there. If the data file is sparse, holes might occur in the file; that is parts of the file which has not been written, and which is all zeros (and which are therefore not stored on disk.

Some implementations will use the same position for both the current read position and the current write position to overcome these implementations. Whenever you are doing a read, and the previous operation was a write (or vice versa), it is may prove useful to reposition the current read (or write) position.

There might be a maximum linesize for your REXX interpreter. At least the 50Kb limit on string length may apply.

Handling the situation where another program writes data to a file which is used by the REXX interpreter for reading.

LINES() and CHARS() are Inaccurate

2025/11/17 15:12

Because of the large differences between various operating systems, REXX allows some fuzz in the implementation of the LINES() and CHARS() built-in functions. Sometimes, it is difficult to calculate the number of lines or characters in a stream; generally because the storage format of the file often requires a linear search through the whole stream to determine that number. Thus, REXX allows an implementation to return the value 1 for any situation where the real number is difficult or impossible to determine. Effectively, an implementation can restrict the domain of return values for these two functions only 1 and 0 from these two functions.

Many operating systems store lines using a special end-of-line character sequence. For these systems, it is very time-consuming to count the number of lines in a file, as the file must be scanned for such character sequences. Thus, it is very tempting for an implementor to return the value 1 for any situation where there are more than zero lines left.

A similar situation arises for the number of characters left, although it is more common to know this number, thus it is generally a better chance of CHARS() returning the true number of characters left than LINES() returning the true number of lines left.

However, you can be fairly sure that if an implementation returns a number greater than 1, then that number is the real number of lines (or characters) left in the stream. And simultaneously, if the number returned is 0, then there is no lines (or characters) left to be read in the stream. But if the number is 1, then you will never know until you have tried.

Example: File reading idiom

This example shows a common idiom for reading all contents of a file into REXX variables using the LINES() and LINEIN() built-in functions.

```
i = 1
signal on notready
lleft = lines(file)
do while lleft>0
    do i=i to i+lleft
        line.i = linein(file)
```

```
end
lleft = lines(file)
end

notready:
    lines.0 = i-1
```

Here, the two nested loops iterates over all the data to be read. The innermost loop reads all data currently available, while the outermost loop checks for more available data. Implementations having a LINES() that return only 0 and 1 will generally iterate the outermost loop many times; while implementations that returns the "true" number from LINES() generally only iterates the outermost loop once.

There is only one place in this code that LINEIN() is called. The I variable is incremented at only one place, and the variable LINES.0 is set in one clause, too. Some redundancy can be removed by setting the WHILE expression to:

```
do while word(value('lleft',lines(file)) lleft,2)>0
```

The two assignments to the LLEFT variable must be removed. This may look more complicated, but it decreases the number of clauses having a call to LINES() from two till one. However, it is less certain that this second solution is more efficient, since using VALUE() built-in function can be inefficient over "normal" variable references.

The Last Line of a Stream

How to handle the last line in a stream is sometimes a problem. If you use a system that stores endof-lines as special character sequences, and the last part of the data of a stream is an unterminated line, then what is returned when you try to read that part of data?

There are three possible solutions: First, it may interpret the end-of-file itself as an implicit end-of-line, in this case, the partial part of the line is returned, as if it was properly terminated. Second, it may raise the NOTREADY condition, since the end-of-file was encountered during reading. Third, if there is any chance of additional data being appended, it may wait until such data are available. The second and third approaches are suitable for persistent and transient files, respectively.

The first approach is sometimes encountered. It has some problems though. If the end of a stream contains the data ABC<NL>XYZ, then it might return the string XYZ as the last line of the stream. However, suppose the last line was an empty line, then the last part of the stream would be: ABC<NL>. Few would argue that there is any line in this stream after the line ABC. Thus, the decision whether the end-of-file is an implicit end-of-line depends on whether the would-be last line has zero length or not.

An pragmatic solution is to let the end-of-file only be an implicit end-of-file if the characters immediately in front of it are not an explicit end-of-line character sequence.

However, TRL gives some indications that an end-of-file is not an implicit end-of-line. It says that LINES() returns the number of complete lines left, and that LINEIN() returns a complete line. On the other hand, the end-of-line sequence is not rigidly defined by TRL, so an implementor is almost free to define end-of-line in just about any terms that are comfortable. Thus, the last line of a stream may be

a source of problem if it is not explicitly terminated by an end-of-line.

Other Parts of the I/O System

This section lists some of the other parts of REXX and the environments around REXX that may be considered a part of the I/O system.

[Stack.]

The stack be used to communicate with external environments. At the REXX side, the interface to the stack is the instructions PUSH, PULL, PARSE PULL, and QUEUE; and the built-in function QUEUED(). These can be used to communicate with external programs by storing data to be transferred on the stack.

[The STREAM() built-in function.]

This function is used to control various aspects about the files manipulated with the other standard I/O functions. The standard says very little about this function, and leaves it up to the implementor to specify the rest. Operations like opening, closing, truncating, and changing modes

[The SAY instruction.]

The SAY instruction can be used to write data to the default output stream. If you use redirection, you can indirectly use it to write data to a file.

[The ADDRESS instruction.]

The ADDRESS instruction and commands can be used to operate on files, depending on the power of your host environments and operating system.

[The VALUE() built-in function.]

The function VALUE(), when used with three parameters, can be used to communicate with external host environments and the operating system. However, this depends on the implementation of your interpreter.

[SAA API.]

The SAA API provides several operations that can be used to communicate between processes. In general, SAA API allows you to perform the operations listed above from a binary program written in a language other than REXX.

And of course, I/O is performed whenever a REXX program or external function is started.

Implementation-Specific Information

This section describes some implementations of stream I/O in REXX. Unfortunately, this has become a very large section, reflecting the fact that stream I/O is an area of many system-specific solutions.

In addition, the variations within this topic are rather large. Regina implements a set of functions that are very close to that of TRL2. The other extreme are ARexx and BRexx, which contain a set of

functions which is very close to the standard I/O library of the C programming language.

Stream I/O in Regina

Regina implements stream I/O in a fashion that closely resembles how it is described in TRL2. The following list gives the relevant system-specific information.

[Names for standard streams.]

Regina uses <stdout> and <stdin> as names for the standard output and input streams. Note that the angle brackets are part of the names. You may also access the standard error stream (on systems supporting this stream) under the name <stderr>. In addition, the nullstring is taken to be equivalent to an empty first parameter in the I/O-related built-in functions.

[Implicit opening.]

Regina implicitly opens any file whenever it is first used.

If the first operation is a read, it will be opened in read-only mode. If the first operation is a write, it is opened in read-write mode. In this case if the read-write opening does not succeed, the file is opened in write-only mode. If the file exists, the opening is non-destructive, i.e. that the file is not truncated or overwritten when opened, else it is created if opened in read-write mode.

If you name a file currently open in read-only mode in a write operation, Regina closes the file, and reopens it in read-write mode. The only exception is when you call LINEOUT() with both second and third arguments unspecified, which always closes a file, both for reading and writing. Similarly, if the file was opened in write-only mode, and you use it in a read operation, Regina closes and reopens in read-write mode.

This implicit reopening is enabled by default. You can turn it off by unsetting the extension ExplicitOpen.

[Separate current positions.]

The environment in which Regina operates (ANSI C and POSIX) does not allow separate read and write positions, but only supplies one position for both operations. Regina handles this by maintaining the two positions internally, and move the "real" current position back and forth depending on whether a read or write operation is next.

[Swapping out file descriptors.]

In order to defend itself against "open-many-close-none" programming, Regina tries to "swap out" files that have been unused for some time. Assume that your operating system limits Regina to 100 simultaneously open files; when your try to open your 101st file, Regina closes the least recently used stream, and recycles its descriptor for the new file. You can enable or disable this recycling with the SwapFilePtr extension.

During this recycling, Regina only closes the file in the operating system, but retains all vital information about the file itself. If you re-access the file later, Regina reopens it, and positions the current read and write positions at the correct (i.e. previous) positions. This introduces some uncertainties into stream processing. Renaming a file affects it only if it gets swapped out. Since the swap operation is something the users do not see, it can cause some strange effects.

Regina will not allow a transient stream to be swapped out, since they often are connected to some sort of active partner in the other end, and closing the file might kill the partner or make it impossible to reestablish the stream. So only persistent files are swapped out. Thus, you can still fill the file table in Regina.

[Explicit opening and closing.]

Regina allows streams to be explicitly opened or closed through the use of the built-in function STREAM(). The exact syntax of this function is described in section stream. Old versions of Regina supported two non-standard built-in functions OPEN() and CLOSE() for these operations. These functions are still supported for compatibility reasons, but might be removed in future releases. Their availability is controlled by the OpenBif and CloseBif extensions.

[Truncation after writing lines.]

If you reposition line-wise the current write position to the middle of a file, Regina truncates the file at the new position. This happens whether data is written during the LINEOUT() or not. If not, the file might contain half a line, some lines might disappear, and the linecount would in general be disrupted. The availability of this behavior is controlled by LineOutTrunc, which is turned on by default.

Unfortunately, the operation of truncating a file is not part of POSIX, and it might not exist on all systems, so on some rare systems, this truncating will not occur. In order to be able to truncate a file, your machine must have the ftruncate() system call in C. If you don't have this, the truncating functionality is not available.

[Caching info on lines left.]

When Regina executes the built-in function LINES() for a persistent stream, it caches the number of lines left as an attribute to the stream. In subsequent calls to LINEIN(), this number is updated, so that subsequent calls to LINES() can retrieve the cached number instead of having to re-scan the rest of the stream, provided that the number is still valid.

Some operations will invalidate the count: repositioning the current read position; reading using the character oriented I/O, i.e. CHARIN(); and any write operation by the same interpreter on the stream. Ideally, any write operation should invalidate the count, but that might require a large overhead before any operation, in order to check whether the file has been written to by other programs.

This functionality can be controlled by the extension called CacheLineNo, which is turned on by default. Note that if you turn that off, you can experience a serious decrease in performance.

The following extra built-in functions relating to stream I/O are defined in Regina. They are provided for extra support and compatibility with other systems. Their support may be discontinued in later versions, and they are likely to be moved to a library of extra support.

CLOSE(streamid)

Closes the stream named by streamid. This stream must have been opened by implicit open or by the OPEN function call earlier. The function returns 1 if there was any file to close, and 0 if the file was not opened. Note that the return value does not indicate whether the closing was successful.

You can use the extension named CloseBif with the OPTIONS instruction to select or remove this function. This function is now obsolete, instead you should use:

STREAM(streamid, 'Command', 'CLOSE')

| CLOSE(myfile) | 1 | if stream was open |
|---------------------|---|------------------------|
| CLOSE('NOSUCHFILE') | 0 | if stream didn't exist |

```
OPEN(streamid,access)
```

Opens the stream named streamid with the access access. If access is not specified, the access R will be used. access may be the following characters. Only the first character of the access is needed.

[R]

(Read) Open for read access. The file pointer will be positioned at the start of the file, and only read operations are allowed.

[W]

(Write) Open for write access and position the current write position at the end of the file. An error is returned if it was not possible to get appropriate access.

The return value from this function is either 1 or 0, depending on whether the named stream is in opened state after the operation has been performed.

Note that if you open the files "foobar" and "./foobar" they will point to the same physical file, but Regina interprets them as two different streams, and will open a internal file descriptor for each one. If you try to open an already open stream, using the same name, it will have no effect.

You can use the extension OpenBif with the OPTIONS instruction to control the availability of this function. This function is now obsolete, but is still kept for compatibility with other interpreters and older versions of Regina. Instead, with Regina you should use:

STREAM(streamid, 'C', 'READ'|'WRITE'|'APPEND'|'UPDATE')

| OPEN(myfile, 'write') | 1 | maybe, if successful |
|-----------------------|---|---------------------------|
| OPEN(passwd, 'Write') | 0 | maybe, if no write access |
| OPEN('DATA', 'READ') | 0 | maybe, if successful |

The return value from this function is either 1 or 0, depending on whether the named stream is in opened state after the operation has been performed.

Functionality to be Implemented Later

This section lists the functionality not yet in Regina, but which is intended to be added later. Most of these are fixes to problems, compatibility modes, etc.

[Indirect naming of streams.]

Currently, streams are named directly, which is a convenient. However, there are a few problems: for instance, it is difficult to write to a file which name is <stdout>, simply because that is a reserved name. To fix this, an indirect naming scheme will be provided through the STREAM()< built-in function. The functionality will resemble the OPEN() built-in function of ARexx.

[Consistence in filehandle swapping.]

When a file handle is currently swapped out in order to avoid filling the system file table, very little checking of consistency is currently performed. At least, vital information about the file should be retained, such as the inode and file system for Unix machines retrieval by the fstat() call. When the file is swapped in again, this information must be checked against the file which is reopened. If there is a mismatch, NOTREADY should be raised.

Similarly, when reopening a file because of a new access mode is requested, the same checking should be performed.

[Files with holes.]

Regina will be changed to allow it to generate files with holes for system where this is relevant. Although standard REXX does not allow this, it is a very common programming idiom for certain systems, and should be allowed. It will, however, be controllable through a extension called SparseFiles.

Stream I/O in ARexx 1.15

ARexx differs considerably from standard REXX with respect to stream I/O. In fact, none of the standard stream functionality of REXX is available in ARexx. Instead, a completely distinct set of functions are used. The differences are so big, that it is useless to describe ARexx stream I/O in terms of standard REXX stream I/O, and everything said so far in this chapter is irrelevant for ARexx. Therefore, we explain the ARexx functionality from scratch.

All in all, the ARexx file I/O interface resembles the functions of the Standard C I/O library, probably because ARexx is written in C, and the ARexx I/O functions are "just" interfaces to the underlying C functions. You may want to check up the documentation for the ANSI C I/O library as described in [ANSIC], [KR], and [PJPlauger].

ARexx uses a two level naming scheme for streams. The file names are bound to a stream name using the OPEN() built-in function. In all other I/O functions, only the stream name is used.

```
OPEN( name , filename [, mode ])
```

You use the OPEN() built-in function to open a stream connected to a file called filename in AmigaDOS. In subsequent I/O calls, you refer to the stream as name. These two names can be different.

The name parameter cannot already be in use by another stream. If so, the OPEN() function fails. Note that the name parameter is case-sensitive. The filename parameter is not strictly case-sensitive: the case used when creating a new file is preserved, but when referring to an existing file, the name is case-insensitive. This is the usual behavior of AmigaDOS.

If any of the other I/O operations uses a stream name that has not been properly opened using OPEN(), that operation fails, because ARexx has no auto-open-on-demand feature.

The optional parameter mode can be any of Read, Write, or Append. The mode Read opens an existing file and sets the current position to the start of the file. The mode Append is identical to Read, but sets the current positions to the end-of-file. The mode Write creates a new file, i.e. if a file

with that name already exists, it is deleted and a new file is created. Thus, with Write you always start with an empty file. Note that the terms "read," "write," and "append" are only remotely connected to the mode in which the file is opened. Both reading and writing are allowed for all of these three modes; the mode names only reflect the typical operations of these modes.

The result from OPEN() is a boolean value, which is 1 if a file by the specified name was successfully opened during the OPEN() call, and 0 otherwise.

The number of simultaneously open files is no problem because AmigaDOS allocates files handles dynamically, and thus only limited by the available memory. One system managed 2000 simultaneously open files during a test.

| OPEN('infile', 'work:DataFile') | 1 | if successful |
|------------------------------------|---|------------------|
| OPEN('work', 'RAM:FooBar', 'Read') | 0 | if didn't exist |
| OPEN('output', 'TmpFile', 'W') | 1 | (re)creates file |

```
CLOSE( name )
```

You use the CLOSE() built-in function to close a stream. The parameter name must match the first parameter in a call to OPEN() earlier in the same program, and must refer to an open stream. The return value is a boolean value that reflects whether there was a file to close (but not whether it was successfully closed).

| | $\overline{}$ | if stream was previously open |
|------------------|---------------|----------------------------------|
| CLOSE('outfile') | 0 | if stream wasn't previously open |

```
WRITELN( name , string )
```

The WRITELN() function writes the contents of string as a line to the stream name. The name parameter must match the value of the first parameter in an earlier call to OPEN(), and must refer to an open stream. The data written is all the characters in string immediately followed by the newline character (ASCII <Ctrl-J> for AmigaDOS).

The return value is the number of characters written, including the terminating newline. Thus, a return value of 0 indicates that nothing was written, while a value which is one more than the number of characters in string indicates that all data was successfully written to the stream.

When writing a line to the middle of a stream, the old contents is written over, but the stream is not truncated; there is no way to truncate a stream with the ARexx built-in functions. This overwriting can leave partial lines in the stream.

| WRITELN('tmp', 'Hello, world!') | 14 | if successful |
|---------------------------------|----|----------------------|
| WRITELN('work', 'Hi there') | 0 | nothing was written |
| WRITELN('tmp', 'Hi there') | 5 | partially successful |

```
WRITECH( name , string )
```

The WRITECH() function is identical to WRITELN(), except that the terminating newline character is not added to the data written out. Thus, WRITELN() is suitable for line-wise output, while WRITECH() is useful for character-wise output.

| WRITECH('tmp', 'Hello, world!') | 13 | if successful |
|---------------------------------|----|----------------------|
| WRITECH('work', 'Hi there') | 0 | nothing was written |
| WRITECH('tmp', 'Hi there') | 5 | partially successful |

READLN(name)

The READLN() function reads a line of data from the stream referred to by name. The parameter name must match the first parameter of an earlier call to OPEN(), i.e. it must be an open stream.

The return value is a string of characters which corresponds to the characters in the stream from and including the current position forward to the first subsequent newline character found. If no newline character is found, the end-of-file is implicitly interpreted as a newline and the end-of-file state is set. However, the data returned to the user never contains the terminating end-of-line.

To differ between the situation where the last line of the stream was implicitly terminated by the endof-file and where it was explicitly terminated by an end-of-line character sequence, use the EOF() built-in function. The EOF() returns 1 in the former case and 0 in the latter case.

There is a limit in ARexx on the length of lines that you can read in one call to READLN(). If the length of the line in the stream is more than 1000 characters, then only the first 1000 characters are returned. The rest of the line can be read by additional READLN() and READCH() calls. Note that whenever READLN() returns a string of exactly 1000 characters, then no terminating end-of-line was found, and a new call to READLN() must be executed in order to read the rest of the line.

| READLN('tmp') | Hello world! | maybe |
|----------------|--------------|------------------------|
| READLN('work') | | maybe, if unsuccessful |

READCH(name [, length])

The READCH() built-in function reads characters from the stream named by the parameter name, which must correspond to the first parameter in a previous call to OPEN(). The number of characters read is given by length, which must be a non-negative integer. The default value of length is 1.

The value returned is the data read, which has the length corresponding to the length parameter if no errors occurred.

There is a limit in ARexx for the length of strings that can be read in one call to READCH(). The limit is 65535 bytes, and is a limitation in the maximum size of an ARexx string.

| READCH('tmp',3) | Hel | maybe |
|-----------------|--------|-------|
| READCH('tmp') | I | maybe |
| READCH('tmp',6) | o worl | maybe |

EOF(name)

The EOF() built-in function tests to see whether the end-of-file has been seen on the stream specified by name, which must be an open stream, i.e. the first parameter in a previous call to OPEN().

The return value is 1 if the stream is in end-of-file mode, i.e. if a read operation (either READLN() or READCH()) has seen the end-of-file during its operation. However, reading the last character of the stream does not put the stream in end-of-file mode; you must try to read at least one character past

the last character. If the stream is not in end-of-file mode, the return value is 0.

Whenever the stream is in end-of-file mode, it stays there until a call to SEEK() is made. No read or write operation can remove the end-of-file mode, only SEEK() (and closing followed by reopening).

| EOF('tmp') | | |
|-------------|---|-------|
| EOF('work') | 1 | maybe |

The SEEK() built-in function repositions the current position of the file specified by the parameter name, which must correspond to an open file, i.e. to the first parameter of a previous call to OPEN(). The current position in the file is set to the byte referred to by the parameter offset. Note that offset is zero-based, so the first byte in the file is numbered 0. The value returned is the current position in the file after the seek operation has been carried through, using Beginning mode.

If the current position is attempted set past the end-of-file or before the beginning of the file, then the current position is not moved, and the old current position is returned. Note that it is legal to position at the end-of-file, i.e. the position immediately after the last character of the file. If a file contains 12 characters, the valid range for the resulting new current position is 0-12.

The last parameter, mode, can take any of the following values:

Beginning, Current, or End. It specify the base of the seeking, i.e. whether it is relative to the first byte, the end-of-file position, or the old current position. For instance: for a 20 byte file with current position 3, then offset 7 for base Beginning is equivalent to offset -13 for base End and offset 4 for Current. Note that only the first character of the mode parameter is required, the rest of that parameter is ignored.

| SEEK('tmp', 12, 'B') | 12 | if successful |
|---------------------------|----|--------------------------------------|
| SEEK('tmp', -4, 'Begin') | 12 | if previously at 12 |
| SEEK('tmp', -10, 'E') | 20 | if length is 30 |
| SEEK('tmp', 5) | 17 | if previously at 12 |
| SEEK('tmp', 5, 'Celcius') | 17 | only first character in mode matters |
| SEEK('tmp', 0, 'B') | 0 | always to start of file |

Main Differences from Standard REXX

Now, as the functionality has been explained, let me point out the main conceptual differences from standard REXX; they are:

[Current position.]

ARexx does not differ between a current read and write position, but uses a common current position for both reading and writing. Further, this current position (which it is called in this documentation) can be set to any byte within the file, and to the end-of-file position. Note that the current position is zero-based.

[Indirect naming.]

The stream I/O operations in ARexx do not get a parameter which is the name of the file. Instead,

ARexx uses an indirect naming scheme. The OPEN() built-in function binds a REXX stream name for a file to a named file in the AmigaDOS operating system; and later, only the REXX stream name is used in other stream I/O functions operating on that file.

[Special stream names.]

There are two special file names in ARexx: STDOUT and STDIN, which refer to the standard input file and standard output file. With respect to the indirect naming scheme, these are not file names, but names for open streams; i.e. they can be used in stream I/O operations other than OPEN(). For some reason, is it possible to close STDIN but not STDOUT.

[NOTREADY not supported.]

ARexx has no NOTREADY condition. Instead, you must detect errors by calling EOF() and checking the return codes from each I/O operations.

[Other things missing.]

In ARexx, all files must be explicitly opened. There is no way to reposition line-wise, except for reading lines and keeping a count yourself.

Of course, ARexx also has a lot of functionality which is not part of standard REXX, like relative repositioning, explicit opening, an end-of-file indicator, etc. But this functionality is descriptive above in the descriptions of extended built-in functions, and it is of less interest here.

When an ARexx script has opened a file in Write mode, other ARexx scripts are not allowed to access that file. However, if the file is opened in Read or Append mode, then other ARexx scripts can open the file too, and the same state of the contents of the file is seen by all scripts.

Note that it is difficult to translate between using standard REXX stream I/O and ARexx stream I/O. In particular, the main problem (other than missing functionality in one of the systems) is the processing of end-of-lines. In standard REXX, the end-of-file is detected by checking whether there is more data left, while in ARexx one checks whether the end-of-file has been read. The following is a common standard REXX idiom:

```
while lines('file')>0 /* for each line available */
  say linein('file') /* process it */
end
```

In ARexx this becomes:

```
tmp = readln('file') /* attempt to read first line */
do until eof('file') /* if EOF was not seen */
  say tmp /* process line */
  tmp = readln('file') /* attempt to read next line */
end
```

It is hard to mechanically translate between them, because of the lack of an EOF() built-in function in standard REXX, and the lack of a LINES() built-in function in ARexx.

Note that in the ARexx example, an improperly terminated last line is not read as an independent line, since READLN() searches for an end-of-line character sequence. Thus, in the last invocation tmp is set to the last unterminated line, but EOF() returns true too. To make this different, make the UNTIL subterm of the DO loop check for the expression EOF('file') && TMP<>".

The limit of 1000 characters for READLN() means that a generic line reading routine in ARexx must be similar to this:

```
readline: procedure
  parse arg filename line = ''
  do until length(tmpline)<1000
    tmpline = readln(filename)
    line = line || tmpline
  end
  return line</pre>
```

This routine calls READLN() until it returns a line that is shorter than 1000 characters. Note that endof-file checking is ignored, since READLN() returns an empty string a the end-of-stream.

Stream I/O in BRexx 1.0b

BRexx contains a set of I/O which shows very close relations with the C programming language I/O library. In fact, you should consider consulting the C library documentation for in-depth documentation on this functionality.

BRexx contains a two-level naming scheme: in REXX, streams are referred to by a stream handle, which is an integer; in the operating system files are referred to by a file name, which is a normal string. The function OPEN() is used to bind a file name to a stream handle. However, BRexx I/O functions generally have the ability to get a reference either as a file name and a stream handle, and open the file if appropriate. However, if the name of a file is an integer which can be interpreted as a file descriptor number, it is interpreted as a descriptor rather than a name. Whenever you use BRexx and want to program robust code, always use OPEN() and the descriptor.

If a file is opened by specifying the name in a I/O operation other than OPEN(), and the name is an integer and only one or two higher than the highest current file descriptor, strange things may happen.

Five special streams are defined, having the pseudo file names: <STDIN>, <STDOUT>, <STDERR>, <STDAUX>, and <STDPRN>; and are assigned pre-defined stream handles from 0 to 4, respectively. These refer to the default input, default output, and default error output, default auxiliary output, and printer output. The two last generally refer to the COM1: and LPT1: devices under MS-DOS. Either upper or lower case letter can be used when referring to these four special names.

However, note that if any of these five special files are closed, they can not be reopened again. The reopened file will be just a normal file, having the name e.g. <STDOUT>.

There is a few things you should watch out for with the special files. I/O involving the <STDAUX> and <STDPRN> can cause the Abort, Retry, Ignore message to be shown once for each character that was attempted read or written. It can be boring and tedious to answer R or I if the text string is long. If A is answered, BRexx terminates.

You should never write data to file descriptor 0 (<STDIN>), apparently, it will only disappear.

Likewise, never read data to file descriptors 1 and 2 (<STDOUT> and <STDERR>), the former seems to terminate the program while the latter apparently just returns the nullstring. Also be careful with reading from file descriptors 3 and 4, since your program may hang if no data is available.

OPEN(file , mode)

The OPEN() built-in function opens a file named by file, in mode mode, and returns an integer which is the number of the stream handle assigned to the file. In general, the stream handle is a non-negative integer, where 0 to 4 are pre-defined for the default streams. If an error occurred during the open operation, the value -1 is returned.

The mode parameter specifies the mode in which the file is opened. It consists of two parts: the access mode, and the file mode. The access mode part consists of one single character, which can be r for read, w for write, and a for append. In addition, the + character can be appended to open a file in both read and write mode. The file mode part can also have of one additional character which can be t for text files and b for binary files. The t mode is default.

The following combinations of + and access mode are possible:

r is non-destructive open for reading;

w is destructive open for write-only mode;

a is non-destructive open for in append-only mode, i.e. only write operations are allowed, and all write operations must be performed at the end-of-file;

r+ is non-destructive open for reading and writing;

w+ is destructive open for reading and writing; and a+ is non-destructive open in append update, i.e. reading is allowed anywhere, but writing is allowed only at end-of-file. Destructive mode means that the file is truncated to zero length when opened.

In addition, the b and t characters can be appended in order to open the file in binary or text mode.

These modes are the same as under C, although the t mode character is strictly not in ANSI C. Also note that r, w, and a are mutually exclusive, but one of them must always be present. The mode + is optional, but if present, it must always come immediately after r, w, or a. The t and b modes are optional and mutually exclusive; the default is t. If present, t or b must be the last character in the mode string.

| open('myfile','w') | 7 | perhaps |
|--------------------------|----|-----------------|
| open('no.such.file','r') | -1 | if non-existent |
| open('c:tmp','r+b') | 6 | perhaps |

If two file descriptors are opened to the same file, only the most recently of them works. However, if the most recently descriptor is closed, the least recently starts working again. There may be other strange effects too, so try avoid reopening a file that is already open.

CLOSE(file)

The CLOSE() built-in function closes a file that is already open. The parameter file can be either a stream handle returned from OPEN() or a file name which has been opened (but for which you do not

Last update: 2024/09/04 06:58

known the correct stream handle).

The return value of this function seems to be the nullstring in all cases.

| close(6) | if open |
|-----------------|-------------|
| close(7) | if not open |
| close('foobar') | perhaps |

EOF(file)

The EOF() built-in function checks the end-of-file state for the stream given by file, which can be either a stream descriptor or a file name. The value returned is 1 if the end-of-file status is set for the stream, and 0 if it is cleared. In addition, the value -1 is returned if an error occurred, for instance if the file is not open.

The end-of-file indicator is set whenever an attempt was made to read at least one character past the last character of the file. Note that reading the last character itself will not set the end-of-file condition.

| eof(foo) | 0 | if not at eof |
|---------------------|----|--------------------|
| eof('8') | 1 | if at eof |
| eof('no.such.file') | -1 | if file isn't open |

READ([file][, length])

The READ() built-in function reads data from the file referred to by the file parameter, which can be either a file name or a stream descriptor. If it is a file name, and that file is not currently open, then BRexx opens the file in mode rt. The default value of the first parameter is the default input stream. The data is read from and including the current position.

If the length parameter is not specified, a whole line is read, i.e. reading forwards to and including the first end-of-line sequence. However, the end-of-line sequence itself is not returned. If the length parameter is specified, it must be a non-negative integer, and specified the number of characters to read.

The data returned is the data read, except that if length is not specified, the terminating end-of-line sequence is stripped off. If the last line of a file contains a string unterminated by the end-of-string character sequence, then the end-of-file is implicitly interpreted as an end-of-line. However, in this case the end-of-file state is entered, since the end-of-stream was found while looking for an end-of-line.

| read('foo') | one line | reads a complete line |
|---------------|-------------|---|
| read('foo',5) | anoth | reads parts of a line |
| read(6) | er line | using a file descriptor |
| read() | hello there | perhaps, reads line from default input stream |

```
WRITE([ file ][,[ string ][, dummy ]])
```

The WRITE() built-in function writes a string of data to the stream specified by the file parameter, or by default the default output stream. If specified, file can be either a file name or a stream descriptor. If it is a file name, and that file is not already open, it is opened using wt mode.

The data written is specified by the string parameter.

The return value is an integer, which is the number of bytes written during the operation. If the file is opened in text mode, all ASCII newline characters are translated into ASCII CRLF character sequences. However, the number returned is not affected by this translation; it remains independent of any text of binary mode. Unfortunately, errors while writing is seldom trapped, so the number returned is generally the number of character that was supposed to be written, independent of whether they was actually written or not.

If a third parameter is specified, the data is written as a line, i.e. including the end-of-line sequence. Else, the data is written as-is, without any end-of-line sequence. Note that with BRexx, the third parameter is considered present if at least the comma in front of it-the second comma-is present. This is a bit inconsistent with the standard operations of the ARG() built-in function. The value of the third parameter is always ignored, only its presence is considered.

If the second parameter is omitted, only an end-of-line action is written, independent of whether the third parameter is present or not.

| write('bar','data') | 4 | writes four bytes |
|--------------------------|------|-------------------|
| write('bar','data','nl') | 4+?? | write a line |
| write('bar','data',) | 4+?? | same as previous |

SEEK(file [,[offset][, origin]])

The SEEK() built-in function moves the current position to a location in the file referred to by file. The parameter file can be either a file name (which must already be open) or a stream descriptor.

This function does not implicitly open files that is not currently open.

The parameter offset determines the location of the stream and must be an integer. It defaults to zero. Note that the addressing of bytes within the stream is zero-based.

The third parameter can be any of TOF, CUR, or EOF, in order to set the reference point in which to recon the offset location. The three strings refer to top-of-file, current position, and end-of-file, and either upper or lower case can be used. The default value is ???.

The return value of this function is the absolute position of the position in the file after the seek operation has been performed.

The SEEK() function provides a very important additional feature. Whenever a file opened for both reading and writing has been used in a read operation and is to be used in a write operation next (or vice versa), then a call to SEEK() must be performed between the two I/O calls. In other words, after a read only a seeking and reading may occur; after a write, only seeking and writing may occur; and after a seek, reading, writing, and seeking may occur.

Problems with Binary and Text Modes

Under the MS-DOS operating system, the end-of-line character sequence is <CR><LF>, while in C, the end-of-line sequence is only <LF>. This opens for some very strange effects.

When an MS-DOS file is opened for read in text mode by BRexx, all <CR><LF> character sequences

in file data are translated to <LF> when transferred into the C program. Further, BRexx, which is a C program, interprets <LF> as an end-of-line character sequence. However, if the file is opened in binary mode, then the first translation from <CR><LF> in the file to <LF> into the C program is not performed. Consequently, if a file that really is a text file is opened as a binary file and read line-wise, all lines would appear to have a trailing <CR> character.

Similarly, <LF> written by the C program is translated to <CR><LF> in the file. This is always done when the file is opened in text mode. When the file is opened in binary mode, all data is transferred without any alterations. Thus, when writing lines to a file which is opened for write in binary mode, the lines appear to have only <LF>, not <CR><LF>. If later opened as a text file, this is not recognized as an end-of-line sequence.

Example: Differing end-of-lines

Here is an example of how an incorrect choice of file type can corrupt data. Assume BRexx running under MS-DOS, using <CR><LF> as a end-of-line sequence in text files, but the system calls translating this to <LF> in the file I/O interface. Consider the following code.

```
file = open('testfile.dat', 'wt') /* text mode */
call write file, '45464748'x, 'dummy' /* i.e. 'abcd' */
call write file, '65666768'x, 'dummy' /* i.e. 'ABCD' */
call close file

file = open('testfile.dat', 'rb') /* binary mode */
say c2x(read(file)) /* says '454647480D' */
say c2x(read(file)) /* says '656667680D' */
call close file
```

Here, two lines of four characters each are written to the file, while when reading, two lines of five characters are read. The reason is simply that the writing was in text mode, so the end-of-line character sequence was <CR><LF>; while the reading was in binary mode, so the end-of-line character sequence was just <LF>. Thus, the <CR> preceding the <LF> is taken to be part of the line during the read.

To avoid this, be very careful about using the correct mode when opening files. Failure to do so will almost certainly give strange effects.

Extensions

This chapter describes how extensions to Regina are implemented. The whole contents of this chapter is specific for Regina.

Why Have Extensions

Why do we need extensions? Well, there are a number of reasons, although not all of these are very good reasons:

Adaptations to new environments may require new functionality in order to easily interface to the operating system.

Extending the language with more power, to facilitate programming.

Sometimes, a lot of time can be saved if certain assumptions are met, so an extension might be implemented to allow programmers to take shortcuts.

When a program is ported from one platform to another, parts of the code may depend of nonstandard features not available on the platform being ported to. In this situation, the availability of extensions that implement the feature may be of great help to the programmer.

The implementor had some good idea during development.

Backwards compatibility.

Extensions arise from holes in the functionality. Whether they will survive or not depends on how they are perceived by programmers; if perceived as useful, they will probably be used and thus supported in more interpreters.

Extensions and Standard REXX

In standard REXX, the OPTIONS instruction provides a "hook" for extensions. It takes any type of parameters, and interprets them in a system-dependent manner.

The format and legal values of the parameters for the OPTIONS instruction is clearly implementation dependent [TRL2, p62].

Specifying Extensions in Regina

In Regina there are three level of extensions. Each independent extension has its own name. Exactly what an independent extension is, will depend on the viewer, but a classification has been done, and is listed at the end of this chapter.

At the lowest level are these "atomic" extensions. Then there are some "meta-extensions". These are collections of other extensions which belong together in some manner. If you need the extension for creating "buffers" on the stack, it would be logical to use the extension to remove buffers from the stack too. Therefore, all the individual extensions for operations that handle buffers in the stack can be named by such a "meta-extensions". At the end of this chapter, there is a list of all the meta-extensions, and which extensions they include.

At the top is "standards". These are sets of extensions that makes the interpreter behave in a fashion compatible with some standard. Note that "standard" is used very liberally, since it may refer to other implementations of REXX. However, this description of how the extensions are structured is only followed to some extent. Where practical, the structure has been deviated.

The Trouble Begins

Last update: 2024/09/04 06:58

There is one very big problem with extensions. If you want to be able to turn them on and off during execution, then your program has to be a bit careful.

More and more REXX interpreters (including Regina parsing the program when the interpreter is started. The "old" way was to postpone the parsing of each clause until it was actually executed. This leads to the problem mentioned.

Suppose you want to use an extension that allows a slightly different syntax, for the sake of the argument, let us assume that you allow an expression after the SELECT keyword. Also assume that this extension is only allowed in extended mode, not in "standard mode". However, since Regina parses the source code only once (typically at the starts of the program), the problem is a catch-22: the extension can only be turned on after parsing the program, but it is needed before parsing. This also applies to a lot of other REXX interpreters, and all REXX compilers and preprocessors.

If the extension is not turned on during parsing, it will generate a syntax error, but the parsing is all done before the first clause is executed. Consequently, this extension can not be turned on during execution, it has to be set before the parsing starts.

Therefore, there are two alternative ways to invoke a set of extensions before the REXX program is parsed:

It can be invoked by setting an environment variable, which must be a string of the same format as the parameters to the OPTIONS clause. Regina supports this mechanism by the use of the REGINA OPTIONS environment variable.

It can be invoked by using a command line option to the interpreter -o; which must be a string of the same format as the parameters to the OPTIONS clause. The command line switch overwrites any option specified in the REGINA OPTIONS environment variable.

The Format of the OPTIONS clause

The format of the OPTIONS clause is very simple, it is followed by any REXX string expression, which is interpreted as a set of space separated words. The words are treated strictly in order from left to right, and each word can change zero or more extension settings.

Each extension has a name. If the word being treated matches that name, that extension will be turned on. However, if the word being treated matches the name of an extension but has the prefix NO, then that extension is turned off. If the word does not match any extensions, then it is simply ignored, without creating any errors or raising any conditions.

Example: Extensions changing parsing

An example of this is the LINES BIF. In the following piece of code the same BIF returns different data:

```
/* file 'aa' contains 5 lines */
options FAST_LINES_BIF_DEFAULT
```

```
do i=1 to 2
   if i=2 then
        OPTIONS NOFAST_LINES_BIF_DEFAULT
   say lines('aa')
end
```

In the first iteration of the loop, LINES('aa') returns 1, indicating that there is at least 1 line remaining the the stream 'aa'. However, in the second iteration of the loop, LINES('aa') will return 5, indicating that there are 5 lines remaining in the stream.

Regina's frequent usage of extensions may slow down execution. To illustrate how this can happen, consider the OPEN() extra built-in function. As this is an extension, it might be dynamically included and excluded from the scope of currently defined function. Thus, if the function is used in a loop, it might be in the scope during the first iteration, but not the second. Thus, Regina can not cache anything relating to this function, since the cached information may be outdated later. As a consequence, Regina must look up the function in the table of functions for each invocation. To avoid this, you can set the extension CACHEEXT, which tells Regina to cache info whenever possible, without regards to whether this may render useless later executions of OPTIONS.

The Fundamental Extensions

Here is a description of all "atomic" extensions in Regina:

[AREXX BIFS]

This option allows the user to enable or disable the AREXX BIFs introduced into Regina 3.1. The default is AREXX BIFS on Amiga and AROS, but NOAREXX BIFS on all other platforms.

[AREXX_SEMANTICS]

With the introduction of AREXX BIFs into Regina 3.1, differences in the semantics of a number of BIFs resulted. These BIFs that differ between Standard Regina and AREXX are OPEN(), CLOSE() and EOF(). This OPTION specifies that the AREXX semantics be used for these BIFs. The default is to use Regina semantics for these BIFs.

[BUFTYPE BIF]

Allows calling the built-in function BUFTYPE(), which will write out all the contents of the stack, indicating the buffers, if there are any. The idea is taken from VM/CMS, and its command named BUFTYPE.

[CALLS AS FUNCS]

Allows the old broken syntax of :

```
call myfunc(arg1,arg2)
```

New programs should use the standard syntax for the CALL instruction. As the determination of invalid syntax is done before the code is executed, then this OPTION can only be specified using the

Last update: 2024/09/04 06:58

REGINA OPTIONS environment variable.

NOCALLS AS FUNCS is the default.

[CACHEEXT]

Tells Regina that information should be cached whenever possible, even when this will render future execution of the OPTIONS instruction useless. Thus, if you use e.g. the OPEN() extra built-in function, and you set CACHEEXT, then you may experience that the OPEN() function does not disappear from the current scope when you set the NOOPEN BIF extension.

Whether or not a removal of an extension really does happen is unspecified when CACHEEXT has been called at least once. Effectively, info cached during the period when CACHEEXT was in effect might not be "uncached". The advantage of CACHEEXT is efficiency when you do not need to do a lot of toggling of some extension.

[DESBUF_BIF]

Allows calling the built-in function DESBUF(), to remove all contents and all buffers from the stack. This function is an idea taken from the program by the same name under VM/CMS.

[DROPBUF_BIF]

Allows calling the built-in function DROPBUF(), to removed one of more buffers from the stack. This function is an idea take from the program by the same name under VM/CMS.

[EXT COMMANDS AS FUNCS]

When Regina resolves an expression to a function, and that function is not a built-in or a registered external function, Regina attempts to execute the function as an operating system command. With NOEXT_COMMANDS_AS_FUNCS set, Regina will return error 43; "Routine not found". EXT_COMMANDS_AS_FUNCS is the default.

[FAST LINES BIF DEFAULT]

The LINES() BIF in versions of Regina prior to 0.08g returned the actual number of lines available in a stream. Since then, the LINES() BIF has been changed to only return 0 or 1. This was done for two reasons. First, it is faster, and secondly. the ANSI standard allows for an option to return the actual number of lines. This OPTION is for backwards compatibility with programs written assuming the prior behavior of the LINES() BIF. FAST_LINES_BIF_DEFAULT is the default.

[FLUSHSTACK]

Tells the interpreter that whenever a command clause instructs the interpreter to flush the commands output on the stack, and simultaneously take the input from the stack, then the interpreter will not buffer the output but flush it to the real stack before the command has terminated. That way, the command may read its own output. The default setting for Regina is not to flush, i.e. NOFLUSHSTACK, which tells interpreter to temporary buffer all output lines, and flush them to the stack when the command has finished.

[HALT ON EXT CALL FAIL]

This options tells the interpreter that when a called external routine fails the caller halts with a syntax

error 40.1. This behaviour also occurs with the STRICT_ANSI option.

167/248

NOHALT_ON_EXT_CALL_FAIL is the default.

[INTERNAL QUEUES]

Regina implements multiple named queues both as part of the interpreter, and as an external resource. If a queue name has the character '@' embedded, Regina will assume this to be an external queue name. This OPTION allows the exclusive use of Regina's internal queuing mechanism regardless of the queue name. NOINTERNAL QUEUES is the default.

[LINEOUTTRUNC]

This options tells the interpreter that whenever the LINEOUT() built-in function is executed for a persistent file, the file will be truncated after the newly written line, if necessary. This is the default setting of Regina, unless your system does not have the ftruncate() system call.

[MAKEBUF_BIF]

Allows calling the built-in function MAKEBUF(), to create a buffer on the stack. This function is an idea taken from a program by the same name under VM/CMS.

[PRUNE TRACE]

Makes deeply nested routines be displayed at one line. Instead of indenting the trace output at a very long line (possibly wrapping over several lines on the screen). It displays [...] at the start of the line, indicating that parts of the white space of the line has been removed.

PRUNE TRACE is the default.

[QUEUES 301]

This OPTION changes the behaviour of external queue names. In Regina 3.1 meaning was given to queue names. If a queue name had '@' in its name, it was identified as an external queue (requiring rxstack to be running). Before 3.1, any time RXQUEUE BIF was used, it always referenced an external queue. New programs should use the naming convention to identify external queues, because you will be able to use internal of external queues in other instructions like ADDRESS.WITH. The default is NOQUEUES_301.

[REGINA BIFS]

This OPTION allows the user to turn on all non-ANSI extension BIFs. The default is REGINA BIFS.

[SINGLE_LINE_COMMENTS]

By default Regina supports the NetRexx and ooRexx single line comment marker; '-'. (two minus signs abutted). This will break code that expects '-' to be semantically equivalent to '+'. To remove single line comments, use NOSINGLE_LINE_COMMENTS. As the determination of single line comments is done before code is executed then this OPTION can only be specified using the REGINA_OPTIONS environment variable or the '-o' command line switch. The default is SINGLE_LINE_COMMENTS.

[STDOUT_FOR_STDERR]

All output that Regina would normally write to stderr, such as TRACE output and errors, are written to

stdout instead. This is useful if you need to capture TRACE output and normal output from SAY to a file in the order in which the lines were generated. The default is NOSTDOUT FOR STDERR.

```
[STRICT_ANSI]
```

This OPTION results in interpretation of a program to strict ANSI standards, and will reject any Regina extensions. NOSTRICT_ANSI is the default. As this OPTION affects the initial parsing of the REXX program, it must be specified using the REGINA_OPTIONS environment variable or the '-o' command line switch.

```
[STRICT WHITE SPACE COMPARISONS]
```

This OPTION specifies if ANSI rules for non-strict comparisons are applied. Under ANSI, when doing non-strict comparisons, only the space character is stripped from the two comparators. Under Regina's default behavior, all whitespace characters are stripped.

NOSTRICT_WHITE_SPACE_COMPARISONS is the default.

```
[TRACE HTML]
```

This OPTION generates HTML <PRE> and </PRE> tags around TRACE output, to enable tracing from within CGI scripts. The default is NOTRACE_HTML. The following code shows the necessary header information to enable this feature:

```
#!/usr/bin/rexx
OPTIONS STDOUT_FOR_STDERR TRACE_HTML
Parse Version ver

/* following 2 lines MUST be 'sayed' before TRACE turned on */
Say 'Content-type: text/html'
Say

Say ver
Trace i
Say 'With tracing on'
Trace 0
Say 'With tracing off'
Return 0
```

The output from this would look like:

```
image here
```

Note: OPEN_BIF, FIND_BIF, CLOSE_BIF and FILEIO OPTIONs have been removed in Regina 3.1

Meta-extensions

[ANSI]

Combination of STRICT_ANSI and STRICT_WHITE_SPACE_COMPARISONS .

[BUFFERS]

Combination of BUFTYPE_BIF, DESBUF_BIF, DROPBUF_BIF and MAKEBUF_BIF.

Semi-standards

[CMS]

A set of extensions that stems from the VM/CMS operating system. Basically, this includes the most common extensions in the VM/CMS version of REXX, in addition of some functions that perform tasks normally done with commands under VM/CMS.

[VMS]

A set of interface functions to the VMS operating system. Basically, this makes the REXX programming under VMS as powerful as programming directly in DCL.

[UNIX]

A set of interface functionality to the Unix operating system. Basically, this includes some functions that are normally called as commands when programming Unix shell scripts.

Although it is possible to call these as commands in Regina, there are considerable speed improvements in implementing them as built-in functions.

Standards

The following table shows which options are available in different REXX Language Levels, and the default settings applicable for Regina.

[ANSI]

REXX Language level 5.0, as described in [ANSI].

[REGINA]

REXX Language level 5.0, plus extensions, as implemented by Regina 3.1 and above.

[SAA]

REXX Language level ??, as defined by IBM's System Application Architecture [SAA].

[TRL1]

REXX Language level 3.50, as described in [TRL1].

[TRL2]

REXX Language level 4.00, as described in [TRL2].

| Option | ANSI | REGINA | SAA | TRL1 | TRL2 |
|--------------------------------|------|--------|-----|------|------|
| AREXX_BIFS | no | yes | no | no | no |
| AREXX_SEMANTICS | no | no | no | no | no |
| BUFTYPE_BIF | no | yes | no | no | no |
| CACHEEXT | no | no | no | no | no |
| CALLS_AS_FUNCS | no | yes | no | no | no |
| DESBUF_BIF | no | yes | no | no | no |
| DROPBUF_BIF | no | yes | no | no | no |
| EXT_COMMANDS_AS_FUNCS | no | yes | no | no | no |
| FAST_LINES_BIF_DEFAULT | yes | yes | no | no | no |
| FLUSHSTACK | no | no | no | no | no |
| HALT_ON_EXT_CALL_FAIL | no | yes | no | no | no |
| INTERNAL_QUEUES | no | no | no | no | no |
| LINEOUTTRUNC | no | yes | no | no | no |
| MAKEBUF_BIF | no | yes | no | no | no |
| PRUNE_TRACE | no | yes | no | no | no |
| QUEUES_301 | no | yes | no | no | no |
| REGINA_BIFS | no | yes | no | no | no |
| SINGLE_LINE_COMMENTS | no | yes | no | no | no |
| STDOUT_FOR_STDERR | no | no | no | no | no |
| STRICT_ANSI | yes | no | no | no | no |
| STRICT_WHITE_SPACE_COMPARISONS | yes | no | no | no | no |
| TRACE_HTML | no | no | no | no | no |

The Stack

In this chapter, the stack and operations manipulating the stack are discussed. Since the stack is external to the REXX language, there are large differences between implementations with respect to the stack. These differences are attempted described in the latter part of this chapter.

Another goal of this chapter is to try to describe both the "real" standards and some of the most commonly used de facto standards related to stack operation. Where something is not a part of any defined standard, this is clearly labelled. Also, some liberties have been taken in order to create a coherent vocabulary on a field where very little standardization has taken place.

Background and history

In the various definitions of REXX, there are numerous references to the "stack" (often called the "external data queue", or just the "queue"). It is a structure capable of storing information, but it is not a part of the REXX language itself. Rather, it is a part of the external environment supporting a REXX implementation.

Originally, the references to the stack was introduced into REXX because of the strong binding between REXX and IBM mainframes in the early history of REXX [BMARKS]. Most (all?) of the operating systems for these machines support a stack, and many of their script programming idioms

involve the stack. Therefore, it was quite natural to introduce an interface to the stack into REXX, and consequently today many of the programming paradigms of REXX involve a stack.

Unfortunately, this introduced an element of incompatibility into REXX, as the stack is not in general supported for other operating systems. Consequently, REXX implementers often must implement a stack as well of the core REXX interpreter. Since no authoritative definition of the stack exists, considerable differences between various implementations. Ironically, although the stack was introduced to help communication between separate programs, the interpreter-specific implementations of stacks may actually be a hindrance against compatibility between different interpreters.

The stack may have "seemed like a good idea at the time", but in hindsight, it was probably a bad move, since it made REXX more dependent on the host operating system and its interfaces.

General functionality of the stack

This section describes the functionality generally available in implementations of stacks. The basic functionality described here will be complemented with information on specific implementations later. Unless explicitly labelled otherwise, this functionality is available in all standards treated in this documentation.

Basic functionality

Below is listed the general functionality of the stack, in order of decreasing compatibility. I.e. the functionality listed first is more likely to be a part of all implementations than the ones listed at the end of the list.

The stack is a data structure, which strings can either be inserted into or extracted from. The strings in the stack are stored in a linear order. Extraction and insertion works at a granularity of a complete string, i.e. it is not possible to insert or extract parts of string.

The stack has two ends: a top and a bottom. New strings can be inserted into the stack in both ends, but strings can only be extracted from the top of the stack.

There exists a way of counting the number of strings currently stored in the stack.

A stack is often compared with the pile of plates you often find in cantinas. It allows you to either add new plates at the top of the pile or take old plates from the top. When a plate is taken from the pile, it will be the most recently plate (that is still present) added to the pile. Stack operating in REXX works the same way, although it also allows "plates" to be added to the bottom of the pile.

There might be an implementation-specific limit on the length and number of strings stored in the stack. Ideally, the maximum length will be fairly large, at least 2**16, although some implementations are likely to enforce shorter limits. Similarly, there might be a limit on the number of strings that can be simultaneously stored in the stack. Ideally, there should be no such limit.

It is natural that there are limits imposed on the amount of memory occupied by the strings in the stack. Some implementations are likely to reserve a fixed (but perhaps configurable) amount of memory for this purpose while others can dynamically re-size the stack as long as enough memory is

Last update: 2024/09/04 06:58

available.

Some implementations might restrict the set of characters allowed in strings in the stack, although ideally, all characters should be allowed, even characters normally used for end-of-line or end-of-string.

This documentation use the term "string", while "line" is in common use elsewhere. The term is used because the strings in the stack are not inherently interpreted as lines (having an implied end-of-line), only as a string.

Note that the stack itself is not a part of REXX, only the parts which interface to the stack.

Example: Using the stack to transfer parameters

This is a common REXX idiom used in several situations for special parameter passing. The following code illustrates its use:

```
do i=1 to 10 /* for each parameter string */
    queue string.1 /* put the string on the stack */
end

call subrout 10 /* call the subroutine */
exit

subrout: procedure

/* the definition of the subroutine */
do j=1 to arg(1) /* for each parameter passed */
    parse pull line.j /* retrieve the parameter */
end
... /*do something with the parameters*/
```

In this example, ten parameter strings are transferred to the subroutine SUBROUT. The parameters are stored in the stack, and only the number of parameters are transferred as a "real" argument.

There are several advantages: first, one avoids problems related to exposing variable names. Since the data is stored on the stack, there is no need to refer to the variable names and bind the variables in the subroutine to variables in the caller routine. In [TRL1], indirect references to variables in PROCEDURE EXPOSE is illegal, and this method circumvent the problem.

Two other ways around this problem is to use INTERPRET for the PROCEDURE EXPOSE instruction in order to dynamically determine which variables to expose; or to use the VALUE() built-in function (with its two first parameters). The former is incompatible with TRL2, while the latter is incompatible with TRL1. Using the stack can solve the problem in a fashion compatible with both standards. Anyway, if the called routine is an external routine, then exposing does not work, so using the stack to transfer values may be the only solution.

Another advantage of this idiom; TRL only requires implementations to support 10 parameters for

subroutines. Although there are no reasons why an implementation should set a limit for the number of parameters a routine can get, you should use another mechanism than arguments when the number of strings is greater than 10. Using the stack fixes this.

LIFO and FIFO stack operations

As already mentioned, the stack is a linear list of strings. Obviously, this list has two ends. Strings can only be extracted from one end, while strings can be added to both ends.

If a set of new strings are added to the same end as they are later extracted from, the strings will be extracted in the reversed order with respect to the order in which they were added. This is called stacking "LIFO", which means "last-in-first-out", meaning that the last string stacked, will be the first string extracted, i.e. reversal of the order.

Similarly, when a set of strings are stacked in the end opposite to the end which they are later extracted from, they will be extracted in the same order in which they were stacked. This is referred to as "FIFO" stacking, meaning "first-in-first-out".

The FIFO method of stacking is also sometimes referred to as "queueing", while the LIFO method is sometimes referred to as "stacking" or "pushing".

Using multiple buffers in the stack

The concept of buffers and everything directly related to buffers lay without the domain of standard REXX. Thus, this section describes a de facto standard.

Note that Regina supports multiple buffers only in internal stacks.

Some implementations support "buffers", which are a means of focusing on a part of the stack. When creating a new buffer, the old contents of the stack is somewhat insulated from the effects of stack operations. When the buffer is removed, the state of the old buffer i restored, to some extent: Whenever a string is read from the stack, and the topmost buffer on the stack is empty, then that buffer will be destroyed. Consequently, if this situation has arisen, dropping buffers will not restore the state of the stack before the buffer was created.

The functionality of buffers, and their effect on other stack operations may differ considerably between implementations.

Whenever a queuing operations is performed (e.g. by the QUEUE instruction), then the new string is inserted into the bottom of the topmost buffer, not the bottom of the stack. This is the same if the stack has no buffers, but else, the outcome of the queuing operation can be very different.

With IBM mainframe operating systems like CMS, buffers can be inserted on the top of the stack. To perform buffer operations, operating system commands are used. It may be instructional to list the buffer operations of CMS:

[DESBUF]

Removes all strings and buffers from the stack, and leaves the stack clean and empty. It is often used instead of repeated calls to DROPBUF. It always returns the value zero.

[DROPBUF]

Last update: 2024/09/04 06:58

Removes zero or more buffers from the stack. It takes one parameter which can be omitted, and which must be an integer position if specified, and is the assigned number of the bottom-most buffer to be removed, i.e. that buffer and all buffers above it (and of course, all the strings in these buffers) are to be removed. If the parameter is not specified, only the topmost buffer is removed. The return valued is always zero, unless an error occurred.

[MAKEBUF]

Makes a new buffer on the stack, starting at the current top of the stack. The return code (as stored in the special variable RC) is the number of buffers currently on the stack after the new buffer has been added. Obviously, this will be a positive integer. This program takes no parameters.

One might regard a buffer as a sort of bookmark, which is inserted into the stack, so that a subsequent DROPBUF command can remove the stack down to a particular such bookmark.

When such a mark is located on the top of the stack, and a PULL instruction is executed, the buffer mark is implicitly destroyed when the PULL instruction reads the string below the buffer mark.

This is to say that a buffer can be destroyed by either a DESBUF command, a DROPBUF command, or a read from the stack (by either the PULL or PARSE PULL instructions).

The zeroth buffer

Normally, data pushed on the stack is added to the top of the stack. When a stack contains only one buffer, the strings in that buffer are the strings stored above that buffer-mark. The strings below it are not part of the first buffer; instead, they are said to belong to the zeroth buffer.

Thus, all strings from the bottom of the stack, up till the first buffer mark (or the top of the stack if no buffers exist) is said to be the strings in the zeroth buffer. However, note that the zeroth buffer is only defined implicitly. Thus, it can not really be removed by calling DROP; only the strings in the zeroth buffer are removed. Afterwards, the zeroth buffer will still contain all strings at the bottom of the stack, up till the first buffer mark (if existing).

Example: Process all strings in the stack

This is a common REXX idiom, where a loop iterates over all the strings currently in the stack, but otherwise leave the stack untouched. Supposing the routine PROCESS() exists, and do to processing with its parameter and return the processed string:

```
do i=1 to 5 /* just to fill the stack */
   push 'line #' i
end

do queued() /* foreach line in the stack */
   parse pull line /* fetch the line */
   queue process(line) /* put back the processed line */
end
```

Here, it is important to use QUEUE to put the strings back into the stack, not PUSH, else the loop will

iterate the correct number of times, but only operate on the same data string. It is also important that the stack does not contain any buffers. Since QUEUE will insert into the bottom of the topmost buffer, the loop would iterate the correct number of times, but only on a part of the stack. Thus, the topmost part of the strings in the stack would be processed multiple times.

Example: How to empty the stack

The following short example shows how you can most easily empty the stack:

```
do i=1 to 5 /* Just to fill the stack */
   push 'line #' i
end

do queued() /* For each line in the stack */
   pull /* Remove the line from the stack */
end
```

This is trivially simple, but there are several interesting and subtle notes to make about this example. First, if the number of strings in the stack is likely to change, due to some external process, then the DO clause should perhaps better be written as:

```
do i=1 to 5 /* Just to file the stack */
   push 'line #' i
end

do while queued()>0 /* While the stack is not empty */
   pull /* Remove a line from the stack */
end
```

This will in general mean more work for the interpreter, as it is now required to check the number of strings in the stack for each iteration, while for the previous code fragment, the number of strings is only checked once. Another point is that this might not remove all buffers from the stack. Suppose the zeroth buffer is empty, i.e. there exists an buffer which was put on the stack when the stack was empty. This buffer is removed in any of the following situations: calling DESBUF, calling DROPBUF (sometimes), or reading a string below the buffer mark. Since there are no strings below the buffer mark, pulling a string from the stack would make the interpreter read from the keyboard, and hang the interpreter.

Thus, the only "safe" way to remove the string and buffers from the stack, without side effects, is to call DESBUF or DROPBUF. On the other hand, if you only want to make sure that there are no strings in the buffer, the method described here is more suitable, since it is far more compatible (although possibly not so efficient). But anyway, buffers are not a compatible construct, so it does not matter so much.

Creating new stacks

The description of multiple stack operations in this section, is not part of standard REXX, nor is it implemented in Regina. Thus, this section describes a de facto standard and you may find that few implementations support these operations.

Last update: 2024/09/04 06:58

Just as the operations described above let the REXX programmer use multiple buffers within one stack, there exists another set of operations which let the programmer create multiple stacks. There is really nothing fancy about this, except that a command will swap the stack the interpreter correctly uses with another stack.

To the interpreter this is really equivalent to a situation where a command empties the current stack, and sets up a new stack. When one stack is empty, and the REXX program tries to read from the stack, the request will not "overflow" to the previous stack (as requests to an empty buffer "overflows" to the previous buffer). Thus, the use of multiple stacks has even less direct impact on REXX interpreters than multiple buffers.

Here, it is instructive to list the commands operating multiple stacks that exists. This list has been taken from the MVS environment, according to [REXXSAA].

[DELSTACK]

Is used to remove the most currently stack, and make the most recent of the saved stacks the current stack. When there are no saved stacks, the current stack is emptied.

[NEWSTACK]

Creates a new stack, which becomes the current stack. The old current stack is put on the top of the list of saved stacks, and can be retrieved as the current stack by a subsequent DELSTACK.

[QBUF]

Counts the number of buffers in the current stack, and returns that number as the return value. A REXX program starting this command can retrieve this value as the special variable RC.

[QELEM]

Counts the number of strings (i.e. elements) in the current stack, and returns that value as the return value of the command. This value can be retrieved in REXX as the special variable RC. This operation is equivalent to the QUEUED() built-in function in REXX; it has been probably included for the benefit of other script languages that have less functionality than REXX.

[QSTACK]

Counts the number of stacks (including the current stack) and returns the value as the return value from the command. This number can be retrieved in REXX as the special variable RC.

One can regard multiple buffers and stacks as two ways of insulating the stack; where multiple stacks are a deeper and more insulating method than buffers. Note that each stack can contain multiple buffers, while a buffer can not contain any stacks. The term "hard buffers" has been used about multiple stacks, as opposed to normal buffers, which are sometimes called "soft buffers".

Also note that neither multiple stacks nor buffers are part of standard REXX, so you might come across implementations that support only multiple stacks, only buffers, or even none of them.

Example: Counting the number of buffers

In order to count the number of buffers on the stack, the following method can be used (Regina syntax has been used for buffer handling). This method is equivalent to the QBUF command described

above.

```
buffers = makebuf() - 1
call dropbuf
```

This will store the number of buffers in the stack in the variable buffers. However, just as for the other examples using buffers, this example also suffers from the fact that buffer handling is fairly non-standard. Thus, you will have to adapt the code to whatever system you want to use.

The interface between REXX and the stack

As defined in TRL, the interface to the stack consists of the PARSE PULL, PULL, PUSH, and QUEUE instructions; and the QUEUED() built-in function.

There exists a binary interface to the stack in SAA, see the chapter on the SAA API interface. This interface consists of the RXMSQ exit handler and the QUENAME value of the RXSHV_PRIV request of the RexxVariablePool() function of the variable pool interface.

Strategies for implementing stacks

As mentioned, stacks are rarely a part of the operating system. Therefore, under most operating systems, REXX interpreters have to implement their own stacks. There are several strategies for doing this, some which are listed below.

[In the operating system.]

This is of course "the right way" to do it. However, it requires that the definition of the operating system is such that stacks are supported. Currently, only IBM mainframe-based systems support stack, together with a few other systems that have included stacks as a consequence of making REXX a main scripting language (Amiga and OS/2 come to mind).

[As a device driver.]

This is really just a variation of making the stack a part of the operating system. However, in some systems, drivers can be added very easily to the system. Drivers are often filesystem-based, in which case driver-based stack operations must operate on a file or pseudo-file. But for some systems, adding a driver requires much more profound changes, reconfiguration, and often system privileges. In all cases, drivers are likely to be very system specific.

[As a daemon.]

A "daemon" is background process that does some housekeeping service, e.g. handling mail from remote systems. Implementing a stack as a daemon is only slightly simpler than using a driver, but the main idea is the same for both approaches.

[In the interpreter.]

Using this approach, the stack is built into the interpreter as a sort of extension. This is often the

Last update: 2024/09/04 06:58

simplest way, since it require very little coordination with other programs during runtime. The main problem is that the stack becomes private to the interpreter, so two interpreters can not use the same stack; not even if they are two invocations of the same interpreter.

These items are listed in the order of how closely they are coupled to the operating system: the first items are very closely, while the last items are loosely coupled. The more closely coupled the implementation of a stack is coupled to the operating system, the better is the chance that several interpreters on the same system can communicate in a compatible way, using the stack.

There is room for several hybrid solutions, based on the four fundamental approaches. For instance, a built-in stack can also act as a daemon.

Regina supports the stack as both a daemon and internal to the interpreter.

Example: Commands takes input from the stack

In the example above, the routine that is called takes its arguments from the stack. Similarly, commands to an external environment can get their arguments in the same way. Here is an example of how to do it:

```
queue 'anonymous' /* the username */
queue 'user@node' /* the password */
queue 'dir' /* first command */
queue 'exit' /* second command */
address command 'FTP flipper.pvv.unit.no'
```

Although this is very convenient in some situations, there is also considerable disadvantages with this method: There is no real interactive communication between the interpreter and the command;

i.e. all input meant for the command must be set up before the command itself is invoked.

Consequently, if one of the input lines to the command provokes an error, there is very little error

handling facility. Commonly, such an error might start a cascade of errors, as the remaining input lines are likely to be invalid, or even be interpreted in a context different from what they were intended.

As with all commands involving the stack, it is important to push or queue the correct order.

Using this technique, a program can "fool" a command to do almost anything, by storing the correct input on the stack. However, there is a big disadvantage: Since the stack is implementation-dependent, it is not certain that a command will take its input from the stack. For some systems, this is the default, while for other systems, this is only possible through some explicit action. Some systems might not even allow commands to take their input from the stack at all.

Example: "Execing" commands

Many script programming languages can only execute commands while still running, or at most start a new command immediately after the termination (like the exec() system call in Unix). However, the stack can be used on some systems to set up the system to execute one or more commands after the current script terminates. Here is an example:

```
push 'ls' /* finally execute 'ls' */
```

```
push 'who' /* then execute 'who' */
push 'pwd' /* first execute 'pwd' */
exit 0
```

Supposing that the system reads its commands from the stack if the stack is not empty, then this script will terminate after having set up the stack so that the three commands pwd, who and Is will be run in that sequence. Note the order, if QUEUE had been used, the order would be the opposite, which is perhaps more intuitive (assuming the topmost buffer is empty).

As with the example above, this too is only relevant for some systems, thus is not very compatible, and you should be careful when using it. It also suffers from the lack of interactivity, error handling, and the importance of the order in which the strings are pushed or queued. For all practical reasons, this is just a special case.

Using the stack to "leave behind" command names and input only works for systems where command interpreters and commands reads their input from the stack. This is in general true for IBM mainframe systems, but very few other systems.

Implementations of the stack in Regina

In Regina, the stack is implemented as both an integral, private part of the interpreter and as a crossplatform external stack able to be used by multiple clients on multiple machines. Internal stacks provide the obvious advantage of speed at the expense of data sharing. External stacks are considerably slower, but do enable data sharing between instances of Regina and/or other programs.

Regina supports the standard TRL (and ANSI) REXX stack interface functionality, like PARSE PULL, PULL, QUEUE, PUSH, the QUEUED() built-in function, and in future versions, support the SAA API stack interface. These commands and functions operate on both the internal and external stacks.

Implementation of the internal stack in Regina 2.2 and above

Whenever the REXX programmer wants to execute a command and let that command either flush the output to the internal stack, or read its input from the internal stack, this has to be arranged by the interpreter itself. In Regina this is normally done by pre pending or appending certain terms to the command to be executed.

Consider the following command clauses for Regina:

```
'ls >LIF0'
'who >FIF0'
'LIF0> wc'
'LIF0> sort >FIF0'
```

For all these commands, the "piping" terms are stripped off the command string before the command is sent to the command interpreter of the operating system. Thus, the command interpreter only sees the commands Is, who, wc, and sort. The terms stripped off, are used as indicators of how the input and output is to be coupled with the stack. The use of input/output redirection as above is only available with the internal stack.

Note that it is important not to confuse the redirection of output to the stack and input from the stack in Regina with the redirection of the Unix shells. The two can be mixed in command lines, but are still two different concepts.

The first command will execute the Is command, and redirect the output from it to the stack in a LIFO fashion. The second executes the command who and redirects the output to the stack to, but in a FIFO fashion. The third command executes the wc, but lets the standard input of that command come from the stack. Actually, it is irrelevant whether FIFO> or LIFO> is used for input; the strings are read from the top of the stack in both cases. The fourth command is a plain ps command without any redirection to or from the stack. The last command executes the sort program and lets it read its input from the stack, and redirect the output to the stack.

Regina allows a command to take both an input and an output "redirection" to a stack, as showed in the last example above. However, it also guarantees that the output is not available in the stack before the command has terminated. The output from the command is stored in a temporary stack, and flushed to the ordinary stack after the command is terminated. Thus, the command will not start to read its own output.

Note that this temporary buffering of command output is the default behavior, which might be set up to something different at your site.

In addition, you can change it through the OPTIONS instruction, by using either FLUSHSTACK or BUFFERSTACK as "parameters".

Note the difference between Regina's redirection and Unix redirection. In Regina, only the term LIFO> (when first in the command string), and the terms >LIFO and >FIFO (when last in the command string), will be interpreted as redirection directives. These terms will be stripped off the command string. All other redirection directives will be left untouched. If you should happen to need to redirect output from a Unix command to the file FIFO or LIFO, then you can append a space at the end or specify the file as ./FIFO of ./LIFO. That will make Regina ignore the redirection term.

Note that this particular form of redirection of command input and output will most probably disappear in future versions of Regina, where it will probably be replaced by an extended ADDRESS instruction.

In addition to the ANSI standard, there are a few extra built-in functions, which are supposed to provide compatibility with other REXX implementations, principally CMS REXX. These are BUFTYPE, DESBUF, DROPBUF and MAKEBUF. See the descriptions of these function in the built-in functions section above.

Implementation of the external stack in Regina 2.2 and above

The implementation of the external stack follows the model used by OS/2 REXX, but is implemented as an operating system daemon. This daemon is rxstack.

rxstack

Under most operating systems, rxstack is started from the operating system's startup process and terminates when the machine is shutdown. Under Windows 2000 and above, it runs as a Service.

Communication between rxstack and Regina is done via TCP/IP sockets. Using sockets as the IPC mechanism on a local machine is somewhat slow compared to other mechanisms such as shared memory or named pipes. It does however enable operation between machines on different operating systems to function seamlessly.

The full syntax of the rxstack command is:

rxstack [switch]

switch is one of the following:

- -h, -help display help message
- -D, -debug show debugging information
- -d, -daemon run rxstack as a daemon Unix only
- -k, -kill kills (stops) rxstack subject to being a valid killer see Security of External Queues
- -p, -port the TCP port on which rxstack runs

Breakage Alert!! - Start

-w, -world allow access to rxstack from anywhere. Since v3.8, rxstack by default only allows access from localhost

Breakage Alert!! - End

the following switches are applicable to Windows 2000 and above

- -install installs the NT Service; REXX Stack Windows 2000 and above only
- -start starts the NT Service; REXX Stack Windows 2000 and above only
- -stop stops the NT Service; REXX Stack Windows 2000 and above only
- -remove stops and removes the NT Service; REXX -Stack Windows 2000 and above only
- -d runs rxstack in a command prompt which then allows non-service related switches Windows 2000 and above only

To stop rxstack, the process can be killed with a SIGINT or SIGTERM or by running rxstack with the -k or -kill switch.

rxqueue

To allow non-REXX program to interface to the rxstack daemon, a companion program; rxqueue, is provided. rxqueue communicates with non-REXX programs via its stdin and stdout.

Consider the following equivalents for Regina's internal and external stack

'ls >LIF0'

```
'ls | rxqueue /lifo'
'who >FIFO'
'who | rxqueue /fifo'
'LIFO> wc'
rxqueue /pull | wc'
'LIFO> sort >FIFO'
rxqueue /pull | sort | rxqueue /fifo'
```

The full syntax of the rxqueue command is:

```
rxqueue [switch] [queue] [action]
```

switch is a Regina extension and is one of the following:

- -h, -help display help message
- -D, -debug show debugging information
- -t, -text "string" queue the supplied string rather than from stdin. Only valid for /fifo or /lifo actions

queue is a Regina external queue name – see Queue Names for structure. If no queue is specified, rxqueue uses the queue name; SESSION

action is one of the following - as per OS/2 REXX

/fifo gueue lines from stdin LIFO onto the gueue

/lifo gueue lines from stdin FIFO onto the gueue

/clear remove all lines from the queue the following switches are Regina extensions

/delete delete the specified queue

/queued return the number of lines on the queue

/pull pull all lines from the queue and display on stdout

/list displays list of queues held by rxstack

rxqueue Built-in Function

REXX programs communicate with rxstack via the normal queueing mechanisms of QUEUE, PUSH, PULL and QUEUED(). These commands operate on the current queue and have no mechanism for changing the queue to use. This is whereRXQUEUE() is used. Its primary purpose is to control the queue that the remainder of the REXX program operates on.

Queue Names

To enable the use of the REXX stack as a cross-platform, multi-machine IPC, the naming conventions adopted by OS/2 REXX has been modified. As OS/2 REXX queues are local to a single machine, queue

names have no structure. To enable identification of queues on different machines, some structure must be built into external queue names on Regina. An external queue name on Regina has the following format:

[queue][@machine[:port]]

The components of the queue name are:

queue the name of the queue. The only criteria for the name is that it contains none of the following characters: @, . or :. The queue component can be blank, when specifying the default queue on a specified machine.

machine the machine that hosts the specified queue. This can either be a standard IPv4 IP address or a machine name that can be resolved to a standard IPv4 IP address. The machine name is optional, and defaults to 127.0.0.1

port The port number that rxstack on machine is listening to. The default port number for rxstack is 5757.

When referring to queues on the local machine, the machine and port components need not be specified. The behaviour of the external stack is then the same as for OS/2 REXX, with the exception that the queues on the local machine can still be manipulated by Regina on another machine.

Some examples may make this clearer. TBD

Security of External Queues

(Not implemented yet)

A daemon process like rxstack, waiting on a TCP/IP socket for anyone to connect to and use is open to abuse. To reduce the openness of rxstack, it uses a security mechanism much like the Unix hosts.allow and hosts.deny files is used to control access to rxstack.

Environment Variables

RXQUEUE RXSTACK

Interfacing REXX to other programs

This chapter describes an interface between a REXX interpreter and another program, typically written in C or another high level, compiled language. It is intended for application programmers who are implementing REXX support in their programs. It describes the interface known as the REXX SAA API.

Last update: 2024/09/04 06:58

Overview of functions in SAA

The functionality of the interface is divided into some main areas:

Subcommand handlers

which trap and handle a command to an external environment.

External function handlers

extend the REXX language with external functions

Interpreting

REXX scripts, either from a disk file, or from memory.

Variable interface

which makes it possible to access the variables in the interpreter, and allows operations like setting, fetching and dropping variables.

System exits

which are used to hook into certain key points in the interpreter while it executes a script.

External Queue interface

which allows access to Regina's external queuing mechanism.

Macrospace functions

which are used to load and save external macros into Regina's macrospace for faster execution. These are not implemented in Regina yet.

Memory Allocation functions

which provide for platform-independent memory allocating/deallocation functions.

Callback functions

which are used to allow the API program to execute a procedure within the running script.

In the following sections each of these areas are described in detail, and a number of brief but complete examples are given at the end of the chapter.

The description is of a highly technical nature, since it is assumed that the reader will be an application programmer seeking information about the interface. Therefore, much of the content is given as prototypes and C style datatype definitions. Although this format is cryptic for non-C programmers, it will convey exact, compact, and complete information to the intended readers.

Also, the problems with ambiguity and incompleteness that often accompany a descriptive prose text are avoided.

Include Files and Libraries

All the C code that uses the REXX application interface, must include a special header file that contains the necessary definitions. This file is called rexxsaa.h. Where you will find this file, will depend on you system and which compiler you use.

Also, the interface part between the application and the REXX interpreter may be implemented as a library, which you link with the application using the functions described in this chapter. The name of this library, and its location might differ from system to system. Under Unix, this library is implemented as a static (libregina.a) or dynamic library (libregina.[so|sl]). Under other platforms the Regina library is also implemented as a static or dynamic library.

Preprocessor Symbols

Including a header file ought to be enough; unfortunately, that is not so. Each of the domains of functionality listed above are defined in separate sections' in the rexxsaa.h header file. In order for these to be made available, certain preprocessor symbols have to be set. For instance, you have to include the following definition:

#define INCL RXSHV

in order to make available the definitions and datatypes concerning the variable pool interface. The various definitions that can be set are:

INCL RXSUBCOM

Must be defined in order to get the prototypes, datatypes and symbols needed for the subcommand interface of the API.

INCL RXFUNC

Must be defined in order to get the prototypes, datatypes and symbols needed for the external function interface of the API.

INCL_RXSYSEXIT

Must be defined in order to get the prototypes, datatypes, and symbols needed for the system exit functions

INCL RXSHV

Must be set in order to get the prototypes, symbols and datatype definitions necessary to use the REXX variable pool.

INCL RXQUEUE

Must be set in order to get the prototypes, symbols and datatype definitions necessary to use the REXX external queues.

INCL RXMACRO

Must be set in order to get the prototypes, symbols and datatype definitions necessary to use the REXX macrospace interface of the API.

Data structures and data types

In this section, some data structures and datatypes relevant to the application interface to REXX are defined and described. The datatypes defined are:

RXSTRING

Holds a REXX string.

RXSYSEXIT

Holds a definition of a system exit handler. Used when starting a REXX script with RexxStart(), and when defining the system exit handlers.

The datatypes used in the SAA API are defined in rexxsaa.h. They are:

```
typedef char CHAR;
typedef short SHORT;
typedef long LONG;
typedef char *PSZ ;
typedef CHAR *PCHAR ;
typedef SHORT *PSHORT ;
typedef LONG *PLONG ;
typedef unsigned char UCHAR;
typedef unsigned short USHORT;
typedef unsigned long ULONG;
typedef USHORT *PUSHORT ;
typedef char *PCH ;
typedef unsigned char *PUCHAR ;
typedef void VOID;
typedef void *PV0ID;
typedef ULONG APIRET;
typedef APIRET (APIENTRY *PFN)();
```

One other item needs mentioning; APIENTRY. This value is used to specify the linkage type on OS/2 and Win32 platforms. It is assumed that this value #defined by inclusion of compiler-specific header files in rexxsaa.h. Under Unix, this is #defined to nothing.

The RXSTRING structured

The SAA API interface uses REXX string which are stored in the structure RXSTRING. There is also a datatype PRXSTRING, which is a pointer to RXSTRING. Their definitions are:

```
typedef struct {
  unsigned char *strptr ; /* Pointer to string contents */
  unsigned long strlength ; /* Length of string */
```

```
} RXSTRING ;
typedef RXSTRING *PRXSTRING ;
```

The strptr field is a pointer to an array of characters making up the contents of the REXX string', while strlength holds the number of characters in that array.

Unfortunately, there are some inconsistencies in naming of various special kinds of strings. In REXX (TRL), a null string is a string that has zero length. On the other hand, the SAA API operates with two kinds of special strings: null strings and zero length strings. The latter is a string with zero length (equals null strings in REXX), while the former is a sort of undefined or empty string, which denotes a string without a value. The null strings of SAA API are used to denote unspecified values (e.g. a parameter left out in a subroutine call). In this chapter, when the terms null strings and zero length strings are italicized, they refer to the SAA API style meaning.

A number of macros are defined, which simplifies operations on RXSTRINGs for the programmer. In the list below, all parameters called x are of type RXSTRING.

MAKERXSTRING(x,content,length)]

The parameter content must be a pointer to char, while length is integer. The x parameter will be set to the contents and length supplied. The only operations are assignments; no new space is allocated and the contents of the string is not copied.

RXNULLSTRING(x)

Returns true only if x is a null string.

i.e. x.strptr is NULL.

RXSTRLEN(x)

Returns the length of the string x as an unsigned long. Zero is returned both when x is a null string or a zero length string.

RXSTRPTR(x)]

Returns a pointer to the first character in the string x, or NULL if x is a null string. If x is a zero length string, and non-NULL pointer is returned.

RXVALIDSTRING(x)]

Returns true only if x is neither a null string nor a zero length string

i.e. x must have non-empty contents.

RXZEROLENSTRING(x)]

Returns true only if x is a zero length string.

i.e. x.strptr is non-NULL, and x.strlength is zero.

These definitions are most likely to be defined as preprocessor macros, so you should never call them with parameters having any side effects. Also note that at least MAKERXSTRING() is likely to be implemented as two statements, and might not work properly if following

e.g. an if statement. Check the actual definitions in the rexxsaa.h header file before using them in a fancy context.

One definition of these might be (don't rely on this to be the case with your implementation):

```
#define MAKERXSTRING(x,c,l) ((x).strptr=(c),(x).strlength=(l))
#define RXNULLSTRING(x) (!(x).strptr)
#define RXSTRLEN(x) ((x).strptr ? (x).strlength : OUL)
#define RXSTRPTR(x) ((x).strptr)
#define RXVALIDSTRING(x) ((x).strptr && (x).strlength)
#define RXZEROLENSTRING(x) ((x).strptr && !(x).strlength)
```

Note that these definitions of strings differ from the normal definition in C programs; where a string is an array of characters, and its length is implicitly given by a terminating ASCII NUL character. In the RXSTRING definition, a string can contain any character, including an ASCII NUL, and the length is explicitly given.

The RXSYSEXIT structured

This structure is used for defining which system exit handlers are to handle which system exits. The two relevant datatypes are defined as:

```
typedef struct {
  unsigned char *sysexit_name ;
  short sysexit_code ;
} RXSYSEXIT ;
typedef RXSYSEXIT *PRXSYSEXIT ;
```

In this structure, sysexit_name is a pointer to the ASCII NUL terminated string containing the name of a previously registered (and currently active) system exit handler. This registration is done by the RexxRegisterExitExe() or RexxRegisterExitDII() functions. The EnvName argument to these function calls match sysexit_name.

The sysexit code field is main function code of a system exit.

The system exits are divided into main functions and sub-functions. An exit is defined to handle a main function, and must thus handle all the sub-functions for that main function. All the functions and sub-functions are listed in the description of the EXIT structure.

The Subcommand Handler Interface

This sections describes the subcommand handler interface, which enables the application to trap commands in a REXX script being executed and handle these commands itself.

What is a Subcommand Handler

A subcommand handler is a piece of code that is called to handle a command to an external

environment in REXX. It must be either a subroutine in the application that started the interpreter, or a subroutine in a dynamic link library. In any case, when the interpreter needs to execute a command to an external environment, it will call the subcommand handler, passing the command as a parameter.

Typically, an application will set up a subcommand handler before starting a REXX script. That way, it can trap and handle any command being executed during the course of the script.

Each subcommand handler handles one environment, which is referred to by a name. It seems to be undefined whether upper and lower case letters differ in the environment name, so you should assume they differ. Also, there might be an upper limit for the length of an environment name, and some letters may be illegal as part of an environment name.

Regina allows any letter in the environment name, except ASCII NUL; and sets no upper limit for the length of an environment name. However, for compatibility reasons, you should avoid uncommon letters and keep the length of the name fairly short.

The prototype of a subcommand handler function is:

```
APIRET APIENTRY handler( PRXSTRING command, PUSHORT flags, PRXSTRING returnstring);
```

After registration, this function is called whenever the application is to handle a subcommand for a given environment. The value of the parameters are:

[command]

The command string that is to be executed. This is the resulting string after the command expression has been evaluated in the REXX interpreter. It can not be empty, although it can be a zero-length-string.

[flags]

Points to an unsigned short which is to receive the status of the completion of the handler. This can be one of the following: RXSUBCOM_OK, RXSUBCOM_ERROR, or RXSUBCOM_FAILURE. The contents will be used to determine whether to raise any condition at return of the subcommand. Do not confuse it with the return value.

[returnstring]

Points to a RXSTRING which is to receive the return value from the subcommand. Passing the return value as a string makes it possible to return non-numeric return codes. As a special case, you might set returnstring.strptr to NULL, instead of specifying a return string of the ASCII representation of zero.

Note that it is not possible to return nothing in a subcommand, since this is interpreted as zero. Nor is it possible to return a numeric return code as such; you must convert it to ASCII representation before you return.

The returnstring string will provide a 256 byte array which the programmer might use if the return data is not longer that that. If that space is not sufficient, the handler can provide another area itself. In that case, the handler should not de-allocate the default area, and the new area should be allocated in a standard fashion.

The RexxRegisterSubcomExe() function

Last update: 2024/09/04 06:58

This function is used to register a subcommand handler with the interface. The subcommand handler must be a procedure located within the code of the application. After registration, the REXX interpreter can execute subcommands by calling the subcommand handler with parameters describing the subcommand.

The prototype for RexxRegisterSubcomExe() is:

APIRET APIENTRY RexxRegisterSubcomExe(PSZ EnvName, PFN EntryPoint, PUCHAR UserArea);

All the parameters are input, and their significance are:

[EnvName]

Points to an ASCII NUL terminated character string which defines the name of the environment to be registered. This is the same name as the REXX interpreter uses with the ADDRESS clause in order to select an external environment.

[EntryPoint]

Points to the entrypoint of the subcommand handler routine for the environment to be registered. See the section on Subcommand Handlers for more information.

There is an upper limit for the length of this name. [UserArea]

Pointer to an 8 byte area of information that is to be associated with this environment. This pointer can be NULL if no such area is necessary.

The areas pointed to by EnvName and UserArea are copied to a private area in the interface, so the programmer may de-allocate or reuse the area used for these parameters after the call has returned.

RexxRegisterSubcomExe() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXSUBCOM values:

[RXSUBCOM OK]

The subcommand handler was successfully registered.

[RXSUBCOM DUP]

The subcommand handler was successfully registered. There already existed another subcommand handler which was registered with RexxRegisterSubcomExe(), but this will be shadowed by the newly registered handler.

[RXSUBCOM NOTREG]

Due to some error, the handler was not registered. Probably because a handler for EnvName was already defined at a previous call to RexxRegisterSubcomExe().

[RXSUBCOM NOEMEM]

The handler was not registered, due to lack of memory.

[RXSUBCOM BADTYPE]

Indicates that the handler was not registered, due to one or more of the parameters having invalid values. Regina addition.

The RexxRegisterSubcomDII() function

This function is used to set up a routine that is located in a module in a dynamic link library, as a subcommand handler. After registration, the REXX interpreter can execute subcommands by calling the subcommand handler with parameters describing the subcommand.

Some operating systems don't have dynamic linking, and thus cannot make use of this facility. The prototype of this function is:

APIRET APIENTRY RexxRegisterSubcomDll(PSZ EnvName, PSZ ModuleName, PFN EntryPoint, PUCHAR UserArea, ULONG DropAuth);

All the parameters are input, and their significance are:

[EnvName]

Points to an ASCII NUL terminated character string which defines the name of the environment to be registered. This is the same name as the REXX interpreter uses with the ADDRESS clause in order to select an external environment.

[ModuleName]

Points to an ASCII NUL terminated character string which defines the name of the dynamic or shared library in which the EntryPoint to the subcommand exists.

[EntryPoint]

Points to the entrypoint of the subcommand handler routine for the environment to be registered. See the section on Subcommand Handlers for more information.

There is an upper limit for the length of this name.

[UserArea]

Pointer to an 8 byte area of information that is to be associated with this environment. This pointer can be NULL if no such area is necessary.

[DropAuth]

Is either RXSUBCOM_DROPABLE or RXSUBCOM_NONDROP. This argument is ignored by Regina as subcommands only exists within the current process.

The areas pointed to by EnvName, ModuleName and UserArea are copied to a private area in the interface, so the programmer may de-allocate or reuse the area used for these parameters after the call has returned.

Last update: 2024/09/04 06:58

RexxRegisterSubcomDII() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXSUBCOM values:

[RXSUBCOM OK]

The subcommand handler was successfully registered.

[RXSUBCOM DUP]

The subcommand handler was successfully registered. There already existed another subcommand handler which was registered with RexxRegisterSubcomDII(), but this will be shadowed by the newly registered handler.

[RXSUBCOM NOTREG]

Due to some error, the handler was not registered. Probably because a handler for EnvName was already defined at a previous call to RexxRegisterSubcomDII().

[RXSUBCOM NOEMEM]

The handler was not registered, due to lack of memory.

[RXSUBCOM_BADTYPE]

Indicates that the handler was not registered, due to one or more of the parameters having invalid values. Regina addition.

The RexxDeregisterSubcom() function

This function is used to remove a particular environment from the list of registered environments. The prototype of the function is:

APIRET APIENTRY RexxDeregisterSubcom(PSZ EnvName, PSZ ModuleName) ;

Both parameters are input values:

[EnvName]

Pointer to ASCII NUL terminated string, which represents the name of the environment to be removed.

[ModuleName]

Also an ASCII NUL terminated string, which points to the name of the module containing the subcommand handler of the environment to be deleted.

The list of defined environments is searched, and if an environment matching the one named by the first parameter are found, it is deleted.

The returned value from RexxDeregisterSubcom() can be one of:

[RXSUBCOM OK]

The subcommand handler was successfully deleted.

[RXSUBCOM NOTREG]

The subcommand handler was not found.

[RXSUBCOM_BADTYPE]

One or more of the parameters had illegal values, and the operation was not carried through. Regina addition.

[RXSUBCOM_NOCANDROP]

Unable to deregister the subcommand handler. Regina addition.

Most systems that do have dynamic linking have no method for reclaiming the space used by dynamically linked routines. So, even if you were able to load a dll, there are no guarantees that you will be able to unload it.

The RexxQuerySubcom() function

This function retrieves information about a previously registered subcommand handler. The prototype of the function is:

APIRET APIENTRY RexxQuerySubcom(PSZ EnvName, PSZ ModuleName, PUSHORT Flag, PUCHAR UserArea);

The significance of the parameters are:

[EnvName]

Pointer to an ASCII NUL terminated character string, which names the subcommand handler about which information is to be returned.

[ModuleName]

Pointer to an ASCII NUL terminated character string, which names a dynamic link library. Only the named library will be searched for the subcommand handler named by EnvName. This parameter must be NULL if all subcommand handlers are to be searched.

[Flag]

Pointer to a short which is to receive the value RXSUBCOM_OK or RXSUBCOM_NOTREG. In fact, this is the same as the return value from the function.

[UserArea]

Pointer to an area of 8 bytes. The userarea of the subcommand handler is copied to the area pointed to by UserArea. This parameter might be NULL if the data of the userarea is not needed.

The returned value from RexxQuerySubcom() can be one of:

[RXSUBCOM OK]

Last update: 2024/09/04 06:58

The subcommand handler was found, and the required information has been returned in the Flag and UserAreavariables.

[RXSUBCOM_NOTREG]

The subcommand handler was not found. The Flag variable will also be set to this value, and the UserArea variable is not changed.

[RXSUBCOM_BADTYPE]

One or more of the parameters had illegal values, and the operation was not carried through. Regina addition.

The External Function Handler Interface

This sections describes the external function handler interface, which extends the language by enabling external functions to be written in a language other than REXX.

What is an External Function Handler

An external function handler is a piece of code, that is called to handle external functions and subroutine calls in REXX. It must be either a subroutine in the application that started the interpreter, or a subroutine in a dynamic link library. In any case, when the interpreter needs to execute a function registered as an external function, it will call the external function handler, passing the function name as a parameter.

All external functions written in a language other than REXX must be registered with the interpreter before starting a REXX script.

An external function handler can handle one or more functions. The handler can determine the function actually called by examining one of the parameters passed to the handler and act accordingly.

The prototype of an external function is:

```
APIRET APIENTRY handler( PSZ name, ULONG argc, PRXSTRING argv, PSZ queuename, PRXSTRING returnstring);
```

After a function is registered with this function defined as the handler, this function is called whenever the application calls the function. The value of the parameters are:

[name]

The function called.

[argc]

The number of parameters passed to the function.

[argv]

Argv will contain argc RXSTRINGs.

[queuename]

The name of the currently define data queue. [returnstring]

Points to a RXSTRING which is to receive the return value from the function. Passing the return value as a string makes it possible to return non-numeric return codes. As a special case, you might set returnstring.strptr to NULL, instead of specifying a return string of the ASCII representation of zero.

The returnstring string will provide a 256 byte array which the programmer might use if the return data is not longer that that. If that space is not sufficient, the handler can provide another area itself. In that case, the handler should not de-allocate the default area, and the new area should be allocated in a standard fashion. if the external function does not return a value, it should set returnstring to an empty RXSTRING. This will enable the interpreter to raise error 44; Function did not return data, if the external function is called as a function. If the external function is invoked via a CALL command, the interpreter drops the special variable RESULT.

The handler returns zero if the function completed successfully. When the handler returns a non-zero value, the interpreter will raise error 40; Invalid call to routine.

The RexxRegisterFunctionExe() function

This function is used to register an external function handler with the interface. The external function handler must be a procedure located within the code of the application. After registration, the REXX interpreter can execute external functions as if they were built-ins.

The prototype for RexxRegisterFunctionExe() is:

APIRET APIENTRY RexxRegisterFunctionExe(PSZ FuncName, PFN EntryPoint) ;

All the parameters are input, and their significance are:

[FuncName]

Points to an ASCII NUL terminated character string which defines the name of the external function to be registered. This is the same name as the REXX interpreter uses with a function call or via the CALL command.

[EntryPoint]

Points to the entrypoint of the external function handler routine for the function to be registered. See the section on External Function Handlers for more information.

The area pointed to by FuncName is copied to a private area in the interface, so the programmer may de-allocate or reuse the area used for this parameter after the call has returned.

The RexxRegisterFunctionExe() returns an unsigned long, which carries status information describing

the outcome of the operation. The status will be one of the RXFUNC values:

[RXFUNC OK]

The handler was successfully registered.

[RXFUNC_DEFINED]

The handler was successfully registered. There already existed another external function handler which was registered with RexxRegisterFunctionExe(), but this will be shadowed by the newly registered handler.

[RXFUNC ENTNOTFND]

The handler was not registered as the EntryPoint was not found.

[RXFUNC_NOMEM]

The handler was not registered, due to lack of memory.

The RexxRegisterFunctionDII() function

This function is used to set up an external function handler that is located in a module in a dynamic link library. Some operating systems don't have dynamic linking, and thus cannot make use of this facility. The prototype of this function is:

APIRET APIENTRY RexxRegisterFunctionDll(PSZ ExternalName, PSZ LibraryName, PSZ InternalName);

All the parameters are input, and their significance are:

[ExternalName]

Points to an ASCII NUL terminated character string which defines the name of the external function to be registered. This is the same name as the REXX interpreter uses with a function call or via the CALL command.

[LibraryName]

Points to an ASCII NUL terminated character string which defines the name of the dynamic library. This string may require a directory specification.

[InternalName]

Points to an ASCII NUL terminated character string which defines the name of the entrypoint within the dynamic library. On systems where the case of function names in dynamic libraries is relevant, this name must be specified in the same case as the function name within the dynamic library.

The areas pointed to by all parameters are copied to a private area in the interface, so the programmer may de-allocate or reuse the area used for these parameters after the call has returned.

The RexxRegisterFunctionDII() returns an unsigned long, which carries status information describing

the outcome of the operation. The status will be one of the RXFUNC values:

[RXFUNC_OK]

The handler was successfully registered.

[RXFUNC_DEFINED]

The handler was successfully registered. There already existed another external function handler which was registered with RexxRegisterFunctionDII(), but this will be shadowed by the newly registered handler.

[RXFUNC MODNOTFND]

The handler was not registered as the LibraryName was not found.

[RXFUNC ENTNOTFND]

The handler was not registered as the InternalName was not found.

[RXFUNC NOMEM]

The handler was not registered, due to lack of memory.

The RexxDeregisterFunction() function

This function is used to remove a particular external function handler from the list of registered external function handlers. The prototype of the function is:

APIRET APIENTRY RexxDeregisterFunction(PSZ FuncName) ;

The parameter is an input value:

[FuncName]

Points to an ASCII NUL terminated character string which defines the name of the external function to be registered. This is the same name as the REXX interpreter uses with a function call or via the CALL command.

The list of defined function handlers is searched, and if an environment matching the one named by the parameter are found, it is deleted. This call is used to de-register function handlers registered with either RexxRegisterFunctionExe() or RexxRegisterFunctionDII().

The returned value from RexxDeregisterFunction() can be one of:

[RXFUNC OK]

The handler was successfully deleted.

[RXFUNC NOTREG]

The handler was not found.

Most systems that do have dynamic linking have no method for reclaiming the space used by dynamically linked routines. So, even if you were able to load a dll, there are no guarantees that you will be able to unload it.

The RexxQueryFunction() function

This function retrieves the status of an external function handler. The prototype of the function is:

```
APIRET APIENTRY RexxQueryFunction( PSZ FuncName);
```

The significance of the parameters is:

[FuncName]

Points to an ASCII NUL terminated character string which defines the name of the external function to be registered. This is the same name as the REXX interpreter uses with a function call or via the CALL command.

The returned value from RexxQueryFunction() can be one of:

[RXFUNC OK]

The external function handler was found.

[RXFUNC NOTREG]

The handler was not found.

Executing REXX Code

This sections describes the RexxStart() function, which allows the application to startup the interpreter and make it interpret pieces of REXX code.

The RexxStart() function

This function is used to invoke the REXX interpreter in order to execute a piece of REXX code, which may be located on disk, as a pre-tokenized macro, or as ASCII source code in memory.

```
APIRET APIENTRY RexxStart(LONG ArgCount, PRXSTRING ArgList, PCSZ ProgramName, PRXSTRING Instore, PCSZ EnvName, LONG CallType, PRXSYSEXIT Exits, PSHORT ReturnCode, PRXSTRING Result);
```

Of these parameters, ReturnCode and Result are output-only, while Instore is both input and output. The rest of the parameters are input-only. The significance of the parameters are:

[ArgCount]

The number of parameter strings given to the procedure. This is the number of defined REXX-strings

pointed to by the ArgList parameter. The default maximum number of arguments that can be passed is 32, but this can be changed by the MAX ARGS TO REXXSTART macro in rexx.h.

[ArgList]

Pointer to an array of REXX-strings, constituting the parameters to this call to REXX. The size of this array is given by the parameter ArgCount. If ArgCount is greater than one, the first and last parameters are ArgList[0] and ArgList[ArgCount-1]. If ArgCount is 0, the value of ArgList is irrelevant.

If the strptr of one of the elements in the array pointed to by ArgList is NULL, that means that this parameter is empty (i.e. unspecified, as opposed to a string of zero size).

[ProgramName]

An ASCII NUL terminated string, specifying the name of the REXX script to be executed. The value of Instore will determine whether this value is interpreted as the name of a (on-disk) script, or a pretokenized macro. If it refers to a filename, the syntax of the contents of this parameter depends on the operating system.

[Instore]

Parameter used for storing tokenized REXX scripts. This parameter might either be NULL, else it will be a pointer to two RXSTRING structures, the first holding the ASCII version of a REXX program, the other holding the tokenized version of that program. See below for more information about how to use Instore.

[EnvName]

Pointer to ASCII NUL terminated string naming the environment which is to be the initial current environment when the script is started. If this parameter is set to NULL, the filetype is used as the initial environment name. What the filetype is, may depend on your operating system, but in general it is everything after the last period '.' in the filename.

[CallType]

A value describing whether the REXX interpreter is to be invoked in command, function or subroutine mode. Actually, this has little significance. The main difference is that in command mode, only one parameter string can be passed, and in function mode, a value must be returned. In addition, the mode chosen will affect the output of the PARSE SOURCE instruction in REXX.

[Exits]

Three symbolic values of integral type are defined, which can be used for this parameter: RXCOMMAND, RXFUNCTION and RXSUBROUTINE.

A value of RXRESTRICTED can be OR'ed with one of the above types to specify that Regina will run in restricted mode. This is particularly useful when Regina is used as an embedded interpreter in applications such as a database procedural language or a web-browser scripting language.

A pointer to an array of exit handlers to be used. If no exit handlers are to be defined, NULL may be specified. Each element in the array defines one exit handler, and the element immediately following the last definition must have a sysexit_code set to RXENDLST. Each element's sysexit_name must match the EnvName specified in a call to RexxRegisterExitExe() or RexxRegisterExitDll() called prior

Last update: 2024/09/04 06:58

to calling RexxStart().

[ReturnCode]

Pointer to a SHORT integer where the return code is stored, provided that the returned value is numeric, and within the range -(2**15) to 2**15-1. I don't know what happens to ReturnCode if either of these conditions is not satisfied. It probably becomes undefined, which means that it is totally useless since the program has to inspect the return string in order to determine whether ReturnCode is valid. Regina allows the value of this parameter to be NULL if the user is not interested in it.

[Result]

Points to a REXX string into which the result string is written. The caller may or may not let the strptr field be supplied. If supplied (i.e. it is non-NULL), that area will be used, else a new area will be allocated. If the supplied area is used, its size is supposed to be given by the strlength field. If the size if not sufficient, a new area will be allocated, by RexxAllocateMemory(), and the caller must see to that it is properly de-allocated using RexxFreeMemory().

Regina allows the value of this parameter to be NULL if the user is not interested in it.

Note that the ArgCount parameter need not be the same as the ARG() built-in function would return. Differences will occur if the last entries in ArgList are null strings.

The Instore parameter needs some special attention. It is used to directly or indirectly specify where to fetch the code to execute. The following algorithm is used to determine what to execute:

If Instore is NULL, then ProgramName names the filename of an on-disk REXX script which it to be read and executed.

Else, if Instore is not NULL, the script is somewhere in memory, and no reading from disk is performed. If both Instore[0].strptr and Instore[1].strptr are NULL, then the script to execute is a pre-loaded macro which must have been loaded with a call to either RexxAddMacro() or RexxLoadMacroSpace(); and ProgName is the name of the macro to execute.

Else, if Instore[1].strptr is non-NULL, then Instore[1] contains the pre-tokenized image of a REXX script, and it is used for the execution.

Else, if Instore[0].strptr is non-NULL, then Instore[0]} contains the ASCII image of a REXX script, just as if the script had been read directly from the disk (i.e. including linefeeds and such). This image is passed to the interpreter, which tokenizes it, and stores the tokenized script in the Instore[1] string, and then proceeds to execute that script. Upon return, the Instore[1] will be set, and can later be used to re-execute the script within the same process, without the overhead of tokenizing.

The user is responsible for de-allocating any storage used by Instore[1]. Note that after tokenizing, the source code in Instore[0] is strictly speaking not needed anymore. It will only be consulted if the user calls the SOURCELINE() built-in function. It is not an error to use SOURCELINE() if the source is not present, but nullstring and zero will be returned.

To tokenise a REXX script and save it for execution by a later execution by RexxStart() either in the currently running process or outside the current process, you need to call RexxStart() with the following arguments:

| Parameter | Value | Notes |
|-----------------------|-----------------------------|---|
| ArgCount | 1 | |
| ArgList.strlength | 3 | |
| ArgList.strptr | //T | |
| ProgramName | | Ignored |
| Instore[0].strptr | ASCII image of REXX script | |
| Instrore[0].strlength | Length of Instore[0].strptr | |
| Instrore[1].strptr | Ignored | This will be populated with the tokenised code. |
| Instore[1].strlength | Ignored | This will be set to the length of Instore[1].strptr |
| EnvName | SYSTEM | |
| CallType | RXCOMMAND | |
| Exits | NULL | |
| ReturnCode | Ignored | |
| Result.strptr | Ignored | |
| Result.strlength | Ignored | |

The valid return values from RexxStart() are:

[Negative]

indicates that a syntax error occurred during interpretation. In general, you can expect the error value to have the same absolute value as the REXX syntax error (but opposite signs, of course).

[Zero]

indicates that the interpreter finished executing the script without errors.

[Positive]

indicates probably that some problem occurred, that made it impossible to execute the script, e.g. a bad parameter value. However, I can't find any references in the documentation which states which values it is supposed to return.

During the course of an execution of RexxStart(), subcommand handlers and exit handlers might be called. These may call any function in the application interface, including another invocation of RexxStart().

Often, the application programmer is interested in providing support simplifying the specification of filenames, like an environment variable search path or a default file type. The REXX interface does support a default file type: .CMD, but the user may not set this to anything else. Therefore, it is generally up to the application programmer to handle search paths, and also default file types (unless .CMD is OK).

If the initial environment name (EvnName) is NULL, then the initial environment during interpretation will be set equal to the file type of the script to execute. If the script does not have a file type, it is probably set to some interpreter specific value.

Last update: 2024/09/04 06:58

Variable Pool Interface

This section describes the variable pool part of the application interface, which allows the application programmer to set, retrieve and drop variables in the REXX interpreter from the application program. It also allows access to other information.

The C preprocessor symbol INCL_RXSHV must be defined if the definitions for the variable pool interface are to be made available when rexxsaa.h is included.

Symbolic or Direct

First, let us define two terms, symbolic variable name and direct variable name, which are used in connection with the variable pool.

A symbolic variable name is the name of a variable, but it needs normalization and tail substitution before it names the real variable. The name foo.bar is a symbolic variable name, and it is transformed by normalization, to FOO.BAR, and then by tail substitution to FOO.42 (assuming that the current value of BAR is 42).

Normalization is the process of uppercasing all characters in the symbolic name; and tail substitution is the process of substituting each distinct simple symbol in the tail for its value.

On the other hand, a direct variable refers directly to the name of the variable. In a sense, it is a symbolic variable that has already been normalized and tail substituted. For instance, foo.bar is not a valid direct variable name, since lower case letters are not allowed in the variable stem. The direct variable FOO.42 is the same as the variable above. For simple variables, the only difference between direct and symbolic variable names is that lower case letters are allowed in symbolic names

Note that the two direct variable names FOO.bar and FOO.BAR refer to different variables, since upper and lower case letters differ in the tail. In fact, the tail of a compound direct variable may contain any character, including ASCII NUL. The stem part of a variable, and all simple variables can not contain any lower case letters.

As a remark, what would the direct variable FOO. refer to: the stem FOO. or the compound variable having stem FOO. and a nullstring as tail? Well, I suppose the former, since it is the more useful. Thus, the latter is inaccessible as a direct variable.

The SHVBLOCK structure

All requests to manipulate the REXX variable pool are controlled by a structure which is called SHVBLOCK, having the definition:

```
typedef struct shvnode {
   struct shvnode *shvnext ; /* ptr to next in blk in chain */
   RXSTRING shvname ; /* name of variable */
   RXSTRING shvvalue ; /* value of variable */
   ULONG shvnamelen ; /* length of shvname.strptr */
   ULONG shvvaluelen ; /* length of shvvalue.strptr */
```

```
UCHAR shvcode ; /* operation code */
UCHAR shvret ; /* return code */
} SHVBLOCK ;
typedef SHVBLOCK *PSHVBLOCK ;
```

The fields shvnext and shvcode are purely input, while shvret is purely output. The rest of the fields might be input or output, depending on the requested operation, and the value of the fields. The significance of each field is:

[shvnext]

One call to RexxVariablePool() may sequentially process many requests. The shvnext field links one request to the next in line. The last request must have set shvnext to NULL. The requests are handled individually and thus, calling RexxVariablePool() with several requests is equivalent to making one call to RexxVariablePool() for each request.

[shvname]

Contains the name of the variable to operate on, as a RXSTRING. This field is only relevant for some requests, and its use may differ.

[shvvalue]

Contains the value of the variable to operate on as a RXSTRING. Like shvname, this might not be relevant for all types of requests.

[shvnamelen]

The length of the array that shvname.strptr points to. This field holds the maximum possible number of characters in shvname.strptr. While shvname.strlength holds the number of characters that are actually in use (i.e. defined).

[shvvaluelen]

The length of the array that shvvalue.strptr points to. Relates to shvvalue, like shvnamelen relates to shvname.

[shvcode]

The code of operation; decides what type of request to perform. A list of all the available requests is given below.

[shvret]

A return code describing the outcome of the request. This code is a bit special. The lower seven bits are flags which are set depending on whether some condition is met or not. Values above 127 are not used in this field.

There is a difference between shvnamelen and shvname.strlength. The former is the total length of the array of characters pointed to by shvname.strptr (if set). While the latter is the number of these characters that are actually in use. When a SHVBLOCK is used to return data from RexxVariablePool(), and a pre-allocated string space has been supplied, both these will be used; shvname.strlength will be set to the length of the data returned, while shvnamelen is never changed, only read to find the

Last update: 2024/09/04 06:58

maximum number of characters that shyname can hold.

Even though shvnamelen is not really needed when shvname is used for input, it is wise to set it to its proper value (or at least set it to the same as shvname.strlength). The same applies for shvvalue and shvvaluelen.

The field shvcode can take one of the following symbolic values:

[RXSHV_DROPV]

The variable named by the direct variable name shvname is dropped (i.e. becomes undefined). The fields shvvalue and shvvaluelen do not matter.

[RXSHV EXIT]

This is used to set the return value for an external function or exit handler.

[RXSHV FETCH]

The value of the variable named by the direct variable name shvname is retrieved and stored in shvvalue. If shvvalue.strptr is NULL, the interpreter will allocate sufficient space to store the value (but it is the responsibility of the application programmer to release that space). Else, the value will be stored in the area allocated for shvvalue, and shvvaluelen is taken to be the maximum size of that area.

[RXSHV_NEXTV]

This code is used to retrieve the names and values of all variables at the current procedure level; i.e. excluding variables shadowed by PROCEDURE. The name and value of each variable are retrieved simultaneously into shvname and shvvalue, respectively.

Successive requests for RXSHV_NEXTV will traverse the interpreter's internal data structure for storing variables, and return a new pair of variable name and value for each request. Each variable that is visible in the current scope, is returned once and only once, but the order is non-deterministic.

When all available variables in the REXX interpreter have already been retrieved, subsequent RXSHV_NEXTV requests will set the flag RXSHV_LVAR in the shvret field. There are a few restrictions. The traversal will be reset whenever the interpreter resumes execution, so an incomplete traversal can not be continued in a later external function, exit handler, or subcommand handler. Also, any set, fetch or drop operation will reset the traversal. These restrictions have been added to ensure that the variable pool is static throughout one traversal.

[RXSHV_PRIV]

Retrieves some piece of information from the interpreter, other than a variable value, based on the value of the shvname field. The value is stored in shvvalue as for a normal fetch. A list of possible names is shown below.

[RXSHV SET]

The variable named by the direct variable name shvname is set to the value given by shvvalue.

[RXSHV SYFET]

Like RXSHV FETCH, except that shvname is a symbolic variable name.

[RXSHV SYDRO]

Like RXSHV_DROPV, except that shvname is a symbolic variable name.

[RXSHV SYSET]

Like RXSHV SET, except that shvname is a symbolic variable name.

One type of request that needs some special attention is the RXSHV_PRIV, which retrieves a kind of meta-variable. Depending on the value of shvname, it returns a value in shvvalue describing some aspect of the interpreter. For RXSHV_PRIV the possible values for shvname are:

[PARM]

Returns the ASCII representation of the number of parameters to the currently active REXX procedure. This may not be the same value as the built-in function ARG() returns, but is the number ArgCount in RexxStart(). The two might differ if a routine was called with trailing omitted parameters.

[PARM.n]

The n must be a positive integer; and the value returned will be the n'th parameter at the current procedure level. This is not completely equivalent to the information that the built-in function ARG() returns. For parameters where ARG() would return the state omitted, the returned value is a null string, while for parameters where ARG() would return the state existing, the return value will be the parameter string (which may be a zero length string.

[QUENAME]

The name of the currently active external data queue. This feature has not yet been implemented in Regina, which always return default.

[SOURCE]

Returns the same string that is used in the PARSE SOURCE clause in REXX, at the current procedure level of interpretation.

[VERSION]

Returns the same string that is used in the PARSE VERSION clause in REXX.

The value returned by a variable pool request is a bit uncommon. A return value is computed for each request, and stored in the shvret field. This is a one-byte field, of which the most significant bit is never set. A symbolic value RXSHV_OK is defined as the value zero, and the shvret field will be equal to this name if none if the flags listed below is set. The symbolic value for these flags are:

[RXSHV BADF]

The shvcode of this request contained a bad function code.

[RXSHV_BADN]

The shvname field contained a string that is not valid in this context. What exactly is a valid value

depends on whether the operation is a private, a symbolic variable, or direct variable operation.

```
[RXSHV LVAR]
```

Set if and only if the request was RXSHV_NEXTV, and all available variables have already been retrieved by earlier requests.

```
[RXSHV MEMFL]
```

There was not enough memory to complete this request.

```
[RXSHV_NEWV]
```

Set if and only if the referenced variable did not previously have a value. It can be returned for any set, fetch or drop operation.

```
[RXSHV TRUNC]
```

Set if the retrieved value was truncated when it was copied into either the shvname or shvvalue fields. See below.

These flags are directly suitable for logical OR, without shifting, e.g. to check for truncation and no variables left, you can do something like:

```
if (req->shvret & (RXSHV_TRUNC | RXSHV_LVAR)) printf("Truncation or no vars left\n") ;
```

RXSHV_TRUNC can only occur when the interface is storing a retrieved value in a SHVBLOCK, and the pre-allocated space is present, but not sufficiently large. As described for RXSHV_FETCH, the interpreter will allocate enough space if shvvalue.strptr is NULL, and then RXSHV_TRUNC will never be set. Else the space supplied by shvvalue.strptr is used, and shvvaluelen is taken as the maximum length of shvvalue, and truncation will occur if the supplied space is too small.

Some implementations will consider SHV_MEMFL to be so severe as to skip the rest of the operations in a chain of requests. In order to write compatible software, you should never assume that requests following in a chain after a request that returned SHV MEMFL have been performed.

RXSHV_BADN is returned if the supplied shvname contains a value that is not legal in this context. For the symbolic set, fetch and drop operations, that means a symbol that is a legal variable name; both upper and lower case letters are allowed. For the direct set, fetch and drop operations, that means a variable name after normalization and tail substitution is not a legal variable name. For RXSHV_PRIV, it must be one of the values listed above.

There is a small subtlety in the above description. TRL states that when a REXX assignment assigns a value to a stem variable, all possible variables having that stem are assigned a new value (independent of whether they had an explicit value before). So, strictly speaking, if a stem is set, then a RXSHV_NEXTV sequence should return an (almost) infinite sequence of compound variables for that stem. Of course, that is completely useless, so you can assume that only compound variables of that stem given an explicit value after the stem was assigned a value will be returned by RXSHV_NEXTV. However, because of that subtlety, the variables returned by RXSHV_NEXTV for compound variables might not be representative for the state of the variables.

e.g. what would a sequence of RXSHV NEXT requests return after the following REXX code:

foo. = 'bar'
drop foo.bar

The second statement here, might not change the returned values! After the first statement, only the stem foo. would probably have been returned, and so also if all variables were fetched after the second statement.

Regina Notes for the Variable Pool

Due to the subtleties described at the end of the previous subsection, some notes on how Regina handles RXSHV_NEXTV requests for compound variables are in order. The following rules applies:

Both the stem variable FOO. and the compound variable having FOO. as stem and a nullstring as tail, are returned with the name of FOO.. In this situation, a sequence of RXSHV_NEXTV requests may seem to return values for the same variable twice. This is unfortunate, but it seems to be the only way. In any case, you'll have to perform the RXSHV SYFET in order to determine which is which.

If a stem variable has not been assigned a value, its compound variables are only returned if they have been assigned an explicit value. i.e. compound variables for that stem that have either never been assigned a value, or have been dropped, will not be reported by RXSHV_NEXTV. There is nothing strange about this.

If a stem variable has been assigned a value, then its compound variables will be reported in two cases: Firstly, the compound variables having explicitly been assigned a value afterward. Secondly, the compound variables which have been dropped afterward, which are reported to have their initial value, and the flag RXSHV_NEWV is set in shvret.

It may sound a bit stupid that unset variables are listed when the request is to list all variables which have been set, but that is about the best I can do, if I am to stay within the standard definition and return a complete and exact status of the variable pool.

If the return code from RexxVariablePool() is less than 128, Regina is guaranteed to have tried to process all requests in the chain. If the return code is above 127, some requests may not have been processed. Actually, the number 127 (or 128) is a bit inconvenient, since it will be an problem for later expansion of the standard. A much better approach would be to have a preprocessor symbol (say, RXSHV_FATAL, and if the return code from the RexxVariablePool() function was larger than that, it would be a direct error code, and not a composite error code built from the shvret fields of the requests. The RXSHV_FATAL would then have to be the addition of all the atomic composite error codes.

(Warning: author mounting the soapbox.)

The right way to fix this, is to let the function RexxVariablePool() set another flag in shvret (e.g. named RXSHV_STEM) during RXSHV_NEXTV if and only if the value returned is a stem variable. That way, the application programmer would be able to differ between stem variables and compound variable with a null string tail.

To handle the other problem with compound variables and RXSHV_NEXTV, I would have liked to return a null string in shvvalue if and only if the variable is a compound variable having its initial value, and the stem of that compound variable has been assigned a value. Then, the value of the compound variable is equal to its name, and is available in the shvname field.

I'd also like to see that the shvret value contained other information concerning the variables, e.g. whether the variable was exposed at the current procedure level. Of course, Regina does not contain any of these extra, non-standard features.

(Author is dismounting the soapbox.)

When Regina is returning variables with RXSHV_NEXTV, the variables are returned in the order in which they occur in the open hash table in the interpreter. i.e. the order in which variables belonging to different bins are returned is consistent, but the order in which variables hashed to the same bin are returned, is non-deterministic. Note that all compound variables belonging to the same stem are returned in one sequence.

The RexxVariablePool() function

This function is used to process a sequence of variable requests, and process them sequentially. The prototype of this function is:

```
APIRET APIENTRY ULONG RexxVariablePool( SHVBLOCK *Request) ;
```

Its only parameter is a pointer to a SHVBLOCK structure, which may be the first of the linked list. The function performs the operation specified in each block. If an error should occur, the current request is terminated, and the function moves on to the next request in the chain.

The result value is a bit peculiar. If the returned value is less than 128, it is calculated by logically OR'ing the returned shvret field of all the requests in the chain. That way, you can easily check whether any of the requests was e.g. skipped because of lack of memory. To determine which request, you have to iterate through the list.

If the result value is higher than 127, it signifies an error. If any of these values are set, you can not assume that any of the requests have been processed. The following symbolic name gives its meaning.

[RXSHV_NOAVL]

Means that the interface is not available for this request. This might occur if the interface was not able to start the interpreter, or if an operation requested a variable when the interpreter is not currently executing any script (i.e. idle and waiting for a script to execute).

The System Exit Handler Interface

The exit handlers provide a mechanism for governing important aspects of the REXX interpreter from the application: It can trap situations like the interpreter writing out text, and then handle them itself, e.g. by displaying the text in a special window. You can regard system exits as a sort of hooks.

The System Exit Handler

Just like the subcommand handler, the system exit handler is a routine supplied by the application,

and is called by the interpreter when certain situations occur. These situations are described in detail later. For the examples below, we will use the output from SAY as an example.

If a system exit handler is enabled for the SAY instruction, it will be called with a parameter describing the text that is to be written out. The system exit handler can choose to handle the situation (e.g. by writing the text itself), or it can ignore it and let the interpreter perform the output. The return code from the system exit tells the interpreter whether a system exit handled the situation or not.

A system exit handler must be a routine defined according to the prototype:

```
LONG APIENTRY my_exit_handler(LONG ExitNumber, LONG Subfunction, PEXIT ParmBlock);
```

In this prototype, the type PEXIT is a pointer to a parameter block containing all the parameters necessary to handle the situation. The actual definition of this parameter block will vary, and is described in detail in the list of each system exit.

The exits are defined in a two-level hierarchy. The ExitNumber defines the main function for a system exit, while the Subfunction defines the subfunction within that main function. e.g. for SAY, the main function will be RXSIO (the system exit for standard I/O) and the subfunction will be RXSIOSAY. The RXSIO main function has other sub-functions for handling trace output, interactive trace input, and PULL input from standard input.

The value returned from the system exit handler must be one of the following symbolic values:

[RXEXIT_HANDLED]

Signals that the system exit handler took care of the situation, and that the interpreter should not proceed to do the default action. For the SAY instruction, this means that the interpreter will not print out anything.

[RXEXIT_NOT_HANDLED]

Signals that the system exit handler did not take care of the situation, and the interpreter will proceed to perform the default action. For the SAY instruction, this means that it must print out the argument to SAY.

[RXEXIT RAISE ERROR]

Signals that the interpreter's default action for this situation should not be performed, but instead a SYNTAX condition should be raised. Don't get confused by the name, it is not the ERROR condition, but the SYNTAX condition is raised, using the syntax error Failure in system service (normally numbered 48).

In addition to returning information as the numeric return value, information may also be returned by setting variables in the parameter block. For instance, if the system exit is to handle interactive trace input, that is how it will supply the interpreter with the input string.

It is a good and disciplined practice to let your exit handlers start by verifying the ExitNumber and Subfunction codes, and immediately return RXEXIT_NOT_HANDLED if it does not recognize both of them. That way, your application will be upwards compatible with future interpreters which might have more sub-functions for any given main function.

List of System Exit Handlers

RXFNC - The External Function Exit Handler

The RXFNC system exit handler provides hooks for external functions. It has only one subfunction; RXFNCCAL, which allows an application program to intervene and handle any external function or subroutine.

Do not confuse this exit handler with the external function routines which allow you to define new REXX, semi-built-in functions. The exit handler is called for all invocations of external routines, and can be called for function names which you were unaware of.

The parameter ParmBlock for RXFNCCAL is defined as:

```
typedef struct {
    typedef struct {
        unsigned int rxfferr:1;
        unsigned int rxffnfndl;
        unsigned int rxffsub: 1;
    } rxfnc_flags;
    unsigned char *rxfnc_address;
    unsigned short rxfnc_addressl;
    unsigned char *rxfnc_que;
    unsigned short rxfnc_que;
    unsigned short rxfnc_quel;
    unsigned short rxfnc_argc;
    RXSTRING *rxfnc_argv;
    RXSTRING rxfnc_retc;
} RXFNCCAL_PARM;
```

The significance of each variable is:

```
[rxfnc_flags.rxfferr]
```

Is an output parameter that is set on return in order to inform the interpreter that the function or subroutine was incorrectly called, and thus the SYNTAX condition should be raised.

```
[rxfnc_flags.rxffnfnd]
```

Is an output parameter that tells the interpreter that the function was not found. Note the inconsistency: it is only effective if the exit handler returns RXEXIT_HANDLED, which looks like a logic contradiction to setting the not-found flag.

```
[rxfnc_flags.rxffsub]
```

Is an input parameter that tells the exit handler whether it was called for a function or subroutine call. If set, the call being handled is a subroutine call and returning a value is optional; else it was called for a function, and must return a value in rxfnc retc if RXEXIT HANDLED is to be returned.

```
[rxfnc_name]
```

Is a pointer to the name of the function or subroutine to be handled, stored as a character array. This

is an input parameter, and its length is given by the rxfnc namel parameter.

```
[rxfnc namel]
```

Holds the length of rxfnc name. Note that the last character is the letter ell, not the number one.

```
[rxfnc_que]
```

Points to a character array holding the name of the currently active queue. This is an input parameter. The length of this name is given by the rxfnc_quel field.

```
[rxfnc_que1]
```

Holds the length of rxfnc que. Note that the last character is the letter ell, not the number one.

```
[rxfnc_argc]
```

Is the number of arguments passed to the function or subroutine. It defines the size of the array pointed to by the rxfnc argv field.

```
[rxfnc argv]
```

Points to an array holding the parameters for the routines. The size of this array is given by the rxfnc_argc field. If rxfnc_argc is zero, the value of rxfnc_argv is undefined.

```
[rxfnc_retc]
```

Holds an RXSTRING structure suitable for storing the return value of the handler. It is the responsibility of the handler to allocate space for the contents of this string (i.e. the array pointed to by the rxfnc retc.strptr).

RXCMD - The Subcommand Exit Handler

The main function code for this exit handler is given by the symbolic name RXCMD. It is called whenever the interpreter is about to call a subcommand, i.e. a command to an external environment. It has only one subfunction:

RXCMDHST

The ParmBlock parameter for this subfunction has the following definition:

```
typedef struct {
    typedef struct {
      unsigned int rxfcfail:1;
      unsigned int rxfcerr:1;
    } rxcmd_flags;
    unsigned char *rxcmd_address;
    unsigned short rxcmd_addressl;
    unsigned char *rxcmd_dll;
    unsigned short rxcmd_dll_len;
    RXSTRING rxcmd_command;
    RXSTRING rxcmd_retc;
```

Last update: 2024/09/04 06:58

RXCMDHST PARM ;

The significance of each variable is:

[rxcmd_flags.rxfcfail]

If this flag is set, the interpreter will raise a FAILURE condition at the return of the exit handler.

[rxcmd flags.rxfcerr]

Like the previous, but the ERROR condition is raised instead.

[rxcmd address]

Points to a character array containing the name of the environment to which the command normally would be sent.

[rxcmd addressl]

Holds the length of rxcmd address. Note that the last character is the letter ell, not the number one.

[rxcmd_dll]

Defines the name for the DLL which is to handle the command. I'm not sure what this entry is used for. It is not currently in use for Regina.

[rxcmd_dll_len]

Holds the length of rxcmd_dll. If this length is set to zero, the subcommand handler for this environment is not a DLL, but an EXE handler.

[rxcmd command]

Holds the command string to be executed, including command name and parameters.

[rxcmd retc]

Set by the exit handler to the string which is to be considered the return code from the command. It is assigned to the special variable RC at return from the exit handler. The user is responsible for allocating space for this variable. I have no clear idea what happens if rxcmd_retc.strptr is set to NULL; it might set RC to zero, to the null string, or even drop it.

It seems that this exit handler is capable of raising both the ERROR and the FAILURE conditions simultaneously. I don't know whether that is legal, or whether only the FAILURE condition is raised, since the ERROR condition is a sort of subset of FAILURE.

Note that the return fields of the parameter block are only relevant if the value RXEXIT_HANDLED was returned. This applies to the rxcmd flags and rxcmd retc fields of the structure.

RXMSQ - The External Data Queue Exit Handler

The external data gueue exit handler is used as a hook for operations manipulating the external data

queue (or the stack). Unfortunately, the stack is a borderline case of what is relevant to the REXX SAA API. Operations like putting something on, retrieving a string from, obtaining the size, etc. of the stack is not part of the SAA API.

However, some of this functionality is seemingly here; but not all. For instance for the RXMSQPLL subfunction, SAA API is called by the interpreter before the interpreter calls whatever system-specific call is available for retrieving a string from the stack.

Thus the SAA API can be used by an application to provide the interpreter with a fake stack, but it is not a suitable means for the application itself to manipulate the real stack.

The RXMSG exit has four subfunctions:

[RXMSQPLL]

This is called before a line is retrieved from the stack and the application may itself provide the interpreter with an alternative line. On entry, the third parameter points to a structure having the following definition:

```
typedef struct {
  RXSTRING rxmsq_retc;
} RXMSQPLL_PARM;
```

The rxmsq_retc field holds the string to be retrieved from the stack. Note that it is an output parameter, so its value on entry is undefined.

[RXMSQPSH]

This is called before the interpreter puts a line on the stack, and it may grab the line itself, and thus prevent the interpreter from putting the line on the stack. Note that this exit handles both pushing and queuing. The third parameter is:

```
typedef struct {
    struct {
       unsigned rxfmlifo: 1;
    } rxmsq_flags;
    RXSTRING rxmsq_value;
} RXMSQPSH_PARM;
```

Here the field rxmsq_value holds the string to be put on the stack. Whether the string is to be pushed or queued is determined by the boolean value rxmsq_flags.rxmlfifo, which is TRUE if the string is to be pushed.

All values are input values. What happens if you change them is not defined in the SAA API. Some implementations may let you modify the contents of rxmsq_value and return RXEXIT_NOT_HANDLED and the string push by the interpreter contains the modified string. However, you should not rely on this since it is highly incompatible. You may not de-allocate rxmsq_value.

[RXMSQSIZ]

this is called before the interpreter tries to determine the size of the stack, and it may present an alternative size to the interpreter. The third parameter is:

```
typedef struct {
  ULONG rxmsq_size;
} RXMSQSIZ_PARM;
```

The field rxmsq_size can be set to the number the application wants the QUEUED() function to return. Note that this parameter is undefined on entry, so it cannot be used to retrieve the number of lines on the stack.

[RXSONAM]

This is called before the interpreter tries to retrieve the name of the current stack, and it may present the interpreter with an alternative name. Note that this functionality is part of SAA but not TRL; it supports the Get option of the RXQUEUE() built-in function. Note that there are no other exits supporting the other options of RXQUEUE(). The third parameter for this exit is:

```
typedef struct {
  RXSTRING rxmsq_name;
} RXMSQNAM_PARM;
```

As with RXSQMSIZ, the field rxmsq_name can be set to the name which the application wants to return to the interpreter as the name of the current stack. Note that this is an output-only parameter; its value on input is undefined, and in particular is not the name of the real stack.

Note that this area is troublesome. In TRL, external data queues are not defined as part of the language, while in SAA it is. Thus, TRL-compliant interpreters are likely to implement stacks in various ways that may not be compatible with the SAA.

RXSIO - The Standard I/O Exit Handler

The main code for this exit handler has the symbolic value RXSIO. There are four sub-functions:

[RXSIODTR]

Called whenever the interpreter needs to read a line from the user during interactive tracing. Note the difference between this subfunction and RXSIOTRD.

[RXSIOSAY]

Called whenever the interpreter tries to write something to standard output in a SAY instruction, even a SAY instruction without a parameter.

[RXSIOTRC]

Called whenever the interpreter tries to write out debugging information, e.g. during tracing, as a trace back, or as a syntax error message.

[RXSIOTRD]

Called whenever the interpreter need to read from the standard input stream during a PULL or PARSE PULL instruction. Note that it will not be called if there is sufficient data on the stack to satisfy the operation.

Note that these function are only called for the exact situations that are listed above. e.g. the RXSIOSAY is not called during a call to the REXX built-in function LINEOUT() that writes to the default output stream. TRL says that SAY is identical to calling LINEOUT() for the standard output stream, but SAA API still manages to see the difference between stem variables and compound variables with a ``zero-length-string' tail. Please bear with this inconsistency.

Depending on the subfunction, the ParmBlock parameter will have four only slightly different definitions. It is kind of frustrating that the ParmBlock takes so many different datatypes, but it can be handled easily using unions, see a later section. The definitions are:

```
typedef struct {
  RXSTRING rxsiodtr_retc ; /* the interactive trace input */
} RXSIODTR_PARM ;

typedef struct {
  RXSTRING rxsio_string ; /* the SAY line to write out */
} RXSIOSAY_PARM ;

typedef struct {
  RXSTRING rxsio_string ; /* the debug line to write out */
} RXSIOTRC_PARM ;

typedef struct {
  RXSTRING rxsio_string ; /* the line to read in */
} RXSIOTRD_PARM ;
```

In all of these, the RXSTRING structure either holds the value to be written out (for RXSIOSAY and RXSIOTRC), or the value to be used instead of reading standard input stream (for RXSIOTRD and RXSIODTR). Note that the values set by RXSIOTRD and RXSIODTR are ignored if the exit handler does not return the value RXEXIT_HANDLED.

Any end-of-line marker are stripped off the strings in this context. If the exit handler writes out the string during RXSIOSAY or RXSIOTRC, it must supply any end-of-line action itself. Similarly, the interpreter does not expect a end-of-line marker in the data returned from RXSIODTR and RXSIOTRD.

The space used to store the return data for the RXSIODTR and RXSIOTRD sub-functions, must be provided by the exit handler itself, and the space is not de-allocated by the interpreter. The space can be reused by the application at any later time. The space allocated to hold the data given by the RXSIOSAY and RXSIOTRC sub-functions, will be allocated by the interpreter, and must neither be de-allocated by the exit handler, nor used after the exit handler has terminated.

RXHLT - The Halt Condition Exit Handler

Note: Because the RXHLT exit handler is called after every REXX instruction, enabling this exit slows REXX program execution.

The main code for this exit handler has the symbolic value RXHLT. There are two sub-functions:

[RXHLTTST]

Called whenever the interpreter polls externally raised HALT conditions; i.e. after every REXX instruction.

The definition of the ParmBlock is:

```
typedef struct {
  unsigned rxfhhlt : 1 ;
} RXHLTTST_PARM ;
```

The rxfhhlt parameter is set to the state of the HALT condition in the interpreter; either TRUE or FALSE.

[RXHLTCLR]

Called to acknowledge processing of the HALT condition when the interpreter has recognized and raised a HALT condition.

RXTRC - The Trace Status Exit Handler

Not implemented.

RXINI - The Initialization Exit Handler

RXTER and this exit handler are a bit different from the others. RXINI provides the application programmer with a method of getting control before the execution of the script starts. Its main purpose is to enable manipulation of the variable pool in order to set up certain variables before the script starts, or set the trace mode.

It has only one subfunction, RXINIEXT, called once during each call to RexxStart(): just before the first REXX statement is interpreted. Variable manipulations performed during this exit will have effect when the script starts.

As there is no information to be communicated during this exit, the value of ParmBlock is undefined. It makes no difference whether you return RXEXIT_HANDLED or RXEXIT_NOT_HANDLED, since there is no situation to handle.

RXTER - The Termination Exit Handler

This exit resembles RXINI. Its sole subfunction is RXTEREXT, which is called once, just after the last statement of the REXX script has been interpreted. The state of all variables are intact during this call; so it can be used to retrieve the values of the variables at the exit of a script. (In fact, that is the whole purpose of this exit handler.)

Like RXINI, there is no information to be communicated during the exit, so ParamBlock is undefined in this call. And also like RXINI, it is more of a hook than an exit handler, so it does not matter whether you return RXEXIT HANDLED or RXEXIT NOT HANDLED.

RXENV - The External Environment Exit Handler

This System Exit is specific to Regina, so caution should be exercised if you plan on making your code portable to other REXX interpreters.

The main code for this exit handler has the symbolic value RXENV. There are four sub-functions:

[RXGETENV]

Called whenever the BIF; VALUE() is called to obtain a value from the external environment. i.e. the call to VALUE() is of the form:

```
VALUE('VARNAME', ,'ENVIRONMENT').
```

[RXSETENV]

Called whenever the BIF; VALUE() is called to set a value in the external environment. i.e the call to VALUE() is of the form: VALUE('VARNAME',newvalue,'ENVIRONMENT').

[RXGETCWD]

Called whenever the current working directory is needed to be obtained from the environment. The DIRECTORY() BIF respects this system exit.

[RXSETCWD]

Called whenever the current working directory is changed by a call to DIRECTORY() or CHDIR() BIFs.

The ParmBlock parameter has the following definitions for each sub-function type:

```
typedef struct {
   RXSTRING rxenv_name ; /* the name of the external environment variable */
RXSTRING rxenv_value ; /* the returned value of the external environment
variable */
} RXGETENV_PARM ;

typedef struct {
   RXSTRING rxenv_name ; /* the name of the external environment variable */
RXSTRING rxenv_value ; /* the value of the external environment variable */
} RXSETENV_PARM ;
```

In both of these, the RXSTRING; rxenv_name structure holds the name of the environment variable as known by the external environment. Note that the values set by RXSIOTRD and RXSIODTR are ignored if the exit handler does not return the value RXEXIT HANDLED.

The space used to store the return data for the RXSIODTR and RXSIOTRD sub-functions, must be provided by the exit handler itself, and the space is not de-allocated by the interpreter. The space can be reused by the application at any later time. The space allocated to hold the data given by the RXSIOSAY and RXSIOTRC sub-functions, will be allocated by the interpreter, and must neither be de-allocated by the exit handler, nor used after the exit handler has terminated.

The RexxRegisterExitExe() function

This function is used to register a system exit handler with the interface. The system exit handler must be a procedure located within the code of the application. After registration, the REXX interpreter will execute the system exit handler when the approriate event is triggered in the interpreter.

The prototype for RexxRegisterExitExe() is:

APIRET APIENTRY RexxRegisterExitExe(PCSZ EnvName, PFN EntryPoint, PUCHAR UserArea);

All the parameters are input:

[EnvName]

Points to an ASCII NUL terminated character string which defines the name of the system exit handler to be registered.

[EntryPoint]

Points to the entrypoint of the system exit handler routine to be registered. See 8.6.1 The System Exit Handler for more information.

[UserArea]

Pointer to an 8 byte area of information that is to be associated with this environment. This data can be accessed via the RexxQueryExit() function. If no user-supplied data required, set this to NULL.

The RexxRegisterExitExe() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXEXIT values:

[RXEXIT_OK]

The handler was successfully registered.

[RXEXIT LOADERR]

??

[RXEXIT_NOTINIT]

??

[RXEXIT_DUP]

The handler was successfully registered. There already existed another system exit handler which was registered with RexxRegisterExitExe(), but this will be shadowed by the newly registered handler.

[RXEXIT NOTREG]

Due to some error, the handler was not registered. Probably because a handler for EnvName was already defined at a previous call to RexxRegisterExitExe().

[RXEXIT NOEMEM]

The handler was not registered, due to lack of memory.

[RXEXIT_BADTYPE]

One or more of the parameters had illegal values, and the operation was not carried through. Regina addition.

The RexxRegisterExitDII() function

This function is used to set up a routine that is located in a module in a dynamic link library, as a system exit handler. After registration, the REXX interpreter will execute the system exit handler when the approriate event is triggered in the interpreter.

Some operating systems don't have dynamic linking, and thus cannot make use of this facility. The prototype of this function is:

APIRET APIENTRY RexxRegisterExitDll(PSZ EnvName, PSZ ModuleName, PFN EntryPoint, PUCHAR UserArea, ULONG DropAuth);

All the parameters are input, and their significance are:

[EnvName]

Points to an ASCII NUL terminated character string which defines the name of the system exit handler to be registered.

[ModuleName]

Points to an ASCII NUL terminated character string which defines the name of the dynamic or shared library in which the EntryPoint to the system exit exists.

[EntryPoint]

Points to the entrypoint of the system exit handler routine for the environment to be registered. See the section on System Exit Handlers for more information. There is an upper limit for the length of this name.

[UserArea]

Pointer to an 8 byte area of information that is to be associated with this environment. This data can be accessed via the RexxQueryExit() function. This pointer can be NULL if no such area is necessary.

[DropAuth]

Is either RXEXIT_DROPABLE or RXEXIT_NONDROP. This argument is ignored by Regina as system exits only exist within the current process.

The areas pointed to by EnvName, ModuleName and UserArea are copied to a private area in the interface, so the programmer may de-allocate or reuse the area used for these parameters after the call has returned.

RexxRegisterExitDII() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXEXIT values:

[RXEXIT OK]

The system exit handler was successfully registered.

[RXEXIT DUP]

The system exit handler was successfully registered. There already existed another system exit handler which was registered with RexxRegisterExitDII(), but this will be shadowed by the newly registered handler.

[RXEXIT NOTREG]

Due to some error, the handler was not registered. Probably because a handler for EnvName was already defined at a previous call to RexxRegisterExitDII().

[RXEXIT_NOEMEM]

The handler was not registered, due to lack of memory.

[RXEXIT_BADTYPE]

Indicates that the handler was not registered, due to one or more of the parameters having invalid values. Regina addition.

The RexxDeregisterExit() function

This function is used to remove a particular environment from the list of registered environments. The prototype of the function is:

APIRET APIENTRY RexxDeregisterExit(PSZ EnvName, PSZ ModuleName) ;

Both parameters are input values:

[EnvName]

Pointer to ASCII NUL terminated string, which represents the name of the environment to be removed.

[ModuleName]

Also an ASCII NUL terminated string, which points to the name of the module containing the system exit handler of the environment to be deleted.

The list of defined environments is searched, and if an environment matching the one named by the first parameter are found, it is deleted.

The returned value from RexxDeregisterExit() can be one of:

[RXEXIT OK]

The system exit handler was successfully deleted.

[RXEXIT NOTREG]

The system exit handler was not found.

[RXEXIT BADTYPE]

One or more of the parameters had illegal values, and the operation was not carried through. Regina addition.

[RXEXIT_NOCANDROP]

Unable to deregister the system exit handler. Regina addition.

Most systems that do have dynamic linking have no method for reclaiming the space used by dynamically linked routines. So, even if you were able to load a dll, there are no guarantees that you will be able to unload it.

The RexxQueryExit() function

This function retrieves information about a previously registered system exit handler. The prototype of the function is:

```
APIRET APIENTRY RexxQueryExit( PSZ EnvName, PSZ ModuleName, PUSHORT Flag, PUCHAR UserArea);
```

The significance of the parameters are:

[EnvName]

Pointer to an ASCII NUL terminated character string, which names the system exit handler about which information is to be returned.

[ModuleName]

Pointer to an ASCII NUL terminated character string, which names a dynamic link library. Only the named library will be searched for the system exit handler named by EnvName. This parameter must be NULL if all system exit handlers are to be searched.

[Flag]

Pointer to a short which is to receive the value RXEXIT_OK or RXEXIT_NOTREG. In fact, this is the same as the return value from the function.

[UserArea]

Pointer to an area of 8 bytes. The userarea of the system exit handler is copied to the area pointed to by UserArea. This parameter might be NULL if the data of the userarea is not needed.

The returned value from RexxQueryExit() can be one of:

[RXEXIT OK]

The system exit handler was found, and the required information has been returned in the Flag and UserArea variables.

[RXEXIT NOTREG]

The system exit handler was not found. The Flag variable will also be set to this value, and the UserArea variable is not changed.

[RXEXIT BADTYPE]

One or more of the parameters had illegal values, and the operation was not carried through. Regina addition.

The External Queue Interface

The external queue interface provide a mechanism for interacting with the interpreter's external queues. This interface is analogous to a REXX program's use of PUSH, QUEUE, PULL, and RXQUEUE(). Note that this interface only works with the external queues, it cannot interface to the internal named queues that exists within the interpreter.

The RexxCreateQueue() function

This function is used to create a new, named, external queue. The prototype for RexxCreateQueue() is:

```
APIRET APIENTRY RexxCreateQueue( PSZ Buffer, ULONG BuffLen, PSZ RequestedName, ULONG *DupFlag) ;
```

The following parameters are input, and their significance are:

[RequestedName]

Points to an ASCII NUL terminated character string which specifies the name of the queue to be created. See Queue Names for the structure of a queue name. If the user wishes to have the interpreter create a unique queue name on the local queue server at the default port number, then this value should be set to NULL. To request an interpreter-generated queue name, on the machine fred listening on port 5858, then specify @fred:5858. i.e. leave the queue name portion blank.

The following parameters are output, and their significance are:

[Buffer]

Points to an ASCII NUL terminated character string allocated by the user. The name of the queue that is created will be copied into this area.

[BuffLen]

Specifies the size of the memory area pointed to by Buffer.

[DupFlag]

Indicates if the queue name specified already exists. If a queue name already exists, DupFlag is set to 1, otherwise it is set to 0.

The RexxCreateQueue() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXQUEUE values:

[RXQUEUE_OK]

The queue was successfully created.

[RXQUEUE_NOEMEM]

The queue was not created, due to lack of memory.

[RXQUEUE_BADQNAME]

The queue name is invalid or "SESSION" is specified.

The RexxDeleteQueue() function

This function is used to delete a named, external queue. The prototype for RexxDeleteQueue() is:

APIRET APIENTRY RexxDeleteQueue(PSZ QueueName) ;

The only parameters is an input, and its significance is:

[QueueName]

Points to an ASCII NUL terminated character string which specifies the name of the queue to be deleted. See Queue Names for the structure of a queue name.

The RexxDeleteQueue() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXQUEUE values:

[RXQUEUE OK]

The queue was successfully deleted.

[RXQUEUE_NOTREG]

The queue name specified does not exist.

[RXQUEUE BADQNAME]

The queue name was not specified.

The RexxQueryQueue() function

This function is used to determine the number of items that are available on the named, external queue.

The prototype for RexxQueueQueue() is:

```
APIRET APIENTRY RexxQueryQueue( PSZ QueueName, ULONG *Count) ;
```

One parameters is an input, and its significance is:

[QueueName]

Points to an ASCII NUL terminated character string which specifies the name of the queue to be queried. See Queue Names for the structure of a queue name.

The following parameter is output, and its significance is:

[Count]

Points to an unsigned long which indicates the number of items on the specified queue.

The RexxQueryQueue() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXQUEUE values:

[RXQUEUE_OK]

The queue was successfully queried, and Count contains the number of items on the queue.

[RXQUEUE NOTREG]

The queue name specified does not exist.

[RXQUEUE BADQNAME]

The queue name was not specified

The RexxAddQueue() function

This function is used to determine add an item to a named, external queue. The prototype for RexxAddQueue() is:

APIRET APIENTRY RexxAddQueue(PSZ QueueName, PRXSTRING EntryData, ULONG AddFlag);

All parameters are input, and their significance are:

[QueueName]

Points to an ASCII NUL terminated character string which specifies the name of the queue on which the data is to be added. See Queue Names for the structure of a queue name.

[EntryData]

Points to a RXSTRING structure containing the data to be added to the queue.

[AddFlag]

Indicates how the data is to be added. Can be one of:

RXQUEUE_FIFO, to indicate that the data is to be added in a first-in-first-out order. This is equivalent to the QUEUE keyword.

RXQUEUE_LIFO, to indicate that the data is to be added in a last-in-first-out order. This is equivalent to the PUSH keyword.

The RexxAddQueue() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXQUEUE values:

[RXQUEUE OK]

The data was successfully added to the specified queue.

[RXQUEUE NOTREG]

The queue name specified does not exist.

[RXQUEUE BADQNAME]

The queue name was not specified

The RexxPullQueue() function

This function is used to extract an item from the specified named, external queue. When successful, the item from the queue is returned, and that item deleted from the queue.

The prototype for RexxPullQueue() is:

APIRET APIENTRY RexxPullQueue(PSZ QueueName, PRXSTRING DataBuf, PDATETIME TimeStamp, ULONG WaitFlag);

The following parameters are input, and their significance are:

[QueueName]

Points to an ASCII NUL terminated character string which specifies the name of the queue from which the data is to be extracted. See Queue Names for the structure of a queue name.

[WaitFlag]

Indicates if the process should wait until there is data in the specified queue before returning. This could cause the process to block forever, if no data is due in the queue. Regina does not support this option at this stage; RXQUEUE NOWAIT is assumed Value can be one of:

RXQUEUE WAIT, the process is to block and wait for data if the queue is currently empty.

RXQUEUE_NOWAIT, the process does not wait for data in the queue if it is currently empty. RexxPullQueue() will return RXQUEUE EMPTY if there is no data in the queue.

The following parameters are output, and their significance are:

[DataBuf]

Points to a RXSTRING structure into which the contents of the extracted item are placed. The memory associated with the RXSTRING strptr, should be deallocated using RexxFreeMemory().

[TimeStamp]

Points to a PDATETIME structure, which on return, contains the time details of when the item was added to the external queue. Regina does not support this option at this stage.

The RexxPullQueue() returns an unsigned long, which carries status information describing the outcome of the operation. The status will be one of the RXQUEUE values:

[RXQUEUE OK]

The data was successfully added to the specified queue.

[RXQUEUE NOTREG]

The queue name specified does not exist.

[RXQUEUE BADQNAME]

The queue name was not specified

[RXQUEUE EMPTY]

The queue was empty and RXQUEUE NOWAIT was specified.

[RXQUEUE BADWAITFLAG]

The value of the WaitFlag parameter was not RXQUEUE WAIT or RXQUEUE NOWAIT.

The Macro Space Interface

The macro space interface provide a mechanism for pre-loading external REXX programs into the current interpreter's macro space, so that the macros can be executed faster than reading them from disk each time they are called. This interface is not available in Regina at this stage.

The RexxAddMacro() function

The RexxDropMacro() function

The RexxSaveMacroSpace() function

The RexxLoadMacroSpace() function

The RexxQueryMacro() function

The RexxReorderMacro() function

The RexxClearMacroSpace() function

Allocating and De-allocating Space

For several of the functions described in this chapter, the application calling them must allocate or deallocate dynamic memory. Depending on the operating system, compiler and REXX interpreter, the method for these allocations and de-allocations vary. Because of this, Regina supplies the API function calls RexxAllocateMemory() and RexxFreeMemory(). These functions are wrappers for the appropriate compiler or operating system memory functions.

The RexxAllocateMemory() function

The prototype for RexxAllocateMemory() is:

```
PVOID APIENTRY RexxAllocateMemory( ULONG size);
```

The parameter is an input, and its significance is:

[size]

The number of bytes of dynamic memory requested.

RexxAllocateMemory() returns a pointer to the newly allocated block of memory, or NULL if no memory could be allocated.

The RexxFreeMemory() function

The prototype for RexxFreeMemory() is:

```
APIRET APIENTRY RexxFreeMemory( PV0ID MemoryBlock);
```

The parameter is an input, and its significance is:

[MemoryBlock]

A void pointer to the block of memory allocated by the interpreter, or allocated by a previous call to RexxAllocateMemory().

RexxFreeMemory() always return 0.

Calling back into running REXX Code

This section describes the RexxCallBack() function, which allows the application to execute a procedure within the running REXX program. This function is particularly useful for building a REXX interface to those library applications that operate using a callback mechanism.

A callback mechanism is one where certain events within a particular application can be connected to a particular function, so that when a particular event occurs, the connected function is executed. Many C library applications use a callback mechanism.

This function is specific to Regina, so caution should be exercised if you plan on making your code portable to other REXX interpreters.

The RexxCallBack() function

This function is used to execute an internal procedure within the running REXX script. The procedure is executed with the same context as if the procedure were called from within the REXX program as a function call.

APIRET APIENTRY RexxCallBack(PSZ ProcedureName, LONG ArgCount, PRXSTRING ArgList, PUSHORT ReturnCode, PRXSTRING Result);

Of these parameters, ReturnCode and Result are output-only. The rest of the parameters are input-only. The significance of the parameters are:

[ProcedureName]

An ASCII NUL terminated string, specifying the name of the internal procedure of the running REXX script to be executed. This internal procedure name must exist or this function will return with RX_CB_BADN.

[ArgCount]

The number of parameter strings given to the procedure. This is the number of defined REXX-strings pointed to by the ArgList parameter. The default maximum number of arguments that can be passed is 32, but this can be changed by the MAX ARGS TO REXXSTART macro in rexx.h.

[ArgList]

Pointer to an array of REXX-strings, constituting the parameters to this call to REXX. The size of this array is given by the parameter ArgCount. If ArgCount is greater than one, the first and last parameters are ArgList[0] and ArgList[ArgCount-1]. If ArgCount is 0, the value of ArgList is irrelevant.

If the strptr of one of the elements in the array pointed to by ArgList is NULL, that means that this

parameter is empty (i.e. unspecified, as opposed to a string of zero size).

[ReturnCode]

Pointer to a SHORT integer where the return code from the called ProcedureName is stored, provided that the returned value is numeric, and within the range -(2**15) to 2**15-1. I don't know what happens to ReturnCode if either of these conditions is not satisfied. It probably becomes undefined, which means that it is totally useless since the program has to inspect the return string in order to determine whether ReturnCode is valid.

Regina allows the value of this parameter to be NULL if the user is not interested in it.

[Result]

Points to a REXX string into which the result string from the called ProcedureName is written. The caller may or may not let the strptr field be supplied. If supplied (i.e. it is non-NULL), that area will be used, else a new area will be allocated. If the supplied area is used, its size is supposed to be given by the strlength field. If the size if not sufficient, a new area will be allocated, by RexxAllocateMemory(), and the caller must see to that it is properly de-allocated using RexxFreeMemory().

Regina allows the value of this parameter to be NULL if the user is not interested in it.

Note that the ArgCount parameter need not be the same as the ARG() built-in function would return. Differences will occur if the last entries in ArgList are null strings.

The arguments passed to the ProcedureName will be passed individually. i.e. the PARSE ARG command in the ProcedureName must use commas to separate the arguments. The valid return values from RexxCallBack() are:

[Negative]

indicates that a syntax error occurred during interpretation. In general, you can expect the error value to have the same absolute value as the REXX syntax error (but opposite signs, of course).

[Zero, or RX CB OK]

indicates that the interpreter finished executing the procedure without errors.

[Positive]

indicates probably that some problem occurred, that made it impossible to execute the procedure, e.g. a bad parameter value. The values that can be return are: RX CB BADP bad parameters

RX_CB_NOTSTARTED there is no running REXX program RX_CB_TOOMANYP too many parameters supplied RX_CB_BADN the ProcedureName does not exist

During the course of an execution of RexxCallBack(), subcommand handlers and exit handlers might be called. These may call any function in the application interface, including another invocation of RexxCallBack().

Implementation Limits

This chapter lists the implementation limits required by the REXX standard. All implementations are supposed to support at least these limits.

Why Use Limits?

Last update: 2024/09/04 06:58

Why use implementation limits at all? Often, a program (ab)uses a feature in a language to an extent that the implementor did not foresee. Suppose an implementor decides that variable names can not be longer than 64 bytes. Sooner or later, a programmer gets the idea of using very long variable names to encode special information in the name; maybe as the output of a machine generated program. The result will be a program that works only for some interpreters or only for some problems.

By introducing implementation limits, REXX tells the implementors to what extent a implementation is required to support certain features, and simultaneously it tells the programmers how much functionality they can assume is present.

Note that these limited are required minimums for what an implementation must allow. An interpreter is not supposed to enforce these limits unless there is a good reason to.

What Limits to Choose?

A limit must not be perceived as an absolute limit, the implementer is free to increase the limit. To some extent, the implementer may also decrease the limit, in which case this must be properly documented as a non-standard feature. Also, the reason for this should be noted in the documentation.

Many interpreters are likely to have "memory" as an implementation limit, meaning that they will allow any size as long as there is enough memory left. Actually, this is equivalent to no limit, since running out of memory is an error with limit enforcing interpreters as well. Some interpreters let the user set the limits, often controlled through the OPTIONS instruction.

For computers, limit choices are likely to be powers of two, like 256, 1024, 8192, etc. However, the REXX language takes the side of the user, and defines the limits in units which looks as more "sensible" to computer non-experts: most of the limits in REXX are numbers like 250, 500, 1000, etc.

Required Limits

These are the implementation minimums defined by REXX:

[Binary strings]

Must be able to hold at least 50 characters after packing. That means that the unpacked size might

be at least 400 characters, plus embedded white space.

[Elapse time clock]

Must be able to run for at least 10**10-1 seconds, which is approximately 31.6 years. In general, this is really a big overkill, since virtually no program will run for a such a period. Actually, few computers will be operational for such a period.

[Hexadecimal strings]

Must be able to hold at least 50 characters after packing. This means that the unpacked size might be at least 100 characters, plus embedded white space.

[Literal strings]

Must be able to hold at least 100 characters. Note that a double occurrence of the quote character (the same character used to delimit the string) in a literal string counts as a single character. In particular, it does not count as two, nor does it start a new string.

[Nesting of comments]

Must be possible to in at least 10 levels. What happens then is not really defined. Maybe one of the syntax errors is issued, but none is obvious for this use. Another, more dangerous way of handling this situation would be to ignore new start-of-comments designators when on level 10. This could, under certain circumstances, lead to running of code that is actually commented out. However, most interpreter are likely to support nesting of comments to an arbitrary level.

[The Number of Parameters]

In calls must be supported up to at least 10 parameters. Most implementations support somewhat more than that, but quite a few enforce some sort of upper limit. For the built-in function, this may be a problem only for MIN() and MAX().

[Significant digits]

Must be supported to at least 9 decimal digits. Also, if an implementation supports floating point numbers, it should allow exponents up to 9 decimal digits. An implementation is allowed to operate with different limits for the number of significant digits and the numbers of digits in exponents.

[Subroutine levels]

May be nested to a total of 100 levels, which counts both internal and external functions, but probably not built-in functions. You may actually trip in this limit if you are using recursive solution for large problems. Also, some tail-recursive approaches may crash in this limit.

[Symbol (name) length]

Can be at least 50 characters. This is the name of the symbol, not the length of the value if it names a variable. Nor is it the name of the variable after tail substitution. In other words, it is the symbol as it occurs in the source code. Note that this applies not only to simple symbols, but also compound symbols and constant symbols. Consequently, you can not write numbers of more than 50 digits in the source code, even if NUMERIC DIGITS is set high.

[Variable name length]

Of at least 50 characters. This is the name of a variable (which may or may not be set) after tail substitution.

Older (Obsolete) Limits

First edition of TRL1 contained some additional limits, which have been relaxed in the second edition in order to make implementation possible for a large set of computers. These limits are:

[Clock granularity]

Was defined to be at least of a millisecond.

Far from all computers provide this granularity, so the requirement have been relaxed. The current requirement is a granularity of at least one second, although a millisecond granularity is advised.

What the Standard does not Say

An implementation might enforce a certain limit even though one is not specified in the standard. This section tries to list most of the places where this might be the case:

[The stack]

(Also called: the external data queue) is not formally defined as a concept of the language itself, but a concept to which the REXX language has an interface. Several limits might apply to the stack, in particular the maximum length of a line in the stack and the maximum number of lines the stack can hold at once.

There might also be also be other limits related to the stack, like a maximum number of buffers or a maximum number of different stack. These concepts are not referred to by REXX, but the programmer ought to be aware of them.

[Files]

May have several limits not specified by the definition of REXX, e.g. the number of files simultaneously open, the maximum size of a file, and the length and syntax of file names. Some of these limits are enforced by the operating system rather than an implementation. The programmer should be particularly aware of the maximum number of simultaneously open files, since REXX does not have a standard construct for closing files.

[Expression nesting]

Can in some interpreters only be performed to a certain level. No explicit minimum limit has been put forth, so take care in complex expressions, in particular machine generated expressions.

[Environment name length]

May have some restrictions, depending on your operating system. There is not defined any limit, but there exists an error message for use with too long environment names.

[Clause length]

May have an upper limit. There is defined an error message "Clause too long" which is supposed to be issued if a clause exceeds a particular implementation dependent size. Note that a "clause" does not mean a "line" in this context; a line can contain multiple clauses.

[Source line length]

Might have an upper limit. This is not the same as a "clause" (see above). Typically, the source line limit will be much larger than the clause limit. The source line limit ought to be as large as the string limit.

[Stack operations]

Might be limited by several limits; first there is the number of strings in the stack, then there is the maximum length of each string, and at last there might be restrictions on the character set allowed in strings in the stack. Typically, the stack will be able to hold any character. It will either have "memory" as the limit for the number of string and the length of each string, or it might have a fixed amount of memory set aside for stack strings. Some implementations also set a maximum length of stack strings, often 2*8 or 2*16.

What an Implementation is Allowed to "Ignore"

In order to make the REXX language implementable on as many machines as possible, the REXX standard allow implementation to ignore certain features. The existence of these features are recommended, but not required. These features are:

[Floating point numbers]

Are not required; integers will suffice. If floating points are not supported, numbers can have not fractional or exponential part. And the normal division will not be available, i.e. the operator "/" will not be present. Use integer division instead.

[File operations]

Are defined in REXX, but an implementation seems to be allowed to differ in just about any file operation feature.

Limits in Regina

Regina tries not to enforce any limits. Wherever possible, "memory" is the limit, at the cost of some CPU whenever internal data structures must be expanded if their initial size were too small. Note that Regina will only increase the internal areas, not decrease them afterwards. The rationale is that if you happen to need a large internal area once, you may need it later in the same program too.

In particular, Regina has the following limits:

| Binary Strings | source line length |
|-------------------|-------------------------|
| Clock Granularity | 0.001-1 second (note 2) |

| Last update: | 2024/09 | /04 | 06:58 |
|--------------|---------|-----|-------|
|--------------|---------|-----|-------|

| Elapsed Time clock | until ca. 2038 (note 1) |
|-----------------------|-------------------------|
| Named Queues | 100 |
| Hexadecimal Strings | source line length |
| Interpretable String | source line length |
| Literal String Length | source line length |
| Nesting of Comments | memory |
| Parameters | memory |
| Significant Digits | source line length |
| Source Line Length | 100,000 (note 3) |
| Subroutine Levels | memory |
| Symbol Length | source line length |
| Variable Name Length | source line length |

Notes:

Regina uses the Unix-derived call time() for the elapsed time (and time in general). This is a function which returns the number of seconds since January 1st 1970. According to the ANSI C standard, in which Regina is written, this is a number which will at least hold the number 2**31-1. Therefore, these machines will be able to work until about 2038, and Regina will satisfy the requirement of the elapse time clock until 2006. By then, computers will hopefully be 64 bit.

Unfortunately, the time() C function call only returns whole seconds, so Regina is forced to use other (less standardised) calls to get a finer granularity. However, most of what is said about time() applies for these too.

The clock granularity is a bit of a problem to define. All systems can be trusted to have a granularity of about 1 second. Except from that, it's very difficult to say anything more specific for certain. Most systems allows alternative ways to retrieve the time, giving a more accurate result. Wherever these alternatives are available, Regina will try to use them. If everything else fails, Regina will use 1 second granularity.

For most machines, the granularity are in the range of a few milliseconds. Some typical examples are: 20 ms for Sun3, 4 ms for Decstations 3100, and 10 ms for SGI Indigo. Since this is a hardware restriction, this is the best measure anyone can get for these machines.

The line length limit is defined when Regina is built. Due to the nature of implementation of the source parser, it is not possible to make this a dynamically increase as the source line is read. If you need a line length longer than the current default value, you need to make two changes:

change YY_BUF_LEN in lexsrc.c

change BUFFERSIZE in rexx.h

See the notes in rexx.h that explain that YY_BUF_LEN must be larger than BUFFERSIZE

Regina Features and Implementation

This chapter lists features of Regina and specific implementation capabilities.

Regina Restricted Mode

Many language interpreters provide a mechanism where code executed within that interpreter is limited to affecting the environment of the interpreter and cannot change the external environment in which the interpreter runs.

Restricted mode is used in situations where you need to guarantee that the author of a REXX program is unable to affect the user's environment.

Situations where a restricted mode is applicable include, using Regina as a database procedural language, or as a language plug-in for a Web browser.

Features of Regina that are disabled in restricted mode are:

- LINEOUT, CHAROUT, POPEN, RXFUNCADD BIFs
- "OPEN WRITE", "OPEN BOTH" subcommands of STREAM BIF
- The "built-in" environments eg. SYSTEM, CMD or PATH of ADDRESS command
- Setting the value of a variable in the external environment with VALUE BIF.
- Calling external functions

To run Regina in restricted mode, you can start the Regina interpreter from the command line with the '-r' switch, or when using the REXX SAA API, or-ing RXRESTRICTED to the CallType parameter of RexxStart() function.

Native Language Support

Regina provides native language support in the following ways:

- Error messages can be displayed in a user-selectable native language.
- Locale support for whitespace and character translations.

Error Messages

All native language error messages are contained in binary files (*.mtb) that are built with the Regina executables from source files (*.mts).

The mechanism Regina uses to determine what native language to use to display error messages depends on the operating system.

On EPOC32, the language is supplied when installing; the selected language is contained in default.mtb. On all other platforms, Regina uses environment variables if you want to use a language other than English.

The English language messages are built into the interpreter for two reasons:

- to satisfy the ANSI requirement that error messages can be obtained in English using the ERRORTEXT BIF and specifying a value of 'S' for argument 2.
- used as a fallback position when no native language support is available

Locale Support

Locale support is very limited in Regina currently. There is no ANSI specification about it and care has been taken to avoid unexpected behaviour for multi-language scripts. The basic intention of the support was the ability to handle special characters in some western locales or on some systems.

Non-breakable spaces are part of nearly every character set, but they are hard to implement in REXX programs because of the missing information about the runtime character set when writing the program. Another typical problem came from extra characters in the character sets which allow the translation in some cases. This problem is unsolvable in advance, because some glyphs are characters in one language and they are symbols in other languages. These problems can be solved at runtime only with the knowledge of the country and language.

Regina implements some code which is executed once when the interpreter starts up. This code evaluates the command line parameter or the environment variables and extracts the information about the character set. Note that this operation is not done on a per-thread basis and it is done before any other operation happens. So no change can be done once a program has been loaded into memory and parsed. The use of ADDRESS REXX is recommended for cases where a different character set is required for a called program.

Affected operations of the locale support are:

- string comparison if options STRICT ANSI and STRICT WHITESPACE COMPARISON are not set.
- upper-case translation of variable names, see VALUE BIF or the API functions.
- white space delimiter detection and elimination at word boundaries or number boundaries at all possible places including cases of reading REXX programs and processing PARSE operations.
- CASELESS translation in PARSE operations.
- case translation of the builtin functions TRANSLATE, LOWER, UPPER and the instruction
 - UPPER
 - DATATYPE BIF results.
 - file name case translation when searching external procedures or when using the API for loading external libraries.

Using Native Language Support

To specify a native language, up to 2 environment variables are used.

REGINA_LANG environment variable is set to an ISO 639, 2 character language abbreviation as defined in the following table for error messages, optionally followed by a comma and the locale. The locale is explained in Section 1; "Executing REXX programs With Regina". The value given at the command line by the parameter "-I" takes precedence if it is given at all, even if the empty string is used.

| REGINA_LANG | Language | Translation By |
|-------------|------------|--|
| de | German | Floran Grosse-Coosmann |
| es | Spanish | Pablo Garcia-Abia |
| no | Norwegian | Vidar Tysse |
| pl | Polish | Bartosz Kozlowski |
| pt | Portuguese | Susana and Brian Carpenter, Josie Medeiros |

| REGINA_LANG | Language | Translation By |
|-------------|----------|----------------|
| SV | Swedish | Jan-Erik Lärka |
| tr | Turkish | Haluk Polat |

(to get your name in this table, contact the maintainer with the language you wish to support)

If REGINA_LANG is not set, the default is en. The case of the value is irrelevant; EN is the same as en.

REGINA LANG DIR is required if Regina does not know where the language files will be at runtime.

Any binary distribution that includes an installation routine; RPM, deb, Windows NSIS or EPOC32, will set the location of the .mtb files automatically. Similarly building and installing Regina on Unix-like platforms using configure;make install combination will also set the location automatically. All other platforms will require this environment variable to bet set manually.

REXX and Regina binaries: Why?

TODO: static library, dynamic library and rxfuncadd().

Cannot use rxfuncadd() in a static library to load an external function package as the dynamic library that is loaded with the external function package uses the RexxRegisterFunctionDII that the shared library is linked with; this is the one in libregina.so and it updates the internal table of external functions in its address space, so the internal table of external functions in libregina.a (or rexx binary) will not contain the pointers.

Appendixes

Definitions

In order to make the definitions more readable, but still have a rigid definition of the terms, some extra comments have been added to some of the definitions. These comments are enclosed in square brackets.

Argument is an expression supplied to a function or subroutine, and it provides data on which the call can work on.

Assignment is a clause in which second token is the equal sign. [Note that the statements "a==b" and "3=4" are an (invalid) assignment, not an expression. The type of the first token is irrelevant; if the second token is the equal sign, then the clause is assumed to be an assignment.]

Blanks are characters which glyphs are empty space, either vertically or horizontally. A blank is not a token (but may sometimes be embedded in tokens), but acts as token separators. [Exactly which characters are considered blanks will differ between operating systems and implementations, but the

<space> character is always a blank. The <tab> character is also often considered a blank. Other
characters considered blank might be the end-of-line <eol>), vertical tab (<vt>), and formfeed

(<ff>). See specific documentation for each interpreter for more information.]

Buffer

Caller routine

Character is a piece of information about a mapping from a storage unit (normally a byte) and a glyph. Often used as "the meaning of the glyph mapped to a particular storage unit". [The glyph "A" is the same in EBCDIC and ASCII, but the character "A" (i.e. the mapping from glyph to storage unit) differs.]

Character string is an finite, ordered, and possibly empty set of characters.

Clause is a non-empty collection of tokens in a REXX script. The tokens making up a clause are all the consecutive tokens delimited by two consecutive clause delimiters. [Clauses are further divided into null clauses, instructions, assignments, and commands.]

Clause delimiter is a non-empty sequence of elements of a subset of tokens, normally the linefeed and the semicolon. Also the start and end of a REXX script are considered clause delimiters. Also colon is a clause separator, but it is only valid after a label.

Command

Compound variable is a variable which name has at least one "." character that isn't positioned at the end of the name.

Current environment is a particular environment to which commands is routed if no explicit

environment is specified for their routing.

Current procedure level is the procedure level in effect at a certain point during execution.

Daemon Decimal digit Device driver

Digit is a single character having a numeric value associate with its glyph.

Empty string

Environment is a interface to which REXX can route commands and afterwards retrieve status information like return values.

Evaluation is the process applied to an expression in order to derive a character string.

Exposing is the binding of a variable in the current procedure level to the variable having the same name in the caller routine. This binding will be in effect for as long as the current procedure level is active.

Exponential form is a way of writing particularly large or small numbers in a fashion that makes them more readable. The number is divided into a mantissa and an exponent of base 10.

Expression is a non-empty sequence of tokens, for which there exists syntactic restrictions on which tokens can be members, and the order in which the tokens can occur. [Typically, an expression may consist of literal strings or symbols, connected by concatenation and operators.]

External data queue see "stack".

External subroutine is a script of REXX code, which is executed as a response to a subroutine or function call that is neither internal nor built-in.

FIFO

Glyph is an atomic element of text, having a meaning and an appearance; like a letter, a digit, a punctuation mark, etc.

Hex is used as a general abbreviation for term hexadecimal when used in compound words like hex digit and hex string.

Hexadecimal digit is a digit in the number system having a base of 16. The first ten digits are identical with the decimal digits (0-9), while for the last six digits, the first six letters of the Latin alphabet (A-F) are used.

Hexadecimal string is a character string that consists only of the hexadecimal digits, and with optional whitespace to divide the hexadecimal digits into groups. Leading or trailing whitespace is illegal. All groups except the first must consist of an even number of digits. If the first group have an odd number of digits, an extra leading zero is implied under some circumstances.

Instruction is a clause that is recognized by the fact that the first token is a special keyword, and that the clause is not an assignment or label. Instructions typically are well-defined REXX language components, such as loops and function calls.

Interactive trace is a trace mode, where the interpreter halts execution between each clause, and offer the user the possibility to specify arbitrary REXX statements to be executed before the execution continues.

Label LIFO

Line continuation is the comma; ',' character. When it is the last token on a line, then the end of clause implied by the end of line is ignored and the clause continues on the next line.

Literal name is a name which will always be interpreted as a constant, i.e. that no variable substitution will take place.

Literal string is a token in a REXX script, that basically is surrounded by quotation marks, in order to make a character string containing the same characters as the literal string.

Keyword is a element from finite set of symbols.

Main level Main program

Name space is a collection of named variables. In general, the expression is used when referring to the set of variables available to the program at some point during interpretation.

Nullstring is a character string having the length zero, i.e. an empty character string. [Note the difference from the undefined string.]

Operating system Parameters Parsing Procedure level

Program is a collection of REXX code, which may be zero or more scripts, or other repositories of

REXX code. However, a program must contain a all the code to be executed.

Queue see "external data queue" or "stack".

Routine is a unit during run-time, which is a procedural level. Certain settings are saved across routines. One routine (the caller routine) can be temporarily suspended while another routine is executed (the called routine). With such nesting, the called routine must be terminated before execution of the caller routine can be resumed. Normally, the CALL instruction or a function call is used to do this. Note that the main level of a REXX script is also a routine.

Script is a single file containing REXX code.

Space separated Stack

Statement is a clause having in general some action, i.e. a clause other than a null clause. [Assignments, commands and instructions are statements.]

Stem collection Stem variable Strictly order

Subkeyword is a keyword, but the prefix "sub" stresses the fact that a symbol is a keyword only in certain contexts [e.g. inside a particular instruction].

Subroutine is a routine which has been invoked from another REXX routine; i.e. it can not be the "main" program of a REXX script.

Symbol Symbol table

Tail substitution Term

Token

Token separator Uninitialized Variable name Variable symbol

Whitespace One or several consecutive blank characters.

hex literal norm. hex string

bin {digit,string,literal}

norm. bin string packed char string

Character strings is the only type of data available in REXX, but to some extent there are 'subtypes' of character strings; character strings which contents has certain format. These special formats is discussed below.

Bibliography

[KIESEL]

Peter C. Kiesel, REXX - Advanced Techniques for Programmers. McGraw-Hill, 1993, ISBN 0-07-034600-3

[CALLAWAY]

Merill Callaway, The ARexx Cookbook. 511-A Girard Blvd. SE, Albuquerque, NM 87106: Whitestone,1992, ISBN 0-9632773-0-8

[TRL2]

M. F. Cowlishaw, The REXX Language- Second Edition. Englewood Cliffs: Prentice-Hall, 1990, ISBN 0-13-780651-5

[TRL1]

M. F. Cowlishaw, The REXX Language - First Edition. Englewood Cliffs: Prentice-Hall, 1985, ISBN 0-13-780735-X

[SYMPOS3]

Proceedings of the REXX Symposium for Developers and Users. Stanford: Stanford Linear Accelerator Center, 1992

[TRH:PRICE]

Stephen G. Price, SAA Portability, chapter 37, pp 477-498. In Goldberg ans Smith III [TRH], 1992

[TRH]

Gabriel Goldberg and Smith III, Philip H., The REXX Handbook. McGraw-Hill, 1992, ISBN 0-07-023682-8

[DANEY]

Charles Daney, Programming in REXX. McGraw-Hill, 1992, ISBN 0-07-015305-1

[BMARKS]

Brian Marks, Advanced REXX programming. McGraw-Hill, 1992

[ZAMARA]

Chris Zamara and Nick Sullivan, Using ARexx on the Amiga. Abacus, 1991, ISBN 1-55755-114-6

[REXXSAA]

W. David Ashley, SAA Procedure Language REXX Reference. 5 Timberline Dr., Trophy Club, Tx 76262: Pedagogic Software, 1991

[MCGH:DICT]

Sybil P. Parker, McGrw-Hill Dictionary of Computers. McGraw-Hill, 1984, ISBN 0-07-045415-9

[PJPLAUGER]

P. J. Plauger, The Standard C Library. Englewood Cliffs: Prentice Hall, 1992, ISBN 0-13-131509-9

[KR]

Brian W. Kernighan and Dennis M. Ritchie, The C Programming Language - Second Edition. Englewood Cliffs: Prentice Hall, 1988, ISBN 0-13-110362-8

[ANSIC]

Programming languages - C., Technical Report ISO/IEC 9899:1990, ISO, Case postale 56, CH-1211 Geneve 20, Switzerland, 1990

[OX:CDICT]

Edward L. Glaser and I. C. Pyle and Valerie Illingsworth, Oxford Reference Dictionary of Computing - Third Edition. Oxford University Press, 1990, ISBN 0-19-286131-X

[ANSI]

Programming Languages - REXX. , ANSI X3.274-1996, 11 West 42nd Street, New York, New York 10036

GNU Free Documentation License

GNU Free Documentation License Version 1.1, March 2000

Copyright (C) 2000 Free Software Foundation, Inc.

59 Temple Place, Suite 330, Boston, MA 02111-1307 USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

PREAMBLE

The purpose of this License is to make a manual, textbook, or other written document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. The "Document", below, refers to any

such manual or work. Any member of the public is a licensee, and is addressed as "you".

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (For example, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, whose contents can be viewed and edited directly and straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup has been designed to thwart or discourage subsequent modification by readers is not Transparent. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML designed for human modification. Opaque formats include PostScript, PDF, proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

Last update: 2024/09/04 06:58 COPYING IN QUANTITY

If you publish printed copies of the Document numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition.

Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a publicly-accessible computer-network location containing a complete Transparent copy of the Document, free of added material, which the general network-using public has access to download anonymously at no charge using public-standard network protocols. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.

List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has less than five).

State on the Title page the name of the publisher of the Modified Version, as the publisher.

Preserve all the copyright notices of the Document.

Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.

Include, immediately after the copyright notices, a license notice giving the public permission to use

the Modified Version under the terms of this License, in the form shown in the Addendum below.

Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.

Include an unaltered copy of this License.

Preserve the section entitled "History", and its title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.

Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.

In any section entitled "Acknowledgements" or "Dedications", preserve the section's title, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.

Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.

Delete any section entitled "Endorsements". Such a section may not be included in the Modified Version.

Do not retitle any existing section as "Endorsements" or to conflict in title with any Invariant Section.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice.

These titles must be distinct from any other section titles.

You may add a section entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties–for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

COMBINING DOCUMENTS

Last update: 2024/09/04 06:58

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number.

Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections entitled "History" in the various original documents, forming one section entitled "History"; likewise combine any sections entitled "Acknowledgements", and any sections entitled "Dedications". You must delete all sections entitled "Endorsements."

COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, does not as a whole count as a Modified Version of the Document, provided no compilation copyright is claimed for the compilation. Such a compilation is called an "aggregate", and this License does not apply to the other self-contained works thus compiled with the Document, on account of their being thus compiled, if they are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one quarter of the entire aggregate, the Document's Cover Texts may be placed on covers that surround only the Document within the aggregate.

Otherwise they must appear on covers around the whole aggregate.

TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4.

Replacing Invariant Sections with translations requires special permission from their copyright

holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License provided that you also include the original English version of this License. In case of a disagreement between the translation and the original English version of this License, the original English version will prevail.

TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the

option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright © YEAR YOUR NAME.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation; with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have no Invariant Sections, write "with no Invariant Sections" instead of saying which ones are invariant. If you have no Front-Cover Texts, write "no Front-Cover Texts" instead of "Front-Cover Texts being LIST"; likewise for Back-Cover Texts.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

From:

http://ftp.osfree.org/doku/ - osFree wiki

Permanent link:

http://ftp.osfree.org/doku/doku.php?id=en:docs:os2:rexx

Last update: 2024/09/04 06:58

