



DosQVerify

This call returns the value of the verify flag.

Syntax

```
DosQVerify (VerifySetting)
```

Parameters

- VerifySetting (PUSHORT) - output : Address of the verify mode for the process.
- 00H - Verify mode is not active.
- 01H - Verify mode is active.

Return Code

```
rc (USHORT) - return
```

Return code description is:

- 0 NO_ERROR

Remarks

When verify is active, OS performs a verify operation each time it does a file write to assure proper data recording on the disk. Although disk recording errors are rare, this function has been provided for applications to verify the proper recording of critical data.

Example Code

C Binding

```
#define INCL_DOSFILEMGR  
  
USHORT rc = DosQVerify(VerifySetting);  
  
PUSHORT VerifySetting; /* Verify setting (returned) */
```

USHORT	rc;	/* return code */
--------	-----	-------------------

MASM Binding

```
EXTRN DosQVerify:Far
INCL_DOSFILEMGR EQU 1

PUSH@ WORD VerifySetting ;Verify setting (returned)
CALL DosQVerify
```

Returns WORD

Note

Text based on <http://www.edm2.com/index.php/DosQVerify>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:
<http://www.osfree.org/doku/> - osFree wiki



Permanent link:
<http://www.osfree.org/doku/doku.php?id=en:docs:fapi:dosqverify&rev=1535851544>

Last update: 2018/09/02 01:25