




Please help to find info about enries marked as *No info*


ANSICALL

This is forwarder DLL to DOSCALLS.DLL. No any real code here.

Ordinal	Entry	Desc	Status
1	AnsInject	Inject ANSI DSR output to KbdHandler buffer. Forwarder to DOSCALLS.848	Done
3	AnsInterp	ANSI Control Code Sequence interpreter. Forwarder to DOSCALLS.849	Done
2	AnsiKeydef	ANSI keyboard key reassignment. Forwarder to DOSCALLS.850	Done

OS/2 DLLs	
Base API	DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS KBDSCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS BVSCALLS NAMPIPES QUECALLS OS2CHAR
Bidirectional NLS	BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM PMBIDI
Unicode API	UCONV UNIKBD LIBUNI
BVH (Base Video Handlers)	BVHINIT BVHMPA BVHVGGA BVHVS VGA BVHWN DW
GRADD subsystem	VMAN SOFTDRAW GRE2VMAN GENGRADD
IPF (Information Presentation facility)	HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI ERRTXT
REXX	REXX REXXAPI REXXUTIL REGINA
The core PM DLL's	PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG PMCTLS PMMLE PMSPL PMVIO P PMWIN
Open32	PMWINX MIRRORS REGISTRY
Intelligent Font Interface drivers	PMATM TRUETYPE PMUNIF FREETYPE PMPRE
Data Exchange	PMCLIP PMDDE PMDDEML
VDM PM interface	PMVDMH PMVDMP SEAMLESS SHIELD
WPS	PMWP PMWPMRU PMVDDROP
Miscellaneous	PMPIC PMTKT MVDM
SOM API	SOM SOMC





2016/07/25 02:16 · prokushev · 0 Comments

From:
<http://www.osfree.org/doku/> - **osFree** wiki

Permanent link:
<http://www.osfree.org/doku/doku.php?id=en:docs:os2:modules:ansicall&rev=1469413247>

Last update: **2016/07/25 02:20**

