



Note: This IBM PC BIOS API call is for DOS/Win16 personality only. Use [Family API](#) for portability.

Note: [osFree Macro Library](#) provides macros for most of functions

2022/03/13 05:41 · prokushev · [0 Comments](#)

@Scroll

Version

IBM 5150 and higher

Brief

Scroll Screen Area Up or Down

Syntax

```
@Scroll distance, atrib, upcol, uprow, downcol, downrow
```

BIOS Interrupt

[INT10H: 06H 07H](#)

Family API

[VioScrollUpVioScrollDn](#)

Parameters

- distance (BYTE) - rows to scroll
- atrib (BYTE) - fill attribute
- upcol (BYTE) - upper left column
- uprow (BYTE) - upper left row
- downcol (BYTE) - down right column

- downrow (BYTE) - down right row

Return

| IBM PC BIOS API | |
|------------------------|---|
| Video I/O | INT 10H: 00H, 01H, 02H, 03H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0CH, 0DH, 0EH, 0FH |
| Hardware info | INT 11H, INT 12H |
| Serial I/O | INT 14H: 00H, 01H, 02H, 03H |
| Tape I/O | INT 15H: 00H, 01H, 02H, 03H |
| Keyboard I/O | INT 16H: 00H, 01H, 02H |
| Printer I/O | INT 17H: 00H, 01H, 02H |
| Disk I/O | INT 13H: 00H, 01H, 02H, 03H, 04H, 05H |
| Date and Time | INT 1AH: 00H, 01H |

| osFree Macro Library | |
|-----------------------------|--|
| Video I/O | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info | @Equipment @MemSize |
| Serial I/O | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus |
| Tape I/O | @TapeOn @TapeOff @TapeRead @TapeWrite |
| Keyboard I/O | @KbdStatus @CharIn @CharPeek |
| Printer I/O | @PrnPrint @PrnInit @PrnStatus |
| Disk I/O | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat |
| Date and Time | @SetTime @GetTime |
| Mouse | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion |
| Memory manager | @ModBlok SET_BLOCK |

2022/10/04 14:28 · prokushev · 0 Comments

2022/03/13 05:54 · prokushev · 0 Comments

From:

<http://www.osfree.org/doku/> - **osFree wiki**

Permanent link:

<http://www.osfree.org/doku/doku.php?id=en:docs:macrolib:scroll>

Last update: **2022/10/08 03:28**

