

## Errors Returned from Base OS/2 Calls

- 0 NO\_ERROR No error occurred.
- 1 ERROR\_INVALID\_FUNCTION Invalid function number.
- 2 ERROR\_FILE\_NOT\_FOUND File not found.
- 3 ERROR\_PATH\_NOT\_FOUND Path not found.
- 4 ERROR\_TOO\_MANY\_OPEN\_FILES Too many open files (no handles left).
- 5 ERROR\_ACCESS\_DENIED Access denied.
- 6 ERROR\_INVALID\_HANDLE Invalid handle.
- 7 ERROR\_ARENA\_TRASHED Memory control blocks destroyed.
- 8 ERROR\_NOT\_ENOUGH\_MEMORY Insufficient memory.
- 9 ERROR\_INVALID\_BLOCK Invalid memory-block address.
- 10 ERROR\_BAD\_ENVIRONMENT Invalid environment.
- 11 ERROR\_BAD\_FORMAT Invalid format.
- 12 ERROR\_INVALID\_ACCESS Invalid access code.
- 13 ERROR\_INVALID\_DATA Invalid data.
- 14 Reserved.
- 15 ERROR\_INVALID\_DRIVE Invalid drive specified.
- 16 ERROR\_CURRENT\_DIRECTORY Attempting to remove current directory.
- 17 ERROR\_NOT\_SAME\_DEVICE Not same device.
- 18 ERROR\_NO\_MORE\_FILES No more files.
- 19 ERROR\_WRITE\_PROTECT Attempt to write on write-protected diskette.
- 20 ERROR\_BAD\_UNIT Unknown unit.
- 21 ERROR\_NOT\_READY Drive not ready.
- 22 ERROR\_BAD\_COMMAND Unknown command.
- 23 ERROR\_CRC Data error (CRC).
- 24 ERROR\_BAD\_LENGTH Bad request structure length.
- 25 ERROR\_SEEK Seek error.

- 26 ERROR\_NOT\_DOS\_DISK Unknown media type.
- 27 ERROR\_SECTOR\_NOT\_FOUND Sector not found.
- 28 ERROR\_OUT\_OF\_PAPER Printer out of paper.
- 29 ERROR\_WRITE\_FAULT Write fault.
- 30 ERROR\_READ\_FAULT Read fault.
- 31 ERROR\_GEN\_FAILURE General failure.
- 32 ERROR\_SHARING\_VIOLATION Sharing violation.
- 33 ERROR\_LOCK\_VIOLATION Lock violation.
- 34 ERROR\_WRONG\_DISK Invalid disk change.
- 35 ERROR\_FCB\_UNAVAILABLE FCB unavailable.
- 36 ERROR\_SHARING\_BUFFER\_EXCEEDED Sharing buffer overflow.
- 37-49 Reserved.
- 50 ERROR\_NOT\_SUPPORTED Network request not supported.
- 65 Access denied.
- 73-79 Reserved.
- 80 ERROR\_FILE\_EXISTS File exists.
- 81 ERROR\_DUP\_FCB Reserved.
- 82 ERROR\_CANNOT\_MAKE Cannot make directory entry.
- 83 ERROR\_FAIL\_I24 Fail on INT 24.
- 84 ERROR\_OUT\_OF\_STRUCTURES Too many redirections.
- 85 ERROR\_ALREADY\_ASSIGNED Duplicate redirection.
- 86 ERROR\_INVALID\_PASSWORD Invalid password.
- 87 ERROR\_INVALID\_PARAMETER Invalid parameter.
- 88 ERROR\_NET\_WRITE\_FAULT Network device fault.
- 89 ERROR\_NO\_PROC\_SLOTS No process slots available.
- 90 ERROR\_NOT\_FROZEN System error.
- 91 ERR\_TSTOVFL Timer service table overflow.
- 92 ERR\_TSTDUP Timer service table duplicate.

- 93 ERROR\_NO\_ITEMS No items to work on.
- 95 ERROR\_INTERRUPT Interrupted system call.
- 99 ERROR\_DEVICE\_IN\_USE Device in use.
- 100 ERROR\_TOO\_MANY\_SEMAPHORES User/system open semaphore limit exceeded.
- 101 ERROR\_EXCL\_SEM\_ALREADY\_OWNED Exclusive semaphore already owned.
- 102 ERROR\_SEM\_IS\_SET DosCloseSem found semaphore set.
- 103 ERROR\_TOO\_MANY\_SEM\_REQUESTS Too many exclusive semaphore requests.
- 104 ERROR\_INVALID\_AT\_INTERRUPT\_TIME Operation invalid at interrupt time.
- 105 ERROR\_SEM\_OWNER\_DIED Previous semaphore owner terminated without freeing semaphore.
- 106 ERROR\_SEM\_USER\_LIMIT Semaphore limit exceeded.
- 107 ERROR\_DISK\_CHANGE Insert drive B disk into drive A.
- 108 ERROR\_DRIVE\_LOCKED Drive locked by another process.
- 109 ERROR\_BROKEN\_PIPE Write on pipe with no reader.
- 110 ERROR\_OPEN\_FAILED Open/create failed due to explicit fail command.
- 111 ERROR\_BUFFER\_OVERFLOW Buffer passed to system call too small to hold return data.
- 112 ERROR\_DISK\_FULL Not enough space on the disk.
- 113 ERROR\_NO\_MORE\_SEARCH\_HANDLES Cannot allocate another search structure and handle.
- 114 ERROR\_INVALID\_TARGET\_HANDLE Target handle in DosDupHandle invalid.
- 115 ERROR\_PROTECTION\_VIOLATION Bad user virtual address.
- 116 ERROR\_VIOKBD\_REQUEST Error on display write or keyboard read.
- 117 ERROR\_INVALID\_CATEGORY Category for DevIOCtl not defined.
- 118 ERROR\_INVALID\_VERIFY\_SWITCH Invalid value passed for verify flag.
- 119 ERROR\_BAD\_DRIVER\_LEVEL Level four driver not found.
- 120 ERROR\_CALL\_NOT\_IMPLEMENTED Invalid function called.
- 121 ERROR\_SEM\_TIMEOUT Time out occurred from semaphore API function.
- 122 ERROR\_INSUFFICIENT\_BUFFER Data buffer too small.
- 123 ERROR\_INVALID\_NAME Illegal character or bad file-system name.
- 124 ERROR\_INVALID\_LEVEL Non-implemented level for information retrieval or setting.

- 125 ERROR\_NO\_VOLUME\_LABEL No volume label found with DosQFInfo command.
- 126 ERROR\_MOD\_NOT\_FOUND Module handle not found with getprocaddr, getmodhandle.
- 127 ERROR\_PROC\_NOT\_FOUND Procedure address not found with getprocaddr.
- 128 ERROR\_WAIT\_NO\_CHILDREN DosCwait finds no children.
- 129 ERROR\_CHILD\_NOT\_COMPLETE DosCwait children not terminated.
- 130 ERROR\_DIRECT\_ACCESS\_HANDLE Handle operation invalid for direct disk-accesshandles.
- 131 ERROR\_NEGATIVE\_SEEK Attempting seek to negative offset.
- 132 ERROR\_SEEK\_ON\_DEVICE Application trying to seek on device or pipe.
- 133 ERROR\_IS\_JOIN\_TARGET Drive has previously joined drives.
- 134 ERROR\_IS\_JOINED Drive is already joined.
- 135 ERROR\_IS\_SUBSTED Drive is already substituted.
- 136 ERROR\_NOT\_JOINED Cannot delete drive that is not joined.
- 137 ERROR\_NOT\_SUBSTED Cannot delete drive that is not substituted.
- 138 ERROR\_JOIN\_TO\_JOIN Cannot join to a joined drive.
- 139 ERROR\_SUBST\_TO\_SUBST Cannot substitute to a substituted drive.
- 140 ERROR\_JOIN\_TO\_SUBST Cannot join to a substituted drive.
- 141 ERROR\_SUBST\_TO\_JOIN Cannot substitute to a joined drive.
- 142 ERROR\_BUSY\_DRIVE Specified drive is busy.
- 143 ERROR\_SAME\_DRIVE Cannot join or substitute a drive to a directory on the same drive.
- 144 ERROR\_DIR\_NOT\_ROOT Directory must be a subdirectory of the root.
- 145 ERROR\_DIR\_NOT\_EMPTY Directory must be empty to use join command.
- 146 ERROR\_IS\_SUBST\_PATH Path specified is being used in a substitute.
- 147 ERROR\_IS\_JOIN\_PATH Path specified is being used in join.
- 148 ERROR\_PATH\_BUSY Path specified is being used by another process.
- 149 ERROR\_IS\_SUBST\_TARGET Cannot join or substitute drive having directory that is target of a previous substitute.
- 150 ERROR\_SYSTEM\_TRACE System trace error.
- 151 ERROR\_INVALID\_EVENT\_COUNT DosMuxSemWait errors.

- 152 ERROR\_TOO\_MANY\_MUXWAITERS System limit of 100 entries reached.
- 153 ERROR\_INVALID\_LIST\_FORMAT Invalid list format.
- 154 ERROR\_LABEL\_TOO\_LONG Volume label too big.
- 155 ERROR\_TOO\_MANY\_TCBS Cannot create another TCB.
- 156 ERROR\_SIGNAL\_REFUSED Signal refused.
- 157 ERROR\_DISCARDED Segment is discarded.
- 158 ERROR\_NOT\_LOCKED Segment not locked.
- 159 ERROR\_BAD\_THREADID\_ADDR Bad thread-identity address.
- 160 ERROR\_BAD\_ARGUMENTS Bad environment pointer.
- 161 ERROR\_BAD\_PATHNAME Bad path name passed to exec.
- 162 ERROR\_SIGNAL\_PENDING Signal already pending.
- 163 ERROR\_UNCERTAIN\_MEDIA ERROR\_I24 mapping.
- 164 ERROR\_MAX\_THRDS\_REACHED No more process slots.
- 165 ERROR\_MONITORS\_NOT\_SUPPORTED ERROR\_I24 mapping.
- 166 ERROR\_UNC\_DRIVER\_NOT\_INSTALLED Default redir return code
- 167 ERROR\_LOCK\_FAILED Locking failed.
- 168 ERROR\_SWAPIO\_FAILED Swap IO failed.
- 169 ERROR\_SWAPIN\_FAILED Swap in failed.
- 170 ERROR\_BUSY Busy.
- 180 ERROR\_INVALID\_SEGMENT\_NUMBER Invalid segment number.
- 181 ERROR\_INVALID\_CALLGATE Invalid call gate.
- 182 ERROR\_INVALID\_ORDINAL Invalid ordinal.
- 183 ERROR\_ALREADY\_EXISTS Shared segment already exists.
- 184 ERROR\_NO\_CHILD\_PROCESS No child process to wait for.
- 185 ERROR\_CHILD\_ALIVE\_NOWAIT NoWait specified and child alive.
- 186 ERROR\_INVALID\_FLAG\_NUMBER Invalid flag number.
- 187 ERROR\_SEM\_NOT\_FOUND Semaphore does not exist.
- 188 ERROR\_INVALID\_STARTING\_CODESEG Invalid starting code segment,incorrect END (label)

directive.

189 ERROR\_INVALID\_STACKSEG Invalid stack segment.

190 ERROR\_INVALID\_MODULETYPE Invalid module type - dynamic-link library file cannot be used as an application. Application cannot be used as a dynamic-link library.

191 ERROR\_INVALID\_EXE\_SIGNATURE Invalid EXE signature - file is DOS mode program or improper program.

192 ERROR\_EXE\_MARKED\_INVALID EXE marked invalid - link detected errors when application created.

193 ERROR\_BAD\_EXE\_FORMAT Bad EXE format - file is DOS mode program or improper program.

194 ERROR\_ITERATED\_DATA\_EXCEEDS\_64K Iterated data exceeds 64KB - more than 64KB of data in one of the segments of the file.

195 ERROR\_INVALID\_MINALLOCSIZE Invalid minimum allocation size - size is specified to be less than the size of the segment data in the file.

196 ERROR\_DYNLINK\_FROM\_INVALID\_RING Dynamic link from invalid privilege level - privilege level 2 routine cannot link to dynamic-link libraries.

197 ERROR\_IOPL\_NOT\_ENABLED IOPL not enabled - IOPL set to "NO" in CONFIG.SYS.

198 ERROR\_INVALID\_SEGDPL Invalid segment descriptor privilege level - can only have privilege levels of 2 and 3.

199 ERROR\_AUTODATASEG\_EXCEEDS\_64k Automatic data segment exceeds 64KB.

200 ERROR\_RING2SEG\_MUST\_BE\_MOVABLE Privilege level 2 segment must be movable.

201 ERROR\_RELOC\_CHAIN\_XEEDS\_SEGLIM Relocation chain exceeds segment limit.

202 ERROR\_INFLOOP\_IN\_RELOC\_CHAIN Infinite loop in relocation chain segment.

203 ERROR\_ENVVAR\_NOT\_FOUND Environment variable not found.

204 ERROR\_NOT\_CURRENT\_CTRY Not current country.

205 ERROR\_NO\_SIGNAL\_SENT No signal sent - no process in the command subtree has a signal handler.

206 ERROR\_FILENAME\_EXCED\_RANGE File name or extension greater than "8.3" characters.

207 ERROR\_RING2\_STACK\_IN\_USE Privilege level 2 stack in use.

208 ERROR\_META\_EXPANSION\_TOO\_LONG Meta (global) expansion is too long.

209 ERROR\_INVALID\_SIGNAL\_NUMBER Invalid signal number.

210 ERROR\_THREAD\_1\_INACTIVE Inactive thread.

211 ERROR\_INFO\_NOT\_AVAIL File system information not available for this file.

- 212 ERROR\_LOCKED Locked error.
- 213 ERROR\_BAD\_DYNALINK Attempted to execute non-family API in DOS mode.
- 214 ERROR\_TOO\_MANY\_MODULES Too many modules.
- 215 ERROR\_NESTING\_NOT\_ALLOWED Nesting not allowed.
- 217 ERROR\_ZOMBIE\_PROCESS Zombie process.
- 218 ERROR\_STACK\_IN\_HIGH\_MEMORY Stack in high memory.
- 219 ERROR\_INVALID\_EXITROUTINE\_RING Invalid exit routine ring.
- 220 ERROR\_GETBUF\_FAILED Get buffer failed.
- 221 ERROR\_FLUSHBUF\_FAILED Flush buffer failed.
- 222 ERROR\_TRANSFER\_TOO\_LONG Transfer is too long.
- 228 ERROR\_NO\_CHILDREN No child process.
- 229 ERROR\_INVALID\_SCREEN\_GROUP Invalid session.
- 230 ERROR\_BAD\_PIPE Non-existent pipe or bad operation.
- 231 ERROR\_PIPE\_BUSY Pipe is busy.
- 232 ERROR\_NO\_DATA No data available on non-blocking read.
- 233 ERROR\_PIPE\_NOT\_CONNECTED Pipe was disconnected by server.
- 234 ERROR\_MORE\_DATA More data is available.
- 240 ERROR\_VC\_DISCONNECTED Session was dropped due to errors.
- 250 ERROR\_CIRCULARITY\_REQUESTED Renaming a directory that would cause a circularity problem.
- 251 ERROR\_DIRECTORY\_IN\_CDS Renaming a directory that is in use.
- 252 ERROR\_INVALID\_FSD\_NAME Trying to access nonexistent FSD.
- 253 ERROR\_INVALID\_PATH Bad pseudo device.
- 254 ERROR\_INVALID\_EA\_NAME Bad character in name, or bad cbName.
- 255 ERROR\_EA\_LIST\_INCONSISTENT List does not match its size, or bad EAs in list.
- 256 ERROR\_EA\_LIST\_TOO\_LONG FEAList > 64K-1 bytes.
- 257 ERROR\_NO\_META\_MATCH String doesn't match expression.
- 259 ERROR\_NO\_MORE\_ITEMS DosQFSAttach ordinal query.
- 260 ERROR\_SEARCH\_STRUC\_REUSED DOS mode findfirst/next search structure reused.

- 261 ERROR\_CHAR\_NOT\_FOUND Character not found.
- 262 ERROR\_TOO\_MUCH\_STACK Stack request exceeds system limit.
- 263 ERROR\_INVALID\_ATTR Invalid attribute.
- 264 ERROR\_INVALID\_STARTING\_RING Invalid starting ring.
- 265 ERROR\_INVALID\_DLL\_INIT\_RING Invalid DLL INIT ring.
- 266 ERROR\_CANNOT\_COPY Cannot copy.
- 267 ERROR\_DIRECTORY Used by DOSCOPY in doscall1.
- 268 ERROR\_OPLOCKED\_FILE Oplocked file.
- 269 ERROR\_OPLOCK\_THREAD\_EXISTS Oplock thread exists.
- 270 ERROR\_VOLUME\_CHANGED Volume changed.
- 271-273 Reserved.
- 274 ERROR\_ALREADY\_SHUTDOWN System already shutdown.
- 275 ERROR\_EAS\_DIDNT\_FIT EAS didnt fit.
- 303 ERROR\_INVALID\_PROCID Invalid process identity.
- 304 ERROR\_INVALID\_PDELTA Invalid priority delta.
- 305 ERROR\_NOT\_DESCENDANT Not descendant.
- 306 ERROR\_NOT\_SESSION\_MANAGER Requestor not session manager.
- 307 ERROR\_INVALID\_PCLASS Invalid P class.
- 308 ERROR\_INVALID\_SCOPE Invalid scope.
- 309 ERROR\_INVALID\_THREADID Invalid thread identity.
- 310 ERROR\_DOSSUB\_SHRINK Cannot shrink segment - DosSubSet.
- 311 ERROR\_DOSSUB\_NOMEM No memory to satisfy request - DosSubAlloc .
- 312 ERROR\_DOSSUB\_OVERLAP Overlap of specified block with an allocated memory - DosSubFree.
- 313 ERROR\_DOSSUB\_BADSIZE Bad size parameter - DosSubAlloc or DosSubFree.
- 314 ERROR\_DOSSUB\_BADFLAG Bad flag parameter - DosSubSet.
- 315 ERROR\_DOSSUB\_BADSELECTOR Invalid segment selector.
- 316 ERROR\_MR\_MSG\_TOO\_LONG Message too long for buffer.
- 317 ERROR\_MR\_MID\_NOT\_FOUND Message identity number not found.

- 318 ERROR\_MR\_UN\_ACC\_MSGF Unable to access message file.
- 319 ERROR\_MR\_INV\_MSGF\_FORMAT Invalid message file format.
- 320 ERROR\_MR\_INV\_IVCOUNT Invalid insertion variable count.
- 321 ERROR\_MR\_UN\_PERFORM Unable to perform function.
- 322 ERROR\_TS\_WAKEUP Unable to wake up.
- 323 ERROR\_TS\_SEMHANDLE Invalid system semaphore.
- 324 ERROR\_TS\_NOTIMER No timers available.
- 326 ERROR\_TS\_HANDLE Invalid timer handle.
- 327 ERROR\_TS\_DATETIME Date or time invalid.
- 328 ERROR\_SYS\_INTERNAL Internal system error.
- 329 ERROR\_QUE\_CURRENT\_NAME Current queue name does not exist.
- 330 ERROR\_QUE\_PROC\_NOT\_OWNED Current process does not own queue.
- 331 ERROR\_QUE\_PROC\_OWNED Current process owns queue.
- 332 ERROR\_QUE\_DUPLICATE Duplicate queue name.
- 333 ERROR\_QUE\_ELEMENT\_NOT\_EXIST Queue element does not exist.
- 334 ERROR\_QUE\_NO\_MEMORY Inadequate queue memory.
- 335 ERROR\_QUE\_INVALID\_NAME Invalid queue name.
- 336 ERROR\_QUE\_INVALID\_PRIORITY Invalid queue priority parameter.
- 337 ERROR\_QUE\_INVALID\_HANDLE Invalid queue handle.
- 338 ERROR\_QUE\_LINK\_NOT\_FOUND Queue link not found.
- 339 ERROR\_QUE\_MEMORY\_ERROR Queue memory error.
- 340 ERROR\_QUE\_PREV\_AT\_END Previous queue element was at end of queue.
- 341 ERROR\_QUE\_PROC\_NO\_ACCESS Process does not have access to queues.
- 342 ERROR\_QUE\_EMPTY Queue is empty.
- 343 ERROR\_QUE\_NAME\_NOT\_EXIST Queue name does not exist.
- 344 ERROR\_QUE\_NOT\_INITIALIZED Queues not initialized.
- 345 ERROR\_QUE\_UNABLE\_TO\_ACCESS Unable to access queues.
- 346 ERROR\_QUE\_UNABLE\_TO\_ADD Unable to add new queue.

- 347 ERROR\_QUE\_UNABLE\_TO\_INIT Unable to initialize queues.
- 349 ERROR\_VIO\_INVALID\_MASK Invalid function replaced.
- 350 ERROR\_VIO\_PTR Invalid pointer to parameter.
- 351 ERROR\_VIO\_APTR Invalid pointer to attribute.
- 352 ERROR\_VIO\_RPTR Invalid pointer to row.
- 353 ERROR\_VIO\_CPTR Invalid pointer to column.
- 354 ERROR\_VIO\_LPTR Invalid pointer to length.
- 355 ERROR\_VIO\_MODE Unsupported screen mode.
- 356 ERROR\_VIO\_WIDTH Invalid cursor width value.
- 357 ERROR\_VIO\_ATTR Invalid cursor attribute value.
- 358 ERROR\_VIO\_ROW Invalid row value.
- 359 ERROR\_VIO\_COL Invalid column value.
- 360 ERROR\_VIO\_TOPROW Invalid TopRow value.
- 361 ERROR\_VIO\_BOTROW Invalid BotRow value.
- 362 ERROR\_VIO\_RIGHTCOL Invalid right column value.
- 363 ERROR\_VIO\_LEFTCOL Invalid left column value.
- 364 ERROR\_SCS\_CALL Call issued by other than sm
- 365 ERROR\_SCS\_VALUE Value is not for save or restore.
- 366 ERROR\_VIO\_WAIT\_FLAG Invalid wait flag setting.
- 367 ERROR\_VIO\_UNLOCK Screen not previously locked.
- 368 ERROR\_SGS\_NOT\_SESSION\_MGR Caller not session manager.
- 369 ERROR\_SMG\_INVALID\_SGID Invalid session identity.
- 369 ERROR\_SMG\_INVALID\_SESSION\_ID Invalid session ID.
- 370 ERROR\_SMG\_NOSG No sessions available.
- 370 ERROR\_SMG\_NO\_SESSIONS No sessions available.
- 371 ERROR\_SMG\_GRP\_NOT\_FOUND Session not found.
- 371 ERROR\_SMG\_SESSION\_NOT\_FOUND Session not found.
- 372 ERROR\_SMG\_SET\_TITLE Title sent by shell or parent cannot be changed.

- 373 ERROR\_KBD\_PARAMETER Invalid parameter to keyboard.
- 374 ERROR\_KBD\_NO\_DEVICE No device.
- 375 ERROR\_KBD\_INVALID\_IOWAIT Invalid I/O wait specified.
- 376 ERROR\_KBD\_INVALID\_LENGTH Invalid length for keyboard.
- 377 ERROR\_KBD\_INVALID\_ECHO\_MASK Invalid echo mode mask.
- 378 ERROR\_KBD\_INVALID\_INPUT\_MASK Invalid input mode mask.
- 379 ERROR\_MON\_INVALID\_PARMS Invalid parameters to DosMon.
- 380 ERROR\_MON\_INVALID\_DEVNAME Invalid device name string.
- 381 ERROR\_MON\_INVALID\_HANDLE Invalid device handle.
- 382 ERROR\_MON\_BUFFER\_TOO\_SMALL Buffer too small.
- 383 ERROR\_MON\_BUFFER\_EMPTY Buffer is empty.
- 384 ERROR\_MON\_DATA\_TOO\_LARGE Data record too large.
- 385 ERROR\_MOUSE\_NO\_DEVICE Mouse device closed (invalid device handle).
- 386 ERROR\_MOUSE\_INV\_HANDLE Mouse device closed (invalid device handle).
- 387 ERROR\_MOUSE\_INV\_PARMS Parameters invalid for display mode.
- 388 ERROR\_MOUSE\_CANT\_RESET Function assigned and cannot be reset.
- 389 ERROR\_MOUSE\_DISPLAY\_PARMS Parameters invalid for display mode.
- 390 ERROR\_MOUSE\_INV\_MODULE Module not valid.
- 391 ERROR\_MOUSE\_INV\_ENTRY\_PT Entry point not valid.
- 392 ERROR\_MOUSE\_INV\_MASK Function mask invalid.
- 393 NO\_ERROR\_MOUSE\_NO\_DATA No valid data.
- 394 NO\_ERROR\_MOUSE\_PTR\_DRAWN Pointer drawn.
- 395 ERROR\_INVALID\_FREQUENCY Invalid frequency for beep.
- 396 ERROR-NLS\_NO\_COUNTRY\_FILE Cannot find COUNTRY.SYS file.
- 397 ERROR-NLS\_OPEN\_FAILED Cannot open COUNTRY.SYS file.
- 398 ERROR-NLS\_NO\_CTRY\_CODE Country code not found.
- 398 ERROR\_NO\_COUNTRY\_OR\_CODEPAGE Country code not found.
- 399 ERROR-NLS\_TABLE\_TRUNCATED Table returned information truncated, buffer too small.

- 400 ERROR\_NLS\_BAD\_TYPE Selected type does not exist.
- 401 ERROR\_NLS\_TYPE\_NOT\_FOUND Selected type not in file.
- 402 ERROR\_VIO\_SMG\_ONLY Valid from session manager only.
- 403 ERROR\_VIO\_INVALID\_ASCIIIZ Invalid ASCIIIZ length.
- 404 ERROR\_VIO\_DEREGISTER VioDeRegister not allowed.
- 405 ERROR\_VIO\_NO\_POPUP Pop-up window not allocated.
- 406 ERROR\_VIO\_EXISTING\_POPUP Pop-up window on screen (NoWait).
- 407 ERROR\_KBD\_SMG\_ONLY Valid from session manager only.
- 408 ERROR\_KBD\_INVALID\_ASCIIIZ Invalid ASCIIIZ length.
- 409 ERROR\_KBD\_INVALID\_MASK Invalid replacement mask.
- 410 ERROR\_KBD\_REGISTER KbdRegister not allowed.
- 411 ERROR\_KBD\_DEREGISTER KbdDeRegister not allowed.
- 412 ERROR\_MOUSE\_SMG\_ONLY Valid from session manager only.
- 413 ERROR\_MOUSE\_INVALID\_ASCIIIZ Invalid ASCIIIZ length.
- 414 ERROR\_MOUSE\_INVALID\_MASK Invalid replacement mask.
- 415 ERROR\_MOUSE\_REGISTER Mouse register not allowed.
- 416 ERROR\_MOUSE\_DEREGISTER Mouse deregister not allowed.
- 417 ERROR\_SMG\_BAD\_ACTION Invalid action specified.
- 418 ERROR\_SMG\_INVALID\_CALL\_INIT called more than once or invalid session identity.
- 419 ERROR\_SCS\_SG\_NOTFOUND New session number.
- 420 ERROR\_SCS\_NOT\_SHELL Caller is not shell.
- 421 ERROR\_VIO\_INVALID\_PARMS Invalid parameters passed.
- 422 ERROR\_VIO\_FUNCTION\_OWNED Save/restore already owned.
- 423 ERROR\_VIO\_RETURN Non-destruct return (undo).
- 424 ERROR\_SCS\_INVALID\_FUNCTION Caller invalid function.
- 425 ERROR\_SCS\_NOT\_SESSION\_MGR Caller not session manager.
- 426 ERROR\_VIO\_REGISTER Vio register not allowed.
- 427 ERROR\_VIO\_NO\_MODE\_THREAD No mode restore thread in SG.

- 428 ERROR\_VIO\_NO\_SAVE\_RESTORE\_THD No save/rest thread in SG.
- 429 ERROR\_VIO\_IN\_BG Function invalid in background.
- 430 ERROR\_VIO\_ILLEGAL\_DURING\_POPUP Function not allowed during pop-up window.
- 431 ERROR\_SMG\_NOT\_BASESHELL Caller is not the base shell.
- 432 ERROR\_SMG\_BAD\_STATUSREQ Invalid status requested.
- 433 ERROR\_QUE\_INVALID\_WAIT NoWait parameter out of bounds.
- 434 ERROR\_VIO\_LOCK Error returned from Scroll Lock.
- 435 ERROR\_MOUSE\_INVALID\_IOWAIT Invalid parameters for IOWait.
- 436 ERROR\_VIO\_INVALID\_HANDLE Invalid VIO handle.
- 437 ERROR\_VIO\_ILLEGAL\_DURING\_LOCK Function not allowed during screen lock.
- 438 ERROR\_VIO\_INVALID\_LENGTH Invalid VIO length.
- 439 ERROR\_KBD\_INVALID\_HANDLE Invalid KBD handle.
- 440 ERROR\_KBD\_NO\_MORE\_HANDLE Ran out of handles.
- 441 ERROR\_KBD\_CANNOT\_CREATE\_KCB Unable to create kcb.
- 442 ERROR\_KBD\_CODEPAGE\_LOAD\_INCOMPL Unsuccessful code-page load.
- 443 ERROR\_KBD\_INVALID\_CODEPAGE\_ID Invalid code-page identity.
- 444 ERROR\_KBD\_NO\_CODEPAGE\_SUPPORT No code page support.
- 445 ERROR\_KBD\_FOCUS\_REQUIRED Keyboard focus required.
- 446 ERROR\_KBD\_FOCUS\_ALREADY\_ACTIVE Calling thread has an outstanding focus.
- 447 ERROR\_KBD\_KEYBOARD\_BUSY Keyboard busy.
- 448 ERROR\_KBD\_INVALID\_CODEPAGE Invalid code page.
- 449 ERROR\_KBD\_UNABLE\_TO\_FOCUS Focus attempt failed.
- 450 ERROR\_SMG\_SESSION\_NON\_SELECT Session is not selectable.
- 451 ERROR\_SMG\_SESSION\_NOT\_FOREGRND Parent/child session not foreground.
- 452 ERROR\_SMG\_SESSION\_NOT\_PARENT Not parent of requested child.
- 453 ERROR\_SMG\_INVALID\_START\_MODE Invalid session start mode.
- 454 ERROR\_SMG\_INVALID\_RELATED\_OPT Invalid session start related option.
- 455 ERROR\_SMG\_INVALID\_BOND\_OPTION Invalid session bond option.

- 456 ERROR\_SMG\_INVALID\_SELECT\_OPT Invalid session select option.
- 457 ERROR\_SMG\_START\_IN\_BACKGROUND Session started in background.
- 458 ERROR\_SMG\_INVALID\_STOP\_OPTION Invalid session stop option.
- 459 ERROR\_SMG\_BAD\_RESERVE Reserved parameters not zero.
- 460 ERROR\_SMG\_PROCESS\_NOT\_PARENT Session parent process already exists.
- 461 ERROR\_SMG\_INVALID\_DATA\_LENGTH Invalid data length.
- 462 ERROR\_SMG\_NOT\_BOUND Parent not bound.
- 463 ERROR\_SMG\_RETRY\_SUB\_ALLOC Retry request block allocation.
- 464 ERROR\_KBD\_DETACHED This call not allowed for detached PID.
- 465 ERROR\_VIO\_DETACHED This call disallowed for detached pid.
- 466 ERROR\_MOU\_DETACHED This call disallowed for detached pid.
- 467 ERROR\_VIO\_FONT No font available to support mode.
- 468 ERROR\_VIO\_USER\_FONT User font active.
- 469 ERROR\_VIO\_BAD\_CP Invalid code page specified.
- 470 ERROR\_VIO\_NO\_CP System displays do not support code page.
- 471 ERROR\_VIO\_NA\_CP Current display does not support code page.
- 472 ERROR\_INVALID\_CODE\_PAGE Invalid code page.
- 473 ERROR\_CPLIST\_TOO\_SMALL Code page list is too small.
- 474 ERROR\_CP\_NOT\_MOVED Code page not moved.
- 475 ERROR\_MODE\_SWITCH\_INIT Mode switch initialization error.
- 476 ERROR\_CODE\_PAGE\_NOT\_FOUND Code page not found.
- 477 ERROR\_UNEXPECTED\_SLOT\_RETURNED Internal error.
- 478 ERROR\_SMG\_INVALID\_TRACE\_OPTION Invalid start session trace indicator.
- 479 ERROR\_VIO\_INTERNAL\_RESOURCE VIO internal resource error.
- 480 ERROR\_VIO\_SHELL\_INIT VIO shell initialization error.
- 481 ERROR\_SMG\_NO\_HARD\_ERRORS No session manager hard errors.
- 482 ERROR\_CP\_SWITCH\_INCOMPLETE DosSetCp unable to set KBD or VIO code page.
- 483 ERROR\_VIO\_TRANSPARENT\_POPUP Error during VIO pop-up window.

484 ERROR\_CRITSEC\_OVERFLOW Critical section overflow.

485 ERROR\_CRITSEC\_UNDERFLOW Critical section underflow.

486 ERROR\_VIO\_BAD\_RESERVE Reserved parameter is not zero.

487 ERROR\_INVALID\_ADDRESS Bad physical address.

488 ERROR\_ZERO\_SELECTORS\_REQUESTED At least one selector must be requested.

489 ERROR\_NOT\_ENOUGH\_SELECTORS\_AVA Not enough GDT selectors to satisfy request.

490 ERROR\_INVALID\_SELECTOR Not a GDT selector.

491 ERROR\_SMG\_INVALID\_PROGRAM\_TYPE Invalid program type.

492 ERROR\_SMG\_INVALID\_PGM\_CONTROL Invalid program control.

493 ERROR\_SMG\_INVALID\_INHERIT\_OPT Bad inherit option.

494 ERROR\_VIO\_EXTENDED\_SG

495 ERROR\_VIO\_NOT\_PRES\_MGR\_SG

496 ERROR\_VIO\_SHIELD\_OWNED

497 ERROR\_VIO\_NO\_MORE\_HANDLES

498 ERROR\_VIO\_SEE\_ERROR\_LOG

499 ERROR\_VIO\_ASSOCIATED\_DC

500 ERROR\_KBD\_NO\_CONSOLE

501 ERROR\_MOUSE\_NO\_CONSOLE

502 ERROR\_MOUSE\_INVALID\_HANDLE

503 ERROR\_SMG\_INVALID\_DEBUG\_PARMS

504 ERROR\_KBD\_EXTENDED\_SG

505 ERROR\_MOU\_EXTENDED\_SG

506 ERROR\_SMG\_INVALID\_ICON\_FILE

From:  
<https://www.osfree.org/doku/> - **osFree wiki**

Permanent link:  
<https://www.osfree.org/doku/doku.php?id=en:ibm:prcp:cpapi&rev=1399995266>

Last update: **2014/05/13 15:34**

